

VERITAS NetBackup™ 4.5

Troubleshooting Guide

for Windows

March 2002
30-000524-011



Disclaimer

The information contained in this publication is subject to change without notice. VERITAS Software Corporation makes no warranty of any kind with regard to this manual, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose. VERITAS Software Corporation shall not be liable for errors contained herein or for incidental or consequential damages in connection with the furnishing, performance, or use of this manual.

Copyright

Copyright © 1998 - 2002 VERITAS Software Corporation. All Rights Reserved. VERITAS, VERITAS SOFTWARE, the VERITAS logo, *Business Without Interruption*, VERITAS The Data Availability Company, VERITAS NetBackup, VERITAS NetBackup BusinessServer, VERITAS Remote Storage for Microsoft Exchange, VERITAS Storage Migrator, and VERITAS Storage Migrator Remote are trademarks or registered trademarks of VERITAS Software Corporation in the U.S. and/or other countries. Other product names mentioned herein may be trademarks or registered trademarks of their respective companies.

Portions of this software are derived from the RSA Data Security, Inc. MD5 Message-Digest Algorithm. Copyright 1991-92, RSA Data Security, Inc. Created 1991. All rights reserved.

VERITAS NetBackup Troubleshooting Guide for Windows

VERITAS Software Corporation
350 Ellis Street
Mountain View, CA 94043
USA
Phone 650-527-8000
Fax 650-527-8050
www.veritas.com

Contents

Preface	ix
Audience	ix
Organization	ix
Related Manuals	x
Accessibility	x
Conventions	x
Type Style	x
Notes and Cautions	xi
Key Combinations	xi
Command Usage	xi
Terms	xii
Getting Help	xii
Chapter 1. Introduction	1
Define the Problem	1
What was the Error Indication?	1
What Were You Trying to Do When the Problem Occurred?	2
Record All Information	2
Troubleshooting the Problem	4
Problem Report Information	5
General Information	5
Chapter 2. Troubleshooting Procedures	7
Preliminary Troubleshooting	7



Troubleshooting Installation and Configuration Problems	10
To Resolve Installation Problems	10
To Resolve Common Configuration Problems	11
To Resolve Device Configuration Problems	12
General Test and Troubleshooting Procedures	16
To Test Master Server and Clients	16
Testing Media Server and Clients	19
Resolving Network Communication Problems	21
Verifying Host Names and Services Entries	25
Using bpcntcmd	28
Host Name and Service Entry Examples	30
Example 1: Master Server and Client	30
Example 2: Master and Media Servers	32
Example 3: NetWare and Macintosh Clients	34
Example 4: Clients in Multiple Networks	36
Example 5: Server Connects to Multiple Networks	38
Using the Host Properties Window	40
Chapter 3. Using the Logs and Reports	41
Reports	43
Status for User Operations	44
Windows Event Viewer Application Logs	44
Debug Logs	44
Debug Logs on Servers	44
Debug Logs on PC Clients	46
Debug Logs on Windows and Netware Clients	46
Debug Logs on Macintosh Clients	48
Media Manager Logs	49
Windows Event Viewer Logging Option	49
To Enable the Logging Tool	50



eventlog File Entries	50
Example	51
Troubleshooting the Administration Console	51
Enabling Detailed Debug Logging	53
Chapter 4. NetBackup Status Codes and Messages	55
Status Codes	55
Messages	173
Chapter 5. Media Manager Status Codes and Messages	201
Status Codes	201
Media Manager Status Codes	201
Device Configuration Status Codes	285
Format Optical Status Codes	306
Device Management Status Codes	313
Robotic Status Codes	338
Robotic Error Codes	359
Messages	364
Chapter 6. Disaster Recovery	399
Master Server Disk Recovery	399
Recovery When Windows is Intact	399
Before Starting	400
To Recover the Master Server (Windows intact)	400
Total Recovery	402
Assumptions	403
Before Starting	403
To Recover the Master Server (total recovery)	403
Media Server Disk Recovery	405
Client System Disk Recovery - Windows	406
Assumptions	406



Before Starting	406
To Recover a Windows Client Disk	407
Recommended Backup Practices	409
Recovering the NetBackup Catalogs	409
Identifying the Most Recent Database Backup	410
Example 1: List by Using a Raw Device	410
Example 2: List by Using a Media Manager Controlled Drive	411
Example 3: List Disk Path	411
Procedures for Recovering NetBackup Catalogs	411
Before Starting	412
Recover Catalogs From Tape - Media Manager Catalogs Lost	412
Recover Catalogs from Tape - Media Manager Catalogs Intact	415
Recover Catalogs From Disk	416
Appendix A. Functional Overview	419
Backup and Restore Functional Description	419
Startup Process	420
Backup and Archive Processes	422
Backups and Archives - UNIX Clients	422
Backups and Archives - Windows 95/98 Clients	426
Backups and Archives - Windows NT/2000 Clients	427
Backups and Archives - NetWare Clients	428
Backups - Macintosh Clients	429
NetBackup Database Backups	430
Restore Processes	432
Restores - UNIX Clients	432
Restores - Windows 95/98 Clients	435
Restores - Windows NT/2000 Clients	436
Restores - NetWare Clients	437
Restores - Macintosh Clients	438



NetBackup Directories and Files	439
NetBackup Programs and Daemons	441
NetBackup Databases	450
Media Manager Functional Description	450
Startup Process	451
Media and Device Management Process	453
Barcode Operations	455
Media Requests Involving Barcodes	455
Media Manager Components	457
Media Manager Directories and Files	457
Programs and Daemons	458
Appendix B. Networks and Hostnames	467
Appendix C. Robotic Test Utilities	471
Appendix D. Backup Exec Tape Reader for NetBackup	473
Overview	473
beconv Error Messages	473
bephyinv Error Messages	476
bpimport Error Messages	477
Backup Exec File Browse	477
Backup Exec File Restore	478
Redirected Restores	479
Restoring to Windows Clients	479
Restoring to UNIX Clients	480
Restoring to Netware Clients	480
Troubleshooting with the Debug Logs	481
Backup Exec File Browse Problems	481
Examples	483
Backup Exec File Restore Problems	484



Examples	487
Glossary	493
Index	521



Preface

This guide explains how to isolate and resolve problems encountered when installing, configuring, or using VERITAS NetBackup™ for Windows. This publication refers to VERITAS NetBackup as NetBackup. This includes coverage for Media Manager, a component of NetBackup used for media and device management.

Audience

This guide is intended primarily for the system administrator who is responsible for installing, configuring, and managing NetBackup. The system administrator is assumed to have a good working knowledge of both NetBackup and Windows. Some sections will also be useful to less-technical users who encounter problems when backing up, archiving, or restoring files.

Organization

- ◆ Chapter 1, “Introduction,” explains how to define a problem and describes the information you should gather during troubleshooting. Both administrators and client users should read this chapter first.
- ◆ Chapter 2, “Troubleshooting Procedures,” includes procedures for isolating the problem to a specific area.
- ◆ Chapter 3, “Using the Logs and Reports,” discusses the NetBackup logs and how to interpret them.
- ◆ Chapter 4, “NetBackup Status Codes and Messages,” explains each NetBackup status code and provides corrective actions for error conditions.
- ◆ Chapter 5, “Media Manager Status Codes and Messages,” explains each Media Manager status code and provides corrective actions for error conditions.
- ◆ Chapter 6, “Disaster Recovery,” explains how to recover critical NetBackup information in case of a disk crash.
- ◆ Appendix A, “Functional Overview,” provides a functional overview of NetBackup and its Media Manager component, for both Windows and UNIX.



Related Manuals

- ◆ Appendix B, “Networks and Hostnames,” provides information useful when configuring NetBackup on a host with multiple network connections and when hosts have multiple names.
- ◆ Appendix C, “Robotic Test Utilities,” explains how to start the tests that are included with the robotic software.
- ◆ Appendix D, “Backup Exec Tape Reader for NetBackup,” provides troubleshooting assistance when browsing, restoring, or converting catalogs from Backup Exec media and databases.

Following the appendixes is a glossary of NetBackup terms.

Related Manuals

Refer to the *NetBackup Release Notes* for a complete list of NetBackup manuals.

Accessibility

NetBackup contains features that make the user interface easier to use by people who are visually impaired and by people who have limited dexterity. Accessibility features include:

- ◆ Support for assistive technologies such as screen readers and voice input (Windows servers only)
- ◆ Support for keyboard (mouseless) navigation using accelerator keys and mnemonic keys

For more information, see the NetBackup system administrator's guide.

Conventions

The following explains typographical and other conventions used in this guide.

Type Style

Table 1. Typographic Conventions

Typeface	Usage
Bold fixed width	Input. For example, type <code>cd</code> to change directories.



Table 1. Typographic Conventions (continued)

Typeface	Usage
Fixed width	Paths, commands, filenames, or output. For example: The default installation directory is <code>/opt/VRTSxx</code> .
<i>Italics</i>	Book titles, new terms, or used for emphasis. For example: <i>Do not</i> ignore cautions.
<i>Sans serif (italics)</i>	Placeholder text or variables. For example: Replace <i>filename</i> with the name of your file.
Serif (no italics)	Graphical user interface (GUI) objects, such as fields, menu choices, etc. For example: Enter your password in the Password field.

Notes and Cautions

Note This is a Note. Notes are used to call attention to information that makes using the product easier or helps in avoiding problems.

Caution This is a Caution. Cautions are used to warn about situations that could cause data loss.

Key Combinations

Some keyboard command sequences use two or more keys at the same time. For example, holding down the **Ctrl** key while pressing another key. Keyboard command sequences are indicated by connecting the keys with a plus sign. For example:

Press Ctrl+t

Command Usage

The following conventions are frequently used in the synopsis of command usage.

brackets []

The enclosed command line component is optional.

Vertical bar or pipe (|)

Separates optional arguments from which the user can choose. For example, when a command has the following format:

`command arg1|arg2`

the user can use either the *arg1* or *arg2* variable.



Terms

The terms listed in the table below are used in the VERITAS NetBackup documentation to increase readability while maintaining technical accuracy.

Term	Definition
Microsoft Windows, Windows	<p>Terms used as nouns to describe a line of operating systems developed by Microsoft, Inc.</p> <p>A term used as an adjective to describe a specific product or noun. Some examples are: Windows 95, Windows 98, Windows NT, Windows 2000, Windows servers, Windows clients, Windows platforms, Windows hosts, and Windows GUI.</p> <p>Where a specific Windows product is identified, then only that particular product is valid with regards to the instance in which it is being used.</p> <p>For more information on the Windows operating systems that NetBackup supports, refer to the VERITAS support web site at http://www.support.veritas.com.</p>
Windows servers	<p>A term that defines the Windows server platforms that NetBackup supports; those platforms are: Windows NT and Windows 2000.</p>
Windows clients	<p>A term that defines the Windows client platforms that NetBackup supports; those platforms are: Windows 95, 98, ME, NT, 2000, XP (for 32- and 64-bit versions), and LE.</p>

Getting Help

For updated information about this product, including system requirements, supported platforms, supported peripherals, and a list of current patches available from Technical Support, visit our web site:

<http://www.support.veritas.com/>

VERITAS Customer Support has an extensive technical support structure that enables you to contact technical support teams that are trained to answer questions to specific products. You can contact Customer Support by sending an e-mail to support@veritas.com, or by finding a product-specific phone number from the VERITAS support web site. The following steps describe how to locate the proper phone number.



1. Open <http://www.support.veritas.com/> in your web browser.
2. Click **Contact Support**. The *Contacting Support Product List* page appears.
3. Select a product line and then a product from the lists that appear. The page will refresh with a list of technical support phone numbers that are specific to the product you just selected.





Introduction

1

This chapter explains the basic steps to take if you encounter a problem while using NetBackup. Other chapters provide more specific information.

Note The term *media server*, as distinct from *master server* or *server*, may or may not apply to the NetBackup BusinessServer product and depends on the context. When troubleshooting a BusinessServer installation, be aware that there is only one host. - the master and media server are one and the same. References to a media server on a different host can be ignored.

Define the Problem

The first step in troubleshooting is to define the problem.

What was the Error Indication?

In defining the problem, you must know what went wrong and sometimes resolving the problem also requires that you also know what went right.

Error messages are usually the vehicle for telling you something went wrong. So the first thing to do is look for an error message. If you don't see an error message in an interface, but still suspect a problem, check the reports and logs. NetBackup provides extensive reporting and logging facilities and these can provide an error message that points you directly to a solution.

The logs also show you what went right and what NetBackup was doing when the problem occurred. For example, a restore can be waiting for media to be mounted and the required media is currently in use for another backup.

The "Using the Logs and Reports" chapter describes the log information that NetBackup provides. The "NetBackup Status Codes and Messages" and "Media Manager Status Codes and Messages" chapters provide interpretations of NetBackup (and Media Manager) status codes and messages.



What Were You Trying to Do When the Problem Occurred?

Another important part of defining the problem is to clearly define what you were trying to do in the first place.

Some questions to ask here are:

- ◆ What operation was being attempted?
- ◆ What method were you using? For example, there is more than one way to install software on a client. There is also more than one possible interface to use for many operations and some operations can even be performed with a script.
- ◆ What type of server platform and operating system was involved?
- ◆ If your site uses both master and media servers, was it a master or a media server?
- ◆ If a client was involved, what type of client was it?
- ◆ Have you ever performed the operation successfully in the past? If so, what is different now?
- ◆ What is the service pack level?
- ◆ Are you using operating system software with the latest fixes supplied, especially those required for use with NetBackup?
- ◆ Is your device firmware at a level, or higher than the level, at which it has been tested according to the posted device compatibility lists?

Record All Information

As you define and troubleshoot a problem, always try to capture potentially valuable information, such as:

- ◆ NetBackup progress logs
- ◆ NetBackup Reports
- ◆ NetBackup debug logs
- ◆ Media Manager debug logs
- ◆ Error or status messages in dialogs
- ◆ Check for error or status information in the Event Viewer Application log

Record this information for each attempt. A benefit of this approach is that you can compare the results of multiple attempts. It is also useful for others at your site and for customer support in the event that you cannot solve the problem yourself.

The “Using the Logs and Reports” chapter explains the various logs.



If your troubleshooting attempt is unsuccessful, customer support can provide further assistance. Before calling, have the following information ready.

- ◆ Product, platform, and device information:
 - ◆ Product and its release level.
 - ◆ Server hardware type and operating system level.
 - ◆ Client hardware type and operating system level, if a client is involved.
 - ◆ Storage units being used, if it is possible that storage units are involved.
 - ◆ If it looks like a device problem, be ready to supply device information, such as the types of robots and drives, and their version levels along with Media Manager and system configuration information.
 - ◆ Software patches to the products that were installed.
 - ◆ Service packs and hotfixes that were installed.
- ◆ What is the definition of the problem as described earlier in this chapter? Copies of logs or core dumps (if any) can also be required.
- ◆ Have you had this problem before? If so, was there a successful resolution and what did you try that time?
- ◆ Has the configuration been changed recently and, if so, what was changed?
- ◆ If necessary, can you communicate with technical support through `ftp`, email, or fax? This can be useful for sending things such as copies of logs.

“Problem Report Information” on page 5 lists the information you need and also provides methods for gathering information.



Troubleshooting the Problem

After defining the problem, use the information in the other chapters of this manual to try and correct it.

- ◆ When you have a status code or message, proceed directly to “NetBackup Status Codes and Messages” or “Media Manager Status Codes and Messages” and try the corrective actions recommended there.
- ◆ When you do not see a status code or message, or the actions in “NetBackup Status Codes and Messages” or “Media Manager Status Codes and Messages” do not solve the problem, try the troubleshooting procedures in the “Troubleshooting Procedures” chapter. Those procedures describe an effective approach for isolating common problems.

If you don't find the solution, obtain assistance by contacting customer support.



Problem Report Information

General Information

Date: _____

Servers (master and media):

Platform Types and Host Names	OS Levels	Product Version and Patch Levels
-------------------------------	-----------	----------------------------------

Clients:

Platform Types and Host Names	OS Levels	Product Version and Patch Levels
-------------------------------	-----------	----------------------------------

Devices:

Robotic Library and Drive Models	Firmware Levels	Firmware Level Listed as “Tested” in the VERITAS Device Compatibility Lists at www.support.veritas.com
----------------------------------	-----------------	---



Problem Report Information

What were you attempting when the problem occurred? (for example, a backup on a Windows client)

What were the error indications? (for example, status code, error dialog box)

Did this occur during or shortly after any of the following:

- ☐ Initial Installation
- ☐ Configuration change (explain)
- ☐ System change or problem (explain)
- ☐ Have you seen the problem before: (if so, what did you do that time)

Logs or other failure data you have saved:

- ☐ All log entries report
- ☐ Media Manager debug logs
- ☐ NetBackup debug logs
- ☐ Event Viewer Application logs (Windows)

Can you communicate with us through any of the following:

- ☐ ftp
- ☐ telnet
- ☐ email
- ☐ fax



Troubleshooting Procedures

2

This chapter has procedures for finding the cause of NetBackup errors. These procedures are general in nature and do not attempt to cover every problem that could occur. They do, however, recommend methods that usually result in successful problem resolution.

When performing these procedures, try each step in sequence. If you have already performed the action or it does not apply, skip to the next step. If it branches you to another chapter, use the solutions suggested there. If you still have a problem, go to the next step in the procedure. Also, alter your approach based on your specific configuration and what you have already tried.

There are three troubleshooting procedures:

- ◆ Preliminary Troubleshooting
- ◆ Troubleshooting Installation and Configuration Problems
- ◆ General Test and Troubleshooting Procedures

Start with “Preliminary Troubleshooting.” This explains what to check first and then branches off to other procedures as appropriate. “Troubleshooting Installation and Configuration Problems” applies specifically to installation and configuration problems. “General Test and Troubleshooting Procedures” defines general methods for finding server and client problems and should be used last.

Note The term *media server*, as distinct from *master server* or *server*, does not apply to the NetBackup BusinessServer product. When troubleshooting a BusinessServer installation, please ignore any references to media server.

Preliminary Troubleshooting

If you are having problems with NetBackup, perform this procedure first.



1. Ensure that your servers and clients are running supported operating system versions and the peripherals you are using (if any) are supported. See the NetBackup release notes and the NetBackup device compatibility lists on www.veritas.com for this information.

2. Check for status codes or messages.

- a. Use the All Log Entries report and check for NetBackup errors for the appropriate time period. This report can show the context in which the error occurred and can often provide specific information that is useful when the status code can result from a variety of problems.

If the problem involved a backup or archive, check the Backup Status report. This report gives you the status code.

If you find a status code or message in either of the above reports, go to the chapter titled “NetBackup Status Codes and Messages” or “Media Manager Status Codes and Messages” and perform the recommended corrective actions.

- b. If the problem pertains to media or device management and either NetBackup does not provide a status code or you cannot correct the problem by following the instructions in “NetBackup Status Codes and Messages” or “Media Manager Status Codes and Messages”, check the Event Viewer Application log. This log can show the context in which the error occurred and the error messages are usually descriptive enough to point you to a problem area.

- c. Check applicable debug logs that are enabled and correct problems you detect.

If these logs are not enabled, enable them before retrying the failed operation (see the “Using the Logs and Reports” chapter).

- d. If you performed corrective actions, retry the operation. If you did not perform corrective actions or the problem persists, go to step 3 below.

3. If you encountered the problem:

- ◆ During a new installation
- ◆ During an upgrade installation
- ◆ After making changes to an existing configuration

Then, go to “Troubleshooting Installation and Configuration Problems” on page 10.

4. Ensure that the server and client are operational.

Verify there is enough space available in the disk partitions that NetBackup uses. If one or more of these partitions is full, NetBackup processes that access the full partition will fail. The resulting error message depends on the process but you could see messages such as “unable to access” or “unable to create or open a file.”

Check the following disk partitions:

- ◆ The partition where NetBackup software is installed (by default, C:\Program Files\VERITAS).
- ◆ On the NetBackup master or media server, the partition where the NetBackup (or Media Manager) databases reside (by default, C:\Program Files\VERITAS).
- ◆ The partition where the NetBackup processes write temporary files.
- ◆ The partition where NetBackup logs are stored (by default, C:\Program Files\VERITAS\NetBackup\logs).
- ◆ The partition where the operating system is installed.

Use Disk Administrator or Explorer to view disk partition information.

5. Enable verbose logging either for everything or just for areas you think are related to the problem. See the “Using the Logs and Reports” chapter for information on verbose logging.

Note If you are using ACS robotic control, the `acsssi` and `acssel` processes will remain running when `ltid` is stopped. For more information about stopping these daemons, refer to the Automated Cartridge System (ACS) Appendix in the *NetBackup Media Manager System Administrator's Guide*.

6. On Windows NetBackup servers, verify that the required services and processes are running:
 - a. Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to start the following services if they are not running:

Note To start all of them, execute `install_path\NetBackup\bin\bpup.exe`.

On NetBackup master servers:

- ◆ NetBackup Request Manager service
- ◆ NetBackup Database Manager service
- ◆ NetBackup Device Manager service (if the system has devices configured)
- ◆ NetBackup Volume Manager service
- ◆ NetBackup Client service



On NetBackup media servers:

- ◆ NetBackup Device Manager service (if the system has devices configured)
- ◆ NetBackup Volume Manager service
- ◆ NetBackup Client service

On NetBackup clients (including NetBackup Remote Administration Consoles)

- ◆ NetBackup Client service

- b. Use the NetBackup Activity Monitor to see if the following Media Manager processes are running:

- ◆ `avrd` (automatic volume recognition)
- ◆ Processes for all configured robots (see the *Media Manager System Administrator's Guide for Windows*)

If the above processes are not running, stop and then restart the NetBackup Device Manager service by using the NetBackup Activity Monitor or the Services application in the Windows Control Panel.

7. If you had to start any of the processes or services in the previous steps, retry the operation. If they are running or the problem persists, go to “General Test and Troubleshooting Procedures” on page 16.

If you cannot start any of these processes or services, check the appropriate debug logs (see the “Using the Logs and Reports” chapter) for NetBackup problems.

When started, these processes and services continue to run unless you stop them manually or there is a problem with the system.

Troubleshooting Installation and Configuration Problems

To Resolve Installation Problems

Note Before you install or use NetBackup on a Linux (RedHat/SuSE) client, verify that the `inetd` (or `xinetd`) service is started on that machine. This will ensure proper communication between the NetBackup master and the Linux (RedHat/SuSE) client.

1. Could you install the software on the master and media servers by using the release media?

Some reasons for failure could be:



- ◆ Not logged in as an Administrator (you must have permission to install services on the system)
 - ◆ Permission denied (ensure you have permission to use the device and to write the directories and files being installed)
 - ◆ Bad media (contact customer support)
 - ◆ Defective drive (replace the drive or refer to vendor's hardware documentation)
 - ◆ Improperly configured drive (refer to system and vendor documentation)
2. Could you install NetBackup client software on the clients?
 3. For general network communications problems, go to "Resolving Network Communication Problems" on page 21.

To Resolve Common Configuration Problems

If this is an initial installation or if you have changed the configuration, check for these problems before proceeding:

1. Check for the following device configuration problems:
 - ◆ Configuration for robotic drive does not specify the robot.
 - ◆ Drive is configured as wrong type or density.
 - ◆ Incorrect Robotic Drive Number.
 - ◆ SCSI ID for the robotic control is specified instead of the logical Robot Number assigned to the robot.
 - ◆ The same robot number is used for different robots.
 - ◆ SCSI ID for the drive is specified instead of a unique Drive Index number.
 - ◆ A platform does not support a device or was not configured to recognize it.
2. Check for the following problems with the services:
 - ◆ Services do not start during reboot (configure system so this occurs).
 - ◆ Configuration was changed while services were running.
 - ◆ The `%SystemRoot%\System32\drivers\etc\services` file does not have an entry for `vmd`, `bprd`, `bpdbm` and `bpcd`. Also, ensure there are entries for the processes for configured robots (see the *Media Manager System Administrator's Guide for Windows* for a list of these processes).



3. If you found and corrected any configuration problems, retry the operation and check for NetBackup status codes or messages.

- a. Check the All Log Entries report for NetBackup errors for the appropriate time period. This report can show the context in which the error occurred and can often have specific information that is useful when the error can result from a variety of problems.

If the problem involved a backup or archive, check the Backup Status report. This report gives you the status code.

If you find a status code or message in either the Backup Status or All Log Entries report, go to the “NetBackup Status Codes and Messages” chapter or “Media Manager Status Codes and Messages” chapter and perform the recommended corrective actions.

- b. If the problem pertains to device or media management and either NetBackup does not provide a status code or you cannot correct the problem by following the instructions in status codes chapters, check the Event Viewer Application log for NetBackup entries.

- c. Check appropriate debug logs that are enabled and correct problems you detect.

If these logs are not enabled, enable them before your next attempt. For more information, see the “Using the Logs and Reports” chapter.

- d. If you performed corrective actions as a result of step a through step c, retry the operation. If you did not perform corrective actions or the problem persists, go to the next section, “General Test and Troubleshooting Procedures.”

To Resolve Device Configuration Problems

Certain auto-configuration warning messages are displayed in the second panel of the Device Configuration wizard if the selected device meets any of the following conditions:

- ◆ Not licensed for NetBackup BusinessServer
- ◆ Exceeds a license restriction
- ◆ Has inherent qualities that make it difficult to auto-configure

These are the messages relating to device configuration, along with explanations and recommended actions:

Message: Drive does not support serialization

Explanation: The drive does not return its serial number. Note that some manufacturers do not support serial numbers. Although automatic device configuration will not function optimally, the drive can be manually configured and operated without its serial number.

Recommended Action: Ask the manufacturer for a newer firmware version that returns serial numbers (if available), or manually configure and operate the drive without a serial number.

Message: Robot does not support serialization

Explanation: The robot does not return its serial number or the serial numbers of the drives contained within it. Note that some manufacturers do not support serial numbers. Although automatic device configuration will not function optimally, the robot and/or drives can be manually configured and operated without serial numbers.

Recommended Action: Ask the manufacturer for a newer firmware version that returns serial numbers (if available), or manually configure and operate the robot and/or drives without serial numbers.

Message: Too many drives in robot

Explanation: The robotic library has more than two installed drives—the maximum allowed with a NetBackup BusinessServer license.

Recommended Action: Remove all but two drives.

Message: Too many slots in robot

Explanation: The robotic library has more than 30 installed slots—the maximum allowed with a NetBackup BusinessServer license.

Recommended Action: If possible, configure the robotic library to have 30 or fewer slots. Only use robotic libraries that are supported with NetBackup BusinessServer.

Message: No license for this robot type

Explanation: The robotic type defined for this robot is not supported by NetBackup BusinessServer.

Recommended Action: Define a different robot. Only use robotic libraries that are supported with NetBackup BusinessServer.

Message: No license for this drive type

Explanation: The drive type defined for this drive is not supported by NetBackup BusinessServer.

Recommended Action: Define a different drive. Only use drives that are supported by NetBackup.



Message: Unable to determine robot type

Explanation: The robotic library is not recognized by NetBackup. The robotic library cannot be auto-configured.

Recommended Action:

1. Download a new external-robot-mapping file from the VERITAS support web site, and try again.
2. Configure the robotic library manually.
3. Use only robotic libraries that are supported by NetBackup.

Message: Drive is standalone or in unknown robot

Explanation: Either the drive is standalone, or the drive or robot is not returning a serial number. Note that some manufacturers do not support serial numbers. Although automatic device configuration will not function optimally, the drive or robot can be manually configured and operated without a serial number.

Recommended Action: Ask the manufacturer for a newer firmware version that returns serial numbers (if available), or manually configure and operate the drive/robot without serial numbers.

Message: Robot drive number is unknown

Explanation: Either the drive or robot is not returning a serial number. Note that some manufacturers do not support serial numbers. Although automatic device configuration will not function optimally, the drive or robot can be manually configured and operated without a serial number.

Recommended Action: Ask the manufacturer for a newer firmware version that returns serial numbers (if available), or manually configure and operate the drive/robot without serial numbers.

Message: Drive exceeds drive limit

Explanation: The NetBackup BusinessServer license allows a maximum of two drives and two drives have already been configured.

Recommended Action: To use this drive, a previously configured drive must be disabled (deleted from the device configuration).

Message: Robot exceeds robot limit

Explanation: A robotic library has already been configured.

Recommended Action: To use this robot, a previously configured robot must be disabled (deleted from the device configuration).

Message: Drive is in an unlicensed robot

Explanation: The drive is in a robotic library that cannot be licensed for the NetBackup BusinessServer. Since the robot cannot be licensed for NetBackup BusinessServer, any drives configured in that robot are unusable.

Recommended Action: Configure a drive that does not reside in the unlicensed robot.

Message: Drive's scsi adapter does not support pass-thru (or pass-thru path does not exist)

Explanation: A drive was found that does not have a SCSI pass-through path configured. There are two possible causes for this message:

- ◆ The drive is connected to an adapter that does not support SCSI pass-through.
- ◆ The pass-through path for this drive has not been defined.

Recommended Action: Change the drive's adapter, or define a pass-through path for the drive. See the *Media Manager Device Configuration Guide for UNIX* for scsi adapter pass-through information.

Message: No configuration device file exists

Explanation: A device has been detected without the corresponding device file necessary to configure that device.

Recommended Action: Refer to the chapter for your system type in the *Media Manager Device Configuration Guide for UNIX* for information on creating device files.

Message: Unable to determine drive type

Explanation: The drive is not recognized by NetBackup BusinessServer. The drive cannot be auto-configured.

Recommended Action:

1. Download a new external-drive-mapping file from the VERITAS support web site, and try again.
2. Configure the drive manually.
3. Use only drives that are supported by NetBackup.

Message: Unable to determine compression device file



Explanation: A drive has been detected without the expected compression device file used to configure that device. Automatic device configuration attempts to use a device file that supports hardware data compression. When multiple compression device files exist for a drive, automatic device configuration cannot determine which compression device file is best. It uses a non-compression device file instead.

Recommended Action: If you do not need hardware data compression, no action is necessary. The drive can be operated without hardware data compression. If you need hardware data compression, refer to the chapter for your system type in the *Media Manager Device Configuration Guide for UNIX* for information on configuring tape drives.

General Test and Troubleshooting Procedures

If the “Preliminary Troubleshooting” or “Troubleshooting Installation and Configuration Problems” procedures did not reveal the problem, perform the following procedures, skipping those steps that you have already performed.

The procedures assume that the software was successfully installed, but not necessarily configured correctly. If NetBackup or Media Manager has never worked properly, there are probably configuration problems. Repeat the checks mentioned in the “Troubleshooting Installation and Configuration Problems” procedure when you encounter errors. In particular, look for device configuration problems.

You may also want to perform each backup and restore twice. Perform them first as a user that is a member of the Administrators group and then as a user that is not a member of the Administrator group. In all cases, ensure that you have read and write permissions on the test files.

To Test Master Server and Clients

1. Enable appropriate debug logs on the master server (see the “Using the Logs and Reports” chapter). If you do not know which logs apply, enable them all until you solve the problem. Delete the debug log directories when you have resolved the problem.
2. Configure a test policy (set backup window to be open while you are testing). Name the master server as the client and a storage unit that is on the master server (preferably a nonrobotic drive). Also, configure a volume in the NetBackup volume pool and insert the volume in the drive. If you don’t label the volume by using the `bplabel` command, NetBackup automatically assigns a previously unused media ID.
3. Verify that the NetBackup services are running on the master server:

Use the NetBackup Activity Monitor or the Services application in the Windows Control Panel.

4. Start a manual backup of a policy by using the manual backup option in the NetBackup administration interface. Then, restore the backup.

This verifies:

- ◆ NetBackup server software is functional, including all services, programs, and databases.
- ◆ Media Manager can mount the media and use the drive you configured.

If a failure occurs, first check the NetBackup All Log Entries report. For failures relating to drives or media, verify that the drive is in an UP state and the hardware is functioning.

To further isolate the problem, use the debug logs.

If the debug logs do not reveal the problem, check the following:

- ◆ Event Viewer System logs
- ◆ Event Viewer Application logs
- ◆ vmd debug logs on the volume database host for the device
- ◆ bptm debug logs

See the vendor manuals for information on hardware failures.

If you are using a robot and this is an initial configuration, verify that the robotic drive is configured correctly. In particular, verify that:

- ◆ The same robot number is used both in the Media Manager and storage unit configurations.
- ◆ Each robot has a unique robot number.

5. If you previously configured a nonrobotic drive and your system includes a robot, change your test policy now to specify a robot. Add a volume to the robot. The volume must be in the NetBackup volume pool on the volume database host for the robot.

Repeat this procedure starting with step 3, but this time for the robot. This verifies that Media Manager can find the volume, mount it, and use the robotic drive.

If you have difficulties with the robot, try the test utilities described in the “Robotic Test Utilities” appendix.



Note Do not use the Robotic Test Utilities when backups or restores are active. These utilities prevent the corresponding robotic processes from performing robotic actions, such as loading and unloading media. This can cause media mount timeouts and prevent other robotic operations like robotic inventory and inject/eject from working.

6. Add a user schedule to your test policy (the backup window must be open while you are testing). Use a storage unit and media that has been verified in previous steps.
7. Start a user backup and restore of a file by using the client-user interface on the master server. Monitor the status log for the operation. If successful, this operation verifies that client software is functional on the master server.

If a failure occurs, check the NetBackup All Log Entries report. To further isolate the problem, check the appropriate debug logs from those listed below. The “Using the Logs and Reports” chapter explains which logs apply to specific client software.

Note These logs exist only if you enabled debug logging in step 1. The debug logs are in the *install_path\NetBackup\logs*directory.

- ◆ bpbkar
 - ◆ bpcd
 - ◆ bprd
 - ◆ nbwin
 - ◆ bpinetd
8. Reconfigure your test policy to name a client that is located elsewhere in the network. Use a storage unit and media that has been verified in previous steps. If necessary, install the NetBackup client software.
 9. Create debug log directories for the processes listed below. The “Using the Logs and Reports” chapter explains which logs apply to specific client types.
 - ◆ bprd on the server
 - ◆ bpcd on the client
 - ◆ bpbkar on the client
 - ◆ nbwin on the client
 - ◆ bpinetd
 10. Perform a user backup and then a restore from the client specified in step 8.

This verifies:

- ◆ Communications between the client and master server
- ◆ NetBackup software on the client

If an error occurs, check the following:

- ◆ All Log Entries report
- ◆ Debug logs created in the previous step

A likely cause for errors is a communications problem between the server and the client.

11. When the test policy operates satisfactorily, repeat specific steps as necessary to verify other clients and storage units.
12. When all clients and storage units are functional, test the remaining policies and schedules that use storage units on the master server. If a scheduled backup fails, check the All Log Entries report for errors, then follow the actions suggested in the status codes chapters.

Testing Media Server and Clients

If you are using media servers, verify their operation as explained in the following steps. Before proceeding, eliminate all problems on the master server by completing “To Test Master Server and Clients” on page 16.

1. Enable appropriate debug logs on the servers (see the “Using the Logs and Reports” chapter). If you are uncertain which logs apply, enable them all until you solve the problem. Delete the debug log directories when you have resolved the problem.
2. Configure a test policy with a user schedule (set the backup window to be open while you are testing).
 - ◆ Name the media server as the client and a storage unit that is on the media server (preferably a nonrobotic drive).
 - ◆ Add a volume on the volume database host for the devices in the storage unit (master server is recommended for the volume database host). Ensure the volume is in the NetBackup volume pool.
 - ◆ Insert the volume in the drive. If you do not prelabel the volume by using the `bplabel` command, NetBackup automatically assigns a previously unused media ID.
3. Verify that all NetBackup services are running on the master and media servers.



To perform this check, use the Activity Monitor or the Services application in the Windows Control Panel.

4. Perform a user backup and then a restore of a file. Perform these operations from a client that has been verified to work with the master server.

This test verifies:

- ◆ NetBackup media server software
- ◆ Media Manager on the media server can mount the media and use the drive that you configured
- ◆ Communications between the master server process `bpsched` and media server processes `bpcd` and `bpbrm`
- ◆ Communications between media server process `bpbrm` and client processes `bpcd` and `bpbkarr`

For failures relating to drives or media, ensure that the drive is in an UP state and the hardware is functioning.

If you suspect a communications problem between the master and media servers, check the debug logs for the involved processes. If the debug logs don't help you, check the following:

- ◆ Event Viewer Application log
- ◆ `vmd` debug logs

See the vendor manuals for information on hardware failures.

If you are using a robot and this is an initial configuration, verify that the robotic drive is configured correctly. In particular, verify that:

- ◆ The same robot number is used both in the Media Manager and storage unit configurations.
- ◆ Each robot has a unique robot number.

5. If you previously configured a nonrobotic drive and a robot attached to your media server, change the test policy to name the robot. Also, add a volume for the robot to the volume database host for the robot. Verify that the volume is in the NetBackup volume pool and in the robot.

Then, repeat this procedure starting with step 3, this time for a robot. This verifies that Media Manager can find the volume, mount it, and use the robotic drive.

If a failure occurs, check the NetBackup All Log Entries report. Look for errors relating to devices or media. If the All Log Entries report doesn't help, check:

- ◆ `vmd` debug logs on the volume database host for the robot

◆ Event Viewer Application log

In an initial configuration, verify that the robotic drive is configured correctly. Do not use a robot number that is already configured on another server.

Try the test utilities described in the “Robotic Test Utilities” appendix.

Note Do not use the Robotic Test Utilities when backups or restores are active. These utilities prevent the corresponding robotic processes from performing robotic actions, such as loading and unloading media. This can cause media mount timeouts and prevent other robotic operations like robotic inventory and inject/eject from working.

6. When the test policy operates satisfactorily, repeat specific steps as necessary to verify other clients and storage units.
7. When all clients and storage units are working, test the remaining policies and schedules that use storage units on the media server. If a scheduled backup fails, check the All Log Entries report for errors, then follow the actions suggested in the status codes chapters.

Resolving Network Communication Problems

The following procedure is for resolving NetBackup communications problems, such as those associated with NetBackup status codes 54, 57, and 58.

Note In all cases, ensure that your network configuration is working correctly outside of NetBackup before trying to resolve NetBackup problems.

1. Before retrying the failed operation:
 - ◆ Increase the logging level on the client (see the user’s guide for the client).
 - ◆ On the NetBackup server, create a `bprd` debug log directory and on the clients create a `bpcd` debug log.
 - ◆ On the NetBackup server, set the Verbose level to 1 on the Troubleshooting tab in the NetBackup Client Properties dialog. To display this dialog, start the Backup, Archive, and Restore interface and click NetBackup Client Properties on the File menu (also see “Using the Host Properties Window” on page 40).
2. If this is a new client, verify the client and server names in your NetBackup configuration as explained in “Verifying Host Names and Services Entries” on page 25.



3. Verify basic network connectivity between client and server by pinging from the server to the client and from the client to the server. Use the following command:

ping *hostname*

Where *hostname* is the name of the host as configured in:

- ◆ NetBackup policy configuration
- ◆ WINS
- ◆ DNS (if applicable).
- ◆ *hosts* file in the system directory:

%SystemRoot%\system32\drivers\etc\hosts (Windows NT/2000)

C:\Windows\hosts (default on Windows 98 and 95)

If ping succeeds in all instances, it verifies basic connectivity between the server and client.

If ping fails, you have a network problem outside of NetBackup that must be resolved before proceeding. As a first step, verify the workstation is turned on, as this is a common source of connection problems with PC workstations.

4. On Microsoft Windows or NetWare clients, check the NetBackup Client service:
 - a. Ensure that the service is active, either by checking the logs (see step b) or as follows:
 - ◆ On Windows NT/2000 clients, use the Services application in the Control Panel to verify that the NetBackup Client service is running and start it if necessary.
 - ◆ On Windows 98 or 95 clients, check the system tray on the taskbar for the NetBackup client icon. If the icon is not there, run the NetBackup Client Job Tracker program from the NetBackup Program folder or the Start menu. When the icon is present, right-click on the icon to start the NetBackup client daemon.
 - ◆ On NetWare clients, enter `load bpcd` from the NetWare server console to start the NetBackup client daemon.
 - b. Check the `bpcd` debug logs for problems or errors. See “Using the Logs and Reports” chapter for instructions on enabling and using these logs.
 - c. Verify that the same NetBackup client Service (`bpcd`) port number is specified on both the NetBackup client and server (by default, 13782).



- ◆ On Microsoft Windows, check the NetBackup Client Service Port number on the Network tab in the NetBackup Client Properties dialog. To display this dialog, start the Backup, Archive, and Restore interface on the client and click NetBackup Client Properties on the File menu.

Verify that the setting on the Network tab matches the one in the services file. The services file is located in:

%SystemRoot%\system32\drivers\etc\services (Windows NT/2000)

C:\Windows\services (Windows 98 and 95)

The values on the Network tab are written to the services file when the NetBackup Client service starts.

- ◆ On NetWare clients, see the BPCD setting in the `openv\netback\bp.ini` file.
- ◆ Or, instead of the first bullet under step c, above: On Windows NetBackup servers, see the Client Properties dialog box in the Configure - NetBackup window (see “Using the Host Properties Window” on page 40).

Correct the port number if necessary. Then, on Windows clients and servers, stop and restart the NetBackup Client service. On Microsoft Windows 98 or 95 and NetWare clients, stop and restart the NetBackup client daemon (`bpcd`).

Note Do not change NetBackup port assignments unless it is absolutely necessary in order to resolve conflicts with other applications. If you do change them, do so on all NetBackup clients and servers. These numbers must be the same throughout your NetBackup configuration.

5. Verify that the NetBackup Request Service (`bprd`) Port number on Microsoft Windows and NetWare clients is the same as on the server (by default, 13720).
 - ◆ On Microsoft Windows clients (use the same method as in step c under step 4).
 - ◆ On NetWare clients, see the BPRD setting in the `openv\netback\bp.ini` file.
 - ◆ Or, instead of the first bullet: On Windows NetBackup servers, set these numbers in the Client Properties dialog box in the Configure - NetBackup window (see “Using the Host Properties Window” on page 40).
6. On a Macintosh client, check NetBackup configuration settings as follows:



- a. Ensure that `NetBackUpListen` and `NetBackupBPCD` are in the Extensions folder.
- b. Check `log.mmddyy` in the `Preferences:NetBackup:Logs:inetd` folder to see if `NetBackUpListen` is running and if it reported any errors.
- c. Check `log.mmddyy` in the `Preferences:NetBackup:Logs:bpcd` folder to see if `NetBackupBPCD` was started and if it reported any errors.
- d. If `NetBackUpListen` or `NetBackupBPCD` are not running, try rebooting the Macintosh. If that does not work, reinstall the software.
- e. Ensure that `bpcd` port number (`portnum` in the `Preferences:NetBackup:mac.conf` file) is the same as on the server (by default, 13782).

On Windows NetBackup servers, check the NetBackup Client Service Port number on the Network tab in the NetBackup Client Properties dialog. To display this dialog box, start the Backup, Archive, and Restore interface on the server and click NetBackup Client Properties on the File menu.

Also verify that the setting on the Network tab matches the one in the services file. The `services` file is located in:

```
%SystemRoot%\system32\drivers\etc\services
```

Correct the port number, if necessary, and reboot the Macintosh.

- f. Verify that the NetBackup request daemon (`bprd`) port number is the same as on the server (by default, 13720).
 - ◆ On the client, this is the `bprdport` setting in the `mac.conf` file, in the NetBackup folder in the Preferences folder.
 - ◆ On a Windows NetBackup server, check the NetBackup Request Service Port number on the Network tab in the NetBackup Client Properties dialog. To display this dialog box, start the Backup, Archive, and Restore interface on the server and click NetBackup Client Properties on the File menu.
- g. Ensure that other values in `mac.conf` are correct and also check the `bp.conf` file. Both files are in the Netbackup folder in the Preferences folder.

If you make changes to `mac.conf` or `bp.conf`, reboot the Macintosh.

7. Verify that the `hosts` file or its equivalent contains the NetBackup server name. On Windows clients, the `hosts` files are:
 - ◆ `%SystemRoot%\system32\drivers\etc\hosts` (Windows NT/2000)



- ◆ C:\Windows\hosts (Windows 98 or 95)
 - ◆ NetWare clients: SYS:etc\hosts
8. Verify client-to-server connectability by using `ping` or its equivalent from the client (step 3 verified the server-to-client connection).
 9. If the client's TCP/IP transport allows `telnet` and `ftp` from the server, try these as additional connectivity checks.
 10. For a Macintosh or NetWare client, ensure that the server is not trying to connect when a backup or restore is already in progress on the client. Attempting more than one job at a time on these clients, results in a "can't connect" or similar error.
 11. Use the `bpcIntcmd` utility to verify basic client to master server communications. When run on a NetBackup client, the `-pn` and `-sv` options initiate inquiries to the NetBackup master server (as configured in the server list on the client). The master server then returns information to the requesting client. For more information, see "Using `bpcIntcmd`" on page 28.
 12. Verify that the client operating system is one of those supported by the client software.

Verifying Host Names and Services Entries

This procedure is useful if you encounter problems with host names or network connections and want to verify that the NetBackup configuration is correct. Several examples follow the procedure.

Note For more information on host names, refer to the "Networks and Hostnames" appendix in this manual and to the "Rules for Using Host Names in NetBackup" appendix in the *NetBackup System Administrator's Guide*.

1. Verify that the correct client and server host names are configured in NetBackup.
 - a. On Windows servers, Windows clients and NetWare nontarget clients, check the General tab in the NetBackup Client Properties dialog and the Servers tab in the Specify NetBackup Machines dialog box. To display these dialog boxes, start the Backup, Archive, and Restore interface on the client. For the General tab, click NetBackup Client Properties on the File menu; for the Servers tab, click Specify NetBackup Machines on the File menu.
 - ◆ On the Servers tab, ensure that there is a server entry for the master server and each media server.



The correct server must be designated as the current master server in the list.

If you add or modify server entries on the master server, stop and restart the NetBackup Request service and NetBackup Database Manager services.

- ◆ On the General tab, verify that the client name setting is correct and matches what is in the policy client list on the master server.
- ◆ On a master or media server, ensure there is a server entry for each Windows administrative client that can be used to administer that server.

You can also make the above changes on the appropriate tabs in the properties dialog boxes on a Windows NetBackup server (see “Using the Host Properties Window” on page 40).

- b. On Macintosh clients, check the server and client name entries in the `bp.conf` file:
 - ◆ Ensure there is a `SERVER` entry for the master server and each media server in the configuration. The master server must be the first name in the list.
 - ◆ Ensure that the `CLIENT_NAME` option (if included) is correct and matches what is in the policy client list on the master server.

The `bp.conf` file is in the NetBackup folder of the Preferences folder on Macintosh clients.

- c. On NetWare clients, check the `openv\netback\bp.ini` file to ensure that:
 - ◆ There is a `SERVER` entry for the master server and each media server in the configuration. The master server must be the first name in the list.
 - ◆ The `ClientName` entry and the entries in the `[clients]` section are correct and match what is in the policy client list on the master server.

- d. On the master server, verify that you have created any required

`install_path\NetBackup\db\altnames` files

Pay particular attention to requirements for `host.xlate` file entries.

2. Verify that each server and client has the required entries for NetBackup reserved port numbers.

Note The examples following this procedure show the default port numbers. Do not change NetBackup port assignments unless it is absolutely necessary in order to resolve conflicts with other applications. If you do change them, do so on all NetBackup clients and servers. These numbers must be the same throughout your NetBackup configuration.

- a. On NetBackup servers, check the `services` file to ensure that they have entries for:

- ◆ `bpcd` and `bprd`
- ◆ `vmd`
- ◆ `bpdbm`
- ◆ Processes for configured robots (for example, `tl8cd`). See the *Media Manager System Administrator's Guide for Windows* for a list of these processes.

On Windows, the `services` file is

`%SystemRoot%\system32\drivers\etc\services`.

- b. On Windows and NetWare clients, verify the NetBackup Client and NetBackup Request service port numbers.

- ◆ On Microsoft Windows clients, verify that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Client Properties dialog match the settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface on the client and click NetBackup Client Properties on the File menu.

The values on the Network tab are written to the `services` file when the NetBackup Client service starts.

The `services` file is located in:

`%SystemRoot%\system32\drivers\etc\services` (Windows NT/2000)

`C:\Windows\services` (Windows 98 and 95)

- ◆ On NetWare clients, check the `BPCD` and `BPRD` entries in the `openv\netback\bp.ini` file.

- c. On Macintosh clients, check the `mac.conf` file in the NetBackup folder in the Preferences folder to ensure that it has the correct `portnum` and `bprdport` entries.

3. On Windows servers and clients, verify that the NetBackup Client service is running.
4. WINS or DNS host name information must correspond to what is in the policy configuration and the name entries in the following:
 - ◆ On Windows NetBackup servers, Microsoft Windows clients, and NetWare nontarget clients, check the General tab in the NetBackup Client Properties dialog and the Servers tab in the Specify NetBackup Machines dialog. To display these



dialogs, start the Backup, Archive, and Restore interface on the client. For the General tab, click NetBackup Client Properties on the File menu; for Servers tab, click Specify NetBackup Machines on the File menu.

- ◆ The `bp.conf` file on Macintosh clients.
- ◆ The `openv\netback\bp.ini` file on NetWare clients.

Also, verify that reverse DNS addressing is configured.

5. To confirm the setup of the IP addresses and hostnames in DNS and (or) local hosts files on each NetBackup node, use the NetBackup `bpcIntcmd` utility.

Using `bpcIntcmd`

The `bpcIntcmd` utility resolves IP addresses into host names and host names into IP addresses by using the same system calls as the NetBackup application software. The command that starts the utility is located in the following directory:

install_path\NetBackup\bin

Run it in an MSDOS command window so you can see the results.

`bpcIntcmd` options that are useful for testing the functionality of the host name and IP address resolution are `-ip`, `-hn`, `-sv` and `-pn`. The following topics explain each of these options:

`bpcIntcmd -ip IP_Address`

The `-ip` option allows you to specify an IP address. `bpcIntcmd` uses `gethostbyaddr()` on the NetBackup node and `gethostbyaddr()` returns the host name with the IP address as defined in the node's DNS, WINS, or local hosts file entries. No connection is established with the NetBackup server.

`bpcIntcmd -hn Hostname`

The `-hn` option allows you to specify a host name. `bpcIntcmd` uses `gethostbyname()` on the NetBackup node to obtain the IP address associated with the host name defined in the node's DNS, WINS, or local hosts file entries. No connection is established with the NetBackup server.

You can use the `-ip` and `-hn` options to verify the ability of a NetBackup node to resolve the IP addresses and host names of other NetBackup nodes. For example, you can verify that a NetBackup server can connect to a client. In this case, the steps are:

1. On the NetBackup server, use `bpcclntcmd -hn` to verify that the operating system can resolve the host name of the NetBackup client (as configured in the client list for the policy) to an IP address. The IP address is then used in the node's routing tables to route a network message from the NetBackup server.
2. On the NetBackup client, use `bpcclntcmd -ip` to verify that the operating system can resolve the IP address of the NetBackup server (the IP address is in the message that arrives at the client's network interface).

bpcclntcmd -pn

When run on a NetBackup client, the `-pn` option initiates an inquiry to the NetBackup master server, and the server then returns information to the requesting client. First, `bpcclntcmd` identifies the server to which it is making the request (Current Server in the server list), then it displays the information that the server returns.

For example:

```
bpcclntcmd -pn
expecting response from server rabbit.friendlyanimals.com
dove.friendlyanimals.com dove 123.145.167.3 57141
```

Where:

- ◆ `expecting response from server rabbit.friendlyanimals.com` is the master server entry from the server list on the client.
- ◆ `dove.friendlyanimals.com` is the connection name (peername) returned by the master server. The master server obtained this name through `gethostbyaddress()`.
- ◆ `dove` is the client name configured in the NetBackup policy client list.
- ◆ `123.145.167.3` is the IP address of the client connection at the master server.
- ◆ `57141` is the port number of the connection on the client.

bpcclntcmd -sv

The `-sv` option displays the NetBackup version number on the master server.




Host Name and Service Entry Examples

Example 1: Master Server and Client

The example network in the following figure shows a Windows NT/2000 master server with one Windows NT/2000 client.



Example 1: Windows NT/2000 Master Server and Client



- Notes:
1. The NetBackup Client Properties dialog also has a Network tab with “NetBackup client service port (BPCD)” and “NetBackup request service port (BPRD)” settings that must be the same as the bpcd and bprd settings in the services file.
 2. The complete path to the Windows NT/2000 \etc\services file is:
%SystemRoot%\system32\drivers\etc\services
 3. All other applicable network configuration must also be updated to reflect the NetBackup information. For example, this could include the
%SystemRoot%\system32\drivers\etc\hosts file and also WIN and DNS (if used).




Example 2: Master and Media Servers

The network in this example (see the next figure) is the same as the previous one except that it includes a NetBackup media server named saturn. The difference to note is the addition of a server list for saturn on all the systems. Jupiter is designated as the master.



Example 2: Windows NT/2000 Master and Media Servers



- Notes:
1. The NetBackup Client Properties dialog also has a Network tab with "NetBackup client service port (BPCD)" and "NetBackup request service port (BPRD)" settings that must be the same as the bpcd and bprd settings in the services file.
 2. The complete path to the Windows NT/2000 \etc\services file is:
 %SystemRoot%\system32\drivers\etc\services
 3. All other applicable network configuration must also be updated to reflect the NetBackup information. For example, this could include the
 %SystemRoot%\system32\drivers\etc\hosts file and also WIN and DNS (if used).



Example 3: NetWare and Macintosh Clients


The network in the next figure shows a NetBackup master server with NetWare and Macintosh clients.

Note the following about this configuration:

- ◆ The server configuration is the same as with for other clients.
- ◆ Configuration entries on the Macintosh client are in the `mac.conf` and `bp.conf` files.
- ◆ Configuration entries on the NetWare client are in the `openv\netback\bp.ini` file.



Example 3: PC Clients




- Notes:
1. The NetBackup Client Properties dialog also has a Network tab with “NetBackup client service port (BPCD)” and “NetBackup request service port (BPRD)” settings that must be the same as the bpcd and bprd settings in the services file.
 2. The complete path to the Windows NT/2000 \etc\services file is:
%SystemRoot%\system32\drivers\etc\services
 3. All other applicable network configuration must also be updated to reflect the NetBackup information. For example, this could include the
%SystemRoot%\system32\drivers\etc\hosts file and also WIN and DNS (if used).



Example 4: Clients in Multiple Networks

The network in this example shows a client (mars/meteor) that is a router to clients in another network. The client's host name on the master server side is mars and the host name presented to the client pluto is meteor.

Example 4: Clients in Multiple Networks



- Notes:
1. The NetBackup Client Properties dialog also has a Network tab with "NetBackup client service port (BPCD)" and "NetBackup request service port (BPRD)" settings that must be the same as the bpcd and bprd settings in the services file.
 2. The complete path to the Windows NT/2000 \etc\services file is:
 %SystemRoot%\system32\drivers\etc\services
 3. All other applicable network configuration must also be updated to reflect the NetBackup information. For example, this could include the
 %SystemRoot%\system32\drivers\etc\hosts file and also WIN and DNS (if used).

First, we examine the configuration of the router system. The NetBackup policy client list shows this system as mars because that is the name of the interface to the master server. There is no special configuration to note other than the client name setting. This name must be set to mars, because this is the name that the master server recognizes.

The second client, pluto, is also configured no differently than if it were in the same network as the master server. Assuming that all the standard networking files (for example, hosts, DNS, WINS, and routing tables) are set up correctly, all the required network connections can be made.

There would be a problem, however, with restoring files from pluto if the mars/meteor system were a type of router that hides the name of the originating host when it routes requests between the two networks. A router between an Ethernet and a token ring network exhibits this behavior.

To illustrate what occurs, assume that pluto is on FDDI (token ring) and the server is on Ethernet. If a user on pluto starts a restore, the router could use the name of its network interface to pluto (meteor) as the peername when it forwards the request to the server. The server interprets the request as coming from a host named meteor and does not allow the restore because meteor is not in the client list.

To resolve this problem, the administrator creates an `altnames` directory on the master server and adds a file for meteor to that directory.

On a Windows NT/2000 NetBackup server, the file is:

```
install_path\NetBackup\db\altnames\meteor
```

Then, the administrator adds the following line to this file:

```
pluto
```

The master server now recognizes, as legitimate, restore requests that show a peername of meteor and client name of pluto. Refer to the *NetBackup System Administrator's Guide for Windows* for more information on `altnames` configuration.

Regardless of the type of router, the configuration for the media server, saturn, is still the same as in example 2. If a media server is involved in a backup or restore for pluto, the master server provides the correct peername and client name for the media server to use in establishing connections.



Example 5: Server Connects to Multiple Networks

The network in this example (see the next figure) shows a NetBackup server (jupiter/meteor) that has two Ethernet connections and clients in both networks. The server's hostname is mars on one network and meteor on the other.

The first thing to note about this configuration is that the NetBackup policy client list specifies jupiter as the client name for the master server. The list could show either jupiter or meteor but not both.

Another important item to note is the configuration of the NetBackup server list.

The NetBackup server list on the master server has entries for both jupiter and meteor. The reason for both names is that when the server does a backup, it uses the name associated with the client it is backing up. For example, it uses the meteor interface when backing up pluto and the jupiter interface when backing up mars. The current server entry (master server name) is jupiter because that is the name used to back up the client on the master server.


The NetBackup server list for the other systems also have entries for both the jupiter and meteor interfaces. This is recommended in order to keep the server entries the same on all clients and servers in the configuration. It would be adequate to list only the master-server name for the local network interface to the client system or media server (for example, meteor for pluto).

For the network shown, the differences mentioned for the policy client list and the server list is the only unique configuration required. Assuming that all the standard networking files (for example, the hosts file, WINS, DNS, and routing tables) are set up correctly, all required network connections can be made.

If the master server system is a type of router that hides the name of the originating host when routing requests between networks, you see the same type of restore problem discussed in example 4. For example, if pluto were on FDDI (token ring), the master server would use meteor as the peername when it forwarded the request to NetBackup. NetBackup would then interpret the request as coming from a host named meteor, which was not in the client list, and the restore would fail.

The solution, in this case, is also identical to that discussed in "Example 4: Clients in Multiple Networks" on page 36.

Example 5: Server Connects to Multiple Networks



- Notes:
1. The NetBackup Client Properties dialog also has a Network tab with "NetBackup client service port (BPCD)" and "NetBackup request service port (BPRD)" settings that must be the same as the bpcd and bprd settings in the services file.
 2. The complete path to the Windows NT/2000 \etc\services file is:
%SystemRoot%\system32\drivers\etc\services
 3. All other applicable network configuration must also be updated to reflect the NetBackup information. For example, this could include the
%SystemRoot%\system32\drivers\etc\hosts file and also WIN and DNS (if used).



Using the Host Properties Window

Note Available only in the NetBackup Administration Console for Windows.

The Host Properties window in the NetBackup Administration console on Windows provides access to many configuration settings for NetBackup clients and servers. For example, you can modify the server list, e-mail notification settings, and various timeout values for servers and clients. The following are general instructions for using this window. For more information, see the online help or the *NetBackup System Administrator's Guide for Windows*.

1. Start the NetBackup Administration interface on a Windows server or on a NetBackup Remote Administration Console.
2. Click Host Properties.
3. Select the servers or clients where you want to make the change.
4. Select Properties from the Actions menu.
5. In the properties dialog box that appears, select the appropriate tab and make your change.

Many procedures in this guide also refer to the NetBackup Client Properties dialog in the Backup, Archive, and Restore interface on Microsoft Windows clients. This dialog lets you change NetBackup configuration settings only for the local system where you are running the interface. Most settings in the NetBackup Client Properties dialog are also available in the Host Properties window.

Using the Logs and Reports

3

NetBackup produces the following categories of information that you can use for troubleshooting problems.

- ◆ Reports
- ◆ Status for User Operations
- ◆ Windows Event Viewer Application Logs
- ◆ Debug Logs
- ◆ Media Manager Logs
- ◆ Windows Event Viewer Logging Option
- ◆ Troubleshooting the Administration Console


Note The format of the entries in the NetBackup logs is subject to change without notice.

The following figure shows whether this information is available on the client or server and the processes involved in making the information available. The remaining topics in this chapter describe the reports and logs shown on the figure.

See Appendix A for more information on the programs and daemons mentioned in this figure and elsewhere in this chapter.



Note The term *media server*, as distinct from *master server* or *server*, does not apply to the NetBackup BusinessServer product. When troubleshooting a BusinessServer installation, please ignore any references to media server in this guide.



Reports

NetBackup provides a set of standard reports that gives you most of the status and error information you need. To run these reports, use the NetBackup administration interface (see the *NetBackup System Administrator's Guide* for instructions). The following table provides a brief description of the reports.

Table 2. NetBackup Reports

Report	Description
Status of Backups	Status and error information on backups and archives completed within the specified time period.
Media Reports	Provides the following reports about the media: <ul style="list-style-type: none"> ◆ Media Lists - Shows information about volumes that NetBackup has used for backups or archives. This report does not show information for disk storage units. ◆ Media Contents - Lists the backup IDs that are on a single volume. The information is read directly from the media. This report does not show information for disk storage units. ◆ Images on Media - Shows the contents of media as recorded in the NetBackup file database. This report shows information for any type of storage unit, including disk. ◆ Media Logs- Lists the media errors that have been recorded. This information is a subset of the All Log Entries report. ◆ Media Summary - Summarizes active and nonactive volumes and groups them according to expiration date. The report shows the expiration date and the number of volumes that are at each retention level. ◆ Media Written - Identifies volumes that have been used for backups or archives within the specified time period. This report does not show media used for image duplication if the original image was created prior to the specified time period.
Client Backups	Detailed information on backups and archives completed within the specified time period.
Problems with Backups	Problems that the server has logged during the specified time period. This information is a subset of the information in the All Log Entries report.
All Log Entries	All log entries for the specified time period.



Status for User Operations

NetBackup allows you to view status on the progress of user operations. See the NetBackup user guides for instructions

Windows Event Viewer Application Logs

On Windows, the NetBackup services and programs log information to the Event Viewer Application log. Look for messages pertaining to NetBackup in these logs.

Debug Logs

If a problem requires more information than is available through the normal logs and reports, you can enable debug logs that show detailed information about specific processes. To enable debug logging for a process, create a directory for its logs as explained in the following topics. Each process creates logs in its own logging directory. The logs that are available depend on whether the system is a server or a client.

Debug Logs on Servers

Note Refer to the *Media Manager Logs* section for enabling Media Manager debug log entries.

To enable debug logging on NetBackup servers, create the appropriate directories under:

install_path\NetBackup\logs

The table below lists the debug log directories that apply to servers. When these directories exist, NetBackup creates log files in the directory for the associated process.

On a Windows server, you can create all of the NetBackup debug log directories at once by running the following batch file:

To create all of the NetBackup debug log directories at once on a master or media server, run the following batch file:

install_path\NetBackup\Logs\mklogdir.bat

Note Media servers have only the bpbrm, bpcd, bpdm, and bptm debug logs.

Table 3. NetBackup Server Debug Logs

Debug Log Directory	Associated Process
admin	Administrative commands.
bpbrm	NetBackup backup and restore manager.
bpcd	NetBackup client manager. This process is started by the NetBackup Client service.
bpdbjobs	NetBackup jobs database manager program.
bpdm	NetBackup disk manager.
bpdbm	NetBackup database manager. This process runs only on master servers. It is the NetBackup Database Manager service.
bprd	NetBackup request manager. This process is the NetBackup Request Manager service.
bpsched	NetBackup backup scheduler. This process runs only on master servers.
bptm	NetBackup tape management process.
symlogs	System log.
user_ops	The user_ops directory is created during the install of NetBackup on all servers and clients. The NetBackup Java interface programs use it for temporary files and for job and progress log files generated by the user backup, archive, and restore program (jbpSA). This directory must exist for successful operation of any of the Java programs and must have public read, write and execute permissions. user_ops will contain a directory for every user that is using the Java programs.

The following is a list of facts to be familiar with before using debug logs:

- ◆ NetBackup retains debug logs for the number of days you specify with the Duration to Retain Logs global attribute (28 days by default) and then deletes them. For instructions on changing Duration to Retain Logs, see the *NetBackup System Administrator's Guide for Windows*.
- ◆ Debug logs can grow very large. Enable them only if unexplained problems exist and delete both the logs and the associated directory when they are no longer needed.
- ◆ Each debug log is kept in a separate subdirectory under:

install_path\NetBackup\Logs

Debug logging takes place only if you create the subdirectory where the process can store its logs.



Debug Logs

- ◆ A process creates one debug log file per day.

On Windows, the file names created are of the form:

mmddyy.log

For example:

040198.log

- ◆ A debug log file is created when the process begins. Therefore, you must create the directory for a debug log before the process starts.

To increase the amount of information that processes write in the logs, set the Verbose level to 1 or more on the Troubleshooting tab of the NetBackup Client Properties dialog. To open this dialog box, start the Backup, Archive, and Restore interface and click NetBackup Client Properties on the File menu.

Debug Logs on PC Clients

Debug Logs on Windows and Netware Clients

To enable detailed debug logging on Microsoft Windows or NetWare target clients, create the appropriate directories in the following locations:

Note These are the default locations in which to place these directories. You can specify another location during client installation (see the user guide for the respective client).

- ◆ Windows clients - C:\Program Files\VERITAS\NetBackup\Logs\
- ◆ NetWare clients - SYS:\OPENV\NETBACK\LOGS\

The following table lists the debug log directories that apply to the above clients:

Table 4. PC Client Debug Logs

Debug Log Directory	NetBackup Client	Associated Process
bp	NetWare target	Client-user interface program for NetWare.
bpinetd	Windows NT/2000	Client service logs. These logs have information on the bpinetd32 process.
bparchive	Windows NT/2000, 98, 95	Archive program that is run from the command line.

Table 4. PC Client Debug Logs

Debug Log Directory	NetBackup Client	Associated Process
bpbbackup	Windows NT/2000, 98, 95	Backup program that is run from the command line.
bpbkar	Windows NT/2000	Backup and archive manager. These logs have information on the bpbkar32 process.
bpcd	All Windows and NetWare clients	NetBackup client manager. These logs have information on communications between the server and client. On NetWare and Windows 98 and 95 clients, these logs also contain the log information for the backup and restore processes.
bplist	Windows NT/2000, 98, 95	List program that is run from the command line.
bpmount	Windows NT/2000, 98, 95	Program used to collect drive names on the client for multistreaming clients.
bprestore	Windows NT/2000, 98, 95	Restore program that is run from the command line.
bpsrv	NetWare nontarget	NetBackup service utility. This program allows the system with the user interface to communicate with the NetBackup for NetWare client.
nbwin	Windows 98, 95	Client-user interface program for Windows 98/95.
nbwin	Windows NT/2000	Client-user interface program for Windows NT/2000.
tar	Windows NT/2000	tar process. These logs have information about the tar32 process.
user_ops	Windows NT/2000, 98, 95	See Table 3.

Before using the debug logs, note the following:

- ◆ For Windows clients, logs are kept for the number of days specified in the Backup, Archive, and Restore interface, under the File menu, NetBackup Client Properties, General tab: “Keep status of user-directed backups, archives, and restores for.” For NetWare clients, logs are kept the number of days specified in file `openv\netback\bp.ini` (under `Keep_Log_Days`).

The currently active logs have names of the form:



Debug Logs

mmddyy.log

For example, 120198.log.

- ◆ You can increase the amount of information that processes write in the logs.
 - ◆ On Windows clients, set the debug level on the TroubleShooting tab of the NetBackup Client Properties dialog. For instructions, see the NetBackup user guide for the client.
 - ◆ On NetWare clients, change the value of the `level` and `tcp` parameters in the debug section of the `bp.ini` file. For instructions, see the NetBackup user guide for the client.

Note Increasing the log level can cause the logs to grow very large, so take this action only if unexplained problems exist.

Debug Logs on Macintosh Clients

There are two types of debug logs on Macintosh clients:

- ◆ `bpcd` logs, which are located in the `Preferences:NetBackup:Logs:bpcd` folder. These logs have information on NetBackupBPCD, which controls communications between the server and the client.
- ◆ `inetd` logs, which are located in the `Preferences:NetBackup:Logs:bpcd` folder. These logs have information on NetBackupListen.

NetBackupBPCD and NetBackupListen each create one debug log file per day. The file names for these log files are of the form:

log.mmddyy

For example:

log.110899

To increase the amount of information that these processes write in the logs, change the value of the `loglevel` parameter in the `mac.conf` file in the NetBackup folder. Increasing the log level can cause these logs to grow very large, so take this action only if unexplained problems exist.

NetBackup retains Macintosh debug logs for the number of days you specify with the `logexpire` parameter in the `mac.conf` file in the NetBackup folder. The default is seven days.

For more on changing the `loglevel` or the `logexpire` value, see the *NetBackup User's Guide for Macintosh*.

Media Manager Logs

On Windows, Media Manager records robotic and drive errors in the Event Viewer Application log. Log entries are also made when drives change between the UP and DOWN states.

If a problem requires more information, increase the level of logging to the Event Viewer Application log by adding a VERBOSE entry to the following file:

```
install_path\Volmgr\vm.conf
```

In addition, you can enable debug logging for the NetBackup Volume Manager service by creating the following directories:

```
install_path\Volmgr\debug\daemon
```

(Debug information on the service)

```
install_path\Volmgr\debug\reqlib
```

(Debug information on the process requesting the service)

```
install_path\Volmgr\debug\tpcommand
```

(Debug information on the tpconfig and tpautoconf commands)

```
install_path\Volmgr\debug\ltid
```

(Debug information on ltid)

NetBackup creates one log per day in each of the above debug directories with file names of the form:

```
mmddy.log
```

For example:

```
110894.log
```

To disable debug logging for the NetBackup Volume Manager service, either delete or rename the directories.

Windows Event Viewer Logging Option

NetBackup Windows master servers can be configured so messages from NetBackup reports are written to the Windows Event Viewer Application Log. This allows you to see these messages in the Application Log and also to use third party tools to monitor the Application Log for these messages.



To Enable the Logging Tool

1. Create the following file on the NetBackup master server:

install_path\NetBackup\db\config\eventlog

2. Add an entry (optional) to the `eventlog` file that specifies the severity and type of NetBackup messages that are written. The following is an example:

56 255

The next topic explains the format of the entry. If you do not add an entry, a default value is used, which is also explained in the next topic.

eventlog File Entries

The `eventlog` entry has two parameters:

- ◆ The first parameter controls which messages NetBackup writes to the Application Log, based on severity level.
- ◆ The second parameter controls which type of messages NetBackup writes to the Application Log.

Both parameters are specified as decimal numbers and equate to a bitmap that expresses the values below:

Severity:

1 = Unknown

2 = Debug

4 = Info

8 = Warning

16 = Error

32 = Critical

Type:

1 = Unknown

2 = General

4 = Backup

8 = Archive

16 = Retrieve

32 = Security

64 = Backup Status

128 = Media Device

- ◆ If the file is empty, the default severity is Error (16) and the default type is Backup Status (64).
- ◆ If the file has only one parameter, it is used for the severity level and the default value of Backup Status (64) is used for the type.

Example

Assume you want to include all types of messages that have severity levels of warning, error, and critical. In this instance, the entry is:

56 255

Where:

56 = severity= the sum of warning, error, and critical (8 + 16 + 32)

255 = type = the sum of all types (1 + 2 + 4 + 8 + 16 + 32 + 64 + 128)

The following is an example of a message written in the Windows Event Viewer Application Log:

```
16 4 10797 cacao bush bpsched backup of client bush exited with status
71
```

The meaning of each field is as follows (left to right):

severity - 16 (Error)

type - 4 (Backup)

jobid - 10797

server - cacao

client - bush

process - bpsched

text - backup of client bush exited with status 71

Troubleshooting the Administration Console

Most errors that occur in the NetBackup (Java) Administration Console appear in an attention dialog. Those that appear elsewhere are Java exception errors (which are not documented in this guide); they may appear in the status line (bottom) of the NetBackup Administration window, or in the log file that contains `stdout` or `stderr` messages written by Java APIs or by the NetBackup Administration Console.



The following are the four kinds of error messages seen in the NetBackup Administration Console.

- ◆ NetBackup status codes and messages as documented in Chapter 4.

Operations performed in the Administration Console can result in errors recognized in other parts of NetBackup. These errors usually appear exactly as documented in Chapter 4.

Note The error message is not always accompanied by a status code. You can find the status code by looking up the message in the alphabetical listing at the end of Chapter 4. Then use the status code to find the full description of the message in the first half of Chapter 4.

- ◆ NetBackup Administration Console: application server status codes and messages as documented in Chapter 4.

These messages have status codes in the 500 range. Messages with status codes 500, 501, 502, 503 and 504 begin with "Unable to login, status:". Messages with status codes 511 and 512 may or may not begin with "Unable to login, status:".

The message is not always accompanied by a status code (see the above note).

- ◆ Java exceptions

These are generated by either the Java APIs or by NetBackup Administration APIs. These messages begin with the name of the exception. For example:

```
java.lang.ClassCastException
```

or

```
vrts.nbu.NBUCommandExecutionException
```

Java exceptions usually appear in one of three places:

- ◆ In the status line (bottom) of the NetBackup Administration window
- ◆ In the log file generated by the `jnbSA` or `jbpSA` commands
- ◆ When set up, in the output file of the Windows Display Console `.bat` file (see "Enabling Detailed Debug Logging" below, for more detail)
- ◆ Operating system errors

Messages that do not match those documented in this manual are probably operating system errors.

Enabling Detailed Debug Logging

The NetBackup Administration Console is a suite of client-server applications that allow administration of remote NetBackup servers. All administration is accomplished via the *application server* of the NetBackup Administration Console. This application server is made up of an authentication service and a user service.

The login request from the login dialog is sent to the authentication service for validation. The user name and password have to be valid in the Windows/UNIX authentication files/process.

After validation, the authentication service starts a user service under the user's account. Thereafter, all NetBackup administrative tasks are performed through that instance of the user service.

On both UNIX and Windows, the authentication service is the `bpjava-msvc` application and the user service is the `bpjava-usvc` application.

Some of the recommendations in Chapter 4 refer to enabling detailed debug logging and examining log files. These are the instructions for this activity.

1. On the NetBackup client (*) or server specified in the login dialog, create the `bpjava-msvc` and `bpjava-usvc` debug log directories in the `/usr/openv/netbackup/logs` directory (UNIX) or in `install_path\NetBackup\logs` (Windows). Refer to Debug Logs earlier in this chapter for more information.

Note The NetBackup Java application server runs only on NetBackup UNIX clients. On Windows, the NetBackup Java application server runs only on NetBackup master servers.

2. On the UNIX machine where you execute the `jnbSA` or `jbpSA` commands, add the following line to the `Launch.properties` or `JBPSimple.properties` file, respectively, in the `/usr/openv/java` directory.

```
debugLevel=2
```

The log file name is displayed in the xterm window where you executed the `jnbSA` or `jbpSA` commands.

3. If you are using the NetBackup Windows Display Console, add the following line to the `host_name.properties` file in the NetBackup Java installed folder (for example, `C:\Veritas\java`):

```
debugLevel=2
```



4. If you are using the Windows Display Console, you should also add the following to the end of the last command in the `associate.bat` file in the NetBackup Java installed folder:

```
> jnbdebug
```

This redirects output to a file.

NetBackup Status Codes and Messages

4

This chapter lists all the status codes and messages provided by NetBackup. (Media Manager Status Codes and Messages are provided in Chapter 5). There are two parts to the chapter:

- ◆ The first section, Status Codes, lists the NetBackup status codes in numerical order and includes an explanation of what occurred along with recommended actions.
- ◆ The second section, Messages, lists the same status codes but sorts them alphabetically according to the message. Only the messages and status codes are included in the second section.

If you see a status code without its associated message text, you can determine the message, its explanation and recommended action by using the `bpperror` command:

```
install_path\NetBackup\bin\admincmd\bpperror -statuscode statuscode
[-recommendation]
```

where *statuscode* is the number of the message.

Example:

```
install_path\NetBackup\bin\admincmd\bpperror -statuscode 150
```

```
termination requested by administrator
```

```
The process is terminating (or has terminated) as a direct result of a
request from an authorized user or process.
```

Status Codes

Note The term *media server*, as distinct from *master server* or *server*, does not apply to the NetBackup BusinessServer product. When troubleshooting a BusinessServer installation, please ignore any references to media server.

NetBackup Status Code: 0

Message: the requested operation was successfully completed



Explanation: There were no problems detected with the requested operation.

Recommended Action: None, unless this was a database backup performed through a database extension product (for example, NetBackup for Oracle or NetBackup for SQL Server). In those instances, code 0 means the backup script that started the backup ran without error. However, you must check other status as explained in the related NetBackup manual to see if the database was successfully backed up.

NetBackup Status Code: 1

Message: the requested operation was partially successful

Explanation: A problem that may require corrective action was detected during the requested operation.

Recommended Action: Check the All Log Entries report and also the progress log (if there is one).

Some of the problems that can show up under status code 1 are:

- ◆ A file or directory path that is more than 1023 characters long.

For NetBackup ServerFree Agent: the maximum pathname length is 1000 characters for frozen image backups, not 1023. When the frozen image is created, a new mount point is added to the beginning of the file path. If this new mount point plus the original file path exceeds 1023 characters, the backup fails with status code 1. The progress log includes the entry “ERR - Skipping long dir path.”
- ◆ Could not open a file.
- ◆ Read error encountered in a file.
- ◆ File is of an unknown type.
- ◆ On clients using Open Transaction Manager (OTM) for open file management, the OTM cache may be full. See the recommended actions under status code 11.
- ◆ A vault job may terminate with status code 1 if non-fatal errors are encountered during one or more of the following operations:
 - ◆ duplication
 - ◆ suspension of unvaulted media
 - ◆ expiration of disk images
 - ◆ execution of vlt_ejectlist_notify script
 - ◆ catalog backup
 - ◆ eject and/or report

In the event of a non-fatal error, Vault will attempt to complete all the steps configured in the vault profile.



Identify which of the above operations encountered an error by reviewing the detail.log file in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where xxx is the session id)

Or review the vault debug log file in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Correct the problem and rerun the vault job.

NetBackup Status Code: 2

Message: none of the requested files were backed up

Explanation: A backup or archive could not back up any of the files in the file list.

Recommended Action: Verify that the files exist and you have read access to them.

- ◆ Check to see if there is a trailing space on one or more of the filenames in the client's file list. Remove any inadvertent trailing characters (such as spaces or tabs).
- ◆ Check the exclude list per the instructions in the user's guide for the client.
- ◆ On Windows clients, verify that the account used to start the NetBackup Client service has read access to the files.

If you are backing up a network drive or a UNC (universal naming convention) path, use the Services application in the Windows Control Panel to verify that the NetBackup Client service does not start under the SYSTEM account. The SYSTEM account cannot access network drives.

To back up network drives or UNC paths, change the NetBackup Client service startup to log in as a user that has permission to access network drives.

NetBackup Status Code: 3

Message: valid archive image produced, but no files deleted due to non-fatal problems

Explanation: The backup portion of the archive command reported problems so the files were not deleted.

Recommended Action: Examine the status of the archive on the client to determine if you need to retry the archive after correcting the problem. If the problem is not serious and the files were backed up, you can manually delete the files. To verify which files were backed up, use the NetBackup client-user interface in restore mode and browse the files in the archive.



NetBackup Status Code: 4

Message: archive file removal failed

Explanation: The backup portion of the archive completed was successful but the delete failed.

Recommended Action: Verify that you have permission to delete the files and that the read-only flag is not set for the files. Since the backup was successful, you can delete the files that were backed up (or have the system administrator delete the files if you do not have the necessary permissions).

NetBackup Status Code: 5

Message: the restore failed to recover the requested files

Explanation: There were errors that caused the restore to fail.

Recommended Action:

1. Ensure that the client's server list contains entries for the master server and for any media servers that could be used during a backup or restore.
2. Examine the status on the client for messages on why the restore failed. Also, check the All Log Entries report on the server.
3. Check ownership and permission on directories where files will be restored.
4. Correct problems that you find and retry the restore.
5. For NetBackup for EMC Fastrax: you may need to increase the `CLIENT_READ_TIMEOUT` and `CLIENT_CONNECT_TIMEOUT` values in the server's `/usr/opensv/netbackup/bp.conf` file. Although the optimal time-out values for your system may be different, the following values may suffice:

```
CLIENT_READ_TIMEOUT = 3000
CLIENT_CONNECT_TIMEOUT = 3000
```

The safest approach is to increase the timeout values and rerun the restore. Note, however, that the Fastrax system may have completed the restore successfully on its own, even though NetBackup experienced the timeout.

NetBackup Status Code: 6

Message: the backup failed to back up the requested files

Explanation: Errors caused the user backup to fail.

Recommended Action:



1. Verify that you have read access to the files. Check the status on the client for messages on why the backup failed. Correct problems and retry the backup.
2. On Windows clients, verify that the account used to start the NetBackup Client service has read access to the files.
3. On Macintosh clients, this code can be due to multiple backups being attempted simultaneously on the same client. Some possible solutions are:
 - ◆ Adjust the backup schedules.
 - ◆ If the client is only in one policy, set the policy attribute, Limit jobs per policy, to 1.
 - ◆ Set the NetBackup global attribute, Maximum jobs per client, to 1 (note that this limits all clients in all policies).

NetBackup Status Code: 7

Message: the archive failed to back up the requested files

Explanation: Errors caused the user archive to fail.

Recommended Action: Verify that you have read access to the files. Check the status on the client for messages on why the archive failed. Correct problems and retry the archive.

On Windows clients, verify that the account used to start the NetBackup services has read access to the files.

NetBackup Status Code: NetBackup Status Code: 9

Message: an extension package is needed but was not installed

Explanation: A NetBackup extension product is required in order to perform the requested operation.

Recommended Action: Install the required extension product.

NetBackup Status Code: 10

Message: allocation failed

Explanation: Allocation of system memory failed because there is insufficient system memory available. This could be caused by the system being overloaded with too many processes and not enough physical or virtual memory.

Recommended Action: Free up memory by terminating unneeded processes that consume memory. Add more swap space or physical memory.



NetBackup Status Code: 11

Message: system call failed

Explanation: A system call failed. This status code is used for a generic system call failure that does not have its own status code.

Recommended Action:

1. Check the All Log Entries and Problems reports to determine which system call failed and other information about the error.
2. For NetBackup ServerFree Agent:
 - ◆ The file system specified as a frozen image source is not mounted. In this case, you may see the following in the `/usr/openv/netbackup/logs/bpbkar` log:

```
17:12:51 bpbkar: FTL - frozen image processing failed, status 11
17:12:51 bpbkar: ERR - bpbkar FATAL exit status = 11: system call failed
17:12:51 bpbkar: INF - EXIT STATUS 11: system call failed
```

and the following in the `/usr/openv/netbackup/logs/online_util` log:

```
17:12:51 onlfi_vfms_logf: INF - cannot snap_on, err: 5
17:12:51 delete_mount_point: INF - Deleted mount point
/tmp/___jody_test:20958
17:12:51 onlfi_freeze: FTL - VfMS error 11; see following messages:
17:12:51 onlfi_freeze: FTL - Fatal method error
17:12:51 onlfi_freeze: FTL - vfm_freeze: method: nbu_snap, type: FIM,
function: nbu_snap_freeze
17:12:51 onlfi_freeze: FTL - VfMS method error 5; see following message:
17:12:51 onlfi_freeze: FTL - nbu_snap_freeze: Cannot turn on snapshot;
frozen image source=/opt, cache=/dev/rdisk/c1t3d1s0, snap error=5
17:12:51 onlfi_thaw: WRN - / is not frozen
```

Make sure that the file system specified for the frozen image source has been mounted.

- ◆ The file system specified as the frozen image source does not correspond to the file system that contains the actual files (as opposed to symbolic links to the files). The mounted file system for the frozen image source must contain the actual files, not symbolic links. If items in the file list, such as `/oracle/datafile` and `/oracle`, are actually symbolic links to `/export/home/oracle`, the frozen image source must specify `/export`, or `/export/home`, not `/oracle`.
- ◆ `vxvm` is selected as the frozen image method but the frozen image source is not configured over a VERITAS Volume Manager VxVM volume. In this case, you may see the following in the `/usr/openv/netbackup/logs/bpbkar` log:

```
17:12:51 bpbkar main: FTL - frozen image processing failed, status 11
```

```
17:12:51 bpbkar Exit: ERR - bpbkar FATAL exit status = 11: system call failed
```

```
17:12:51 bpbkar Exit: INF - EXIT STATUS 11: system call failed
```

and something like the following in the /usr/opensv/netbackup/logs/online_util log:

```
17:12:51 onlfi_vfms_logf: INF - vxvm_freeze: Frozen image source /cockpit1 on device /dev/dsk/clt0d0s6 is not on a VxVM volume
17:12:51 delete_mount_point: INF - Deleted mount point /tmp/_cockpit1_coc_group1:3518
17:12:51 onlfi_freeze: FTL - VfMS error 11; see following messages:
17:12:51 onlfi_freeze: FTL - Fatal method error
17:12:51 onlfi_freeze: FTL - vfm_freeze: method: vxvm, type: FIM, function: vxvm_freeze
17:12:51 onlfi_freeze: FTL - VfMS method error 9; see following message:
17:12:51 onlfi_freeze: FTL - vxvm_freeze: Frozen image source /cockpit1 on device /dev/dsk/clt0d0s6 is not on a VxVM volume
17:12:51 onlfi_thaw: INF - fim=vxvm
17:12:51 onlfi_thaw: WRN - /cockpit1 is not frozen
```

Make sure that the frozen image source is configured over a VERITAS Volume Manager VxVM volume.

- ◆ vxvm was selected as the frozen image method, but a VERITAS Volume Manager snapshot mirror of the frozen image source volume had not been created prior to running the backup, or if another backup is currently running that is using the snapshot mirror. In either case, you may see the following in the /usr/opensv/netbackup/logs/online_util log:

```
17:12:51 onlfi_freeze: FTL - VfMS error 11; see following messages:
17:12:51 onlfi_freeze: FTL - Fatal method error
17:12:51 onlfi_freeze: FTL - vfm_freeze: method: vxvm, type: FIM, function: vxvm_freeze
17:12:51 onlfi_freeze: FTL - VfMS method error 3; see following message:
17:12:51 onlfi_freeze: FTL - find_ready_snapshot: Cannot find available snapshot mirror
```

As described under “Creating a Snapshot Mirror of the vxvm Frozen Image Source” in the *NetBackup ServerFree Agent System Administrator's Guide*, create a snapshot mirror on the client before running the backup.

- ◆ vxvm was selected as the frozen image method, and a VERITAS Volume Manager snapshot mirror of the frozen image source volume has been created. However, two different backup jobs (A and B) attempt to back up the same volume (for example, vol01), but job A starts just before job B. Because there is a brief pause between finding an available snapshot mirror and actually forming the frozen image of it, job B



(running slightly behind job A) might attempt to create a frozen image of the snapshot mirror just before job A (running slightly ahead) actually creates the frozen image and gets the lock on it.

In this case, you may see the following in the
/usr/opensv/netbackup/logs/online_util log:

```
17:12:51 onlfi_freeze: FTL - VfMS error 11; see following messages:
17:12:51 onlfi_freeze: FTL - Fatal method error
17:12:51 onlfi_freeze: FTL - vfm_freeze: method: vxvm, type: FIM, function:
vxvm_freeze
17:12:51 onlfi_freeze: FTL - VfMS method error 3; see following message:
17:12:51 onlfi_freeze: FTL - vxvm_freeze: Command failed with status=11:
/usr/sbin/vxassist -g rootdg snapshot vol01 VfMSCAAu7a4Uw </dev/null
>/var/tmp/VfMSAAAs7a4Uw 2>/var/tmp/VfMSBAAt7a4Uw
```

The job that was unable to get a lock (job B in the above example) fails, and must be run again.

- ◆ When using nbu_snap as a frozen image method, you may have stale snapshots if status code 11 occurs with the following messages in the
/usr/opensv/netbackup/logs/online_util log. (Stale snapshots are those that were not automatically deleted by nbu_snap.)

```
17:12:51 onlfi_freeze: FTL - VfMS error 11; see following messages:
17:12:51 onlfi_freeze: FTL - Fatal method error
17:12:51 onlfi_freeze: FTL - vfm_freeze: method: nbu_snap, type: FIM,
function: nbu_snap_freeze
17:12:51 onlfi_freeze: FTL - VfMS method error 5; see following message:
17:12:51 onlfi_freeze: FTL - nbu_snap_freeze: Cannot turn on snapshot;
frozen image source=/oracle/ufs_r, cache=/dev/rdisk/c4t1d11s4,snap error=11
```

- a. Look for stale snapshots by running the
/usr/opensv/netbackup/bin/driver/snaplist command when there are no active backups running. If the snaplist command shows cache entries, there are stale snapshots. Nothing is displayed if there are no stale snapshots.

Example snaplist output:

```
id  ident      size      cached    minblk    err time
43  6515      8390970      0          0          0  11/16/00 13:31:36
device = /dev/rdisk/c1t6d0s0
cache  = /dev/rdisk/c1t6d0s7
```

- b. Use the snapoff command to remove the stale snapshot, as follows:
/usr/opensv/netbackup/bin/driver/snapoff id
where id is the id from the snaplist output (such as 43 in the above example).



- ◆ If a backup using the fsclone frozen image method failed, the NetBackup bpbkar process should automatically remove the clone. Sometimes, however, bpbkar is unable to remove the clone. In this case, you may see messages such as the following in the `/usr/openv/netbackup/logs/online_util` log:

```
15:21:45.716 [4236] <4> create_mount_point: INF - Created mount point
/tmp/_vtrax_test_fastrax_dlt:4236
15:21:45.869 [4236] <2> onlfi_vfms_logf: INF - vxfs clone handle : 9600344
15:21:45.870 [4236] <2> onlfi_vfms_logf: INF - fsclone_freeze: Cannot create
checkpoint; status=17
15:21:45.872 [4236] <4> delete_mount_point: INF - Deleted mount point
/tmp/_vtrax_test_fastrax_dlt:4236
15:21:45.873 [4236] <32> onlfi_freeze: FTL - VfMS error 11; see following
messages:
15:21:45.873 [4236] <32> onlfi_freeze: FTL - Fatal method error was reported
15:21:45.873 [4236] <32> onlfi_freeze: FTL - vfm_freeze: method: fsclone,
type: FIM, function: fsclone_freeze
15:21:45.873 [4236] <32> onlfi_freeze: FTL - VfMS method error 17; see
following message:
15:21:45.874 [4236] <32> onlfi_freeze: FTL - fsclone_freeze: Cannot create
checkpoint; status=17
```

Remove the clone as follows.

Note If the clone is not removed, you will not be able to use fsclone to back up any data in the file system where the clone is mounted.

- List the name of the clone by entering the following VxFS command:

```
/usr/lib/fs/vxfs/fsckptadm list /file_system
```

where *file_system* is the name of the file system where the clone is mounted.

Following is sample output. In this example, `/vtrax_test` is the file system and `fi_ckpt` is the name of the clone.

```
/vtrax_test
fi_ckpt:
    ctime          = Mon Nov 12 10:08:13 2001
    mtime          = Mon Nov 12 10:08:13 2001
    flags          = largefiles
```

- Remove the clone by entering the following:

```
/usr/lib/fs/vxfs/fsckptadm remove name_of_clone /file_system
```

- If the clone cannot be removed, unmount the clone and retry step b.



- ◆ If a frozen image backup failed using one of the Extended Frozen Image Services methods (TimeFinder, ShadowImage, BusinessCopy), there may be a VxVM clone left over from a previous backup. You may see messages similar to the following in the `/usr/opensv/netbackup/logs/online_util` log:

```
19:13:07.686 [14981] <2> onlfi_vfms_logf: INF - do_cmd: Command failed with status=20:
/usr/opensv/netbackup/bin/bpdgclone -g wil_test -n vol01 -f /var/tmp/HDSTFCAAs7aOqD
</dev/null >/var/tmp/VfMSAAa7aOqD 2>/var/tmp/VfMSBAAr7aOqD
19:13:07.687 [14981] <2> onlfi_vfms_logf: INF - --- Dumping file /var/tmp/VfMSAAa7aOqD (stdout):
19:13:07.687 [14981] <2> onlfi_vfms_logf: INF - --- End of file /var/tmp/VfMSAAa7aOqD
19:13:07.687 [14981] <2> onlfi_vfms_logf: INF - --- Dumping file /var/tmp/VfMSBAAr7aOqD (stderr):
19:13:07.687 [14981] <2> onlfi_vfms_logf: INF - clone group and volume already exists
19:13:07.688 [14981] <2> onlfi_vfms_logf: INF - --- End of file /var/tmp/VfMSBAAr7aOqD
```

NetBackup automatically creates VxVM clones for Extended Frozen Image Services backups of data configured over volumes. After the backup has completed, NetBackup removes the VxVM clone. In this case, a system crash or reboot may have prevented the removal. Remove the clone as follows.

- When no backups are running, use the following VxVM command to list any clones: `vxdg list`

The clone name will be of the form `clone_disk_group_clone`.

- To remove the clone, enter the following:

```
/usr/opensv/netbackup/bin/bpdgclone -g disk_group -n volume -c
```

For example:

```
/usr/opensv/netbackup/bin/bpdgclone -g wil_test -n vol01 -c
```

where `wil_test` is the name of the disk group and `vol01` is the name of the VxVM volume.

For more information on removing a VxVM clone, refer to the *NetBackup ServerFree Agent System Administrator's Guide*. For `vxdg`, refer to the *VERITAS Volume Manager Administrator's Guide*.

- Before running the backup again, resynchronize the primary disk with the secondary disk. For assistance, refer to the “Extended Frozen Image Services” chapter of the *NetBackup ServerFree Agent System Administrator's Guide*.

- For NetBackup for EMC Fastrax:

If a backup fails with a status code 11, and the NetBackup progress log has a message stating `SYMINIT` failed (see example log below), a `/usr/symcli` symbolic link must be created that points to the SYMAPI libraries installed on your system.

The following is an example progress log:

```
Backup started Thu 06 Dec 2001 03:53:52 PM CST
```



```
15:53:52 Initiating backup
15:54:01 ERR - SYMINIT failed status = -1
EXIT STATUS 11: system call failed
15:54:04 INF - Status = system call failed.
```

EMC releases several different versions of its SYMAPI library (`libsymapi.so`), to support multi-threading, 32-bit and 64-bit machines, and so forth. The library name and install location vary, depending on your configuration.

When the SYMAPI library is being installed, the EMC package creates a link to the correct library file name, but in some cases this link may not point to the correct directory (`/usr/symcli`). This may happen if your installation has multiple packages, or if you install another version (such as multi-threaded, or 64-bit `symcli`). Without the proper symbolic link, Fastrax backups will fail.

As a result, you may need to create a `/usr/symcli` symbolic link to the SYMAPI shared libraries. For instance, NetBackup Fastrax must be able to find the following:

```
/usr/symcli/shlib/libsymapi.so
/usr/symcli/shlib/libsymvm.so
```

The default `symcli` location is the following:

```
lrwxrwxrwx 1 root other 22 Dec 3 09:23 symcli ->
/opt/emc/SYMCLI/V4.3.2
```

Note that this example is for version 4.3.2.

4. A frequent cause is that the server's file system is full. For example, you may see a message similar to the following in the Problems report or `bpdbm` debug log:

```
06/27/95 01:04:00 romb romb db_FLISTsend failed: system call failed (11)
06/27/95 01:04:01 romb romb media manager terminated by parent process
06/27/95 01:05:15 romb romb backup of client romb exited with status 11
(system call failed)
```

On Windows systems, verify that there is enough room in the disk partition where NetBackup is installed.

5. Verify that the system is not running out of virtual memory. If virtual memory is the problem, shut down unused applications or increase the amount of virtual memory.

To increase virtual memory on Windows:

- a. Display the Control Panel.
- b. Double-click System.
- c. On the Performance tab, set Virtual Memory to a higher value.



6. Examine other debug logs or the status on the client.
7. If a backup on a Windows NetBackup client fails with status code 11 and the client is using Open Transaction Manager (OTM) for open file management, it is possible that the error was caused by the OTM cache file being full. If this is the case and bpbkar debug logs are turned on, a message similar to the following should appear at the end of the backup:

```
04/28/99 11:27:56 AM: [216]: ERR - OTM Error:0xe0001005
04/28/99 11:27:59 AM: [216]: INF - OTM Terminate - disabled for all
processes
04/28/99 11:27:59 AM: [216]: FTL - Backup operation aborted!
```

If this error is encountered, try one of the following (the first is preferred):

- ◆ Set maximum OTM cache size to zero (0); at run time, OTM will determine how much cache is needed and set it accordingly.
- ◆ Increase either the initial OTM cache size or the maximum OTM cache size on your own, depending on the requirements of your installation and your usage of OTM.

If resizing OTM cache does not fix the problem, you may not have enough free disk space.

NetBackup Status Code: 12

Message: file open failed

Explanation: An open of a file failed.

Recommended Action:

- ◆ For NetBackup ServerFree Agent only:

Status code 12 may appear in the `/usr/opensv/netbackup/logs/bptm` or `bpdm` log, accompanied by the following:

```
tpc_read_config failed: cannot open file
/usr/opensv/volmgr/database/3pc.conf
```

This may indicate that the policy is configured with either NetBackup Media Server or Third-Party Copy Device as the offhost backup method, but that the `3pc.conf` file does not exist or is in the wrong location. (When upgrading from NetBackup 4.0V to 4.5, you must recreate the `3pc.conf` file.) For instructions on creating the `3pc.conf` file, refer to the latest version of the *NetBackup ServerFree Agent System Administrator's Guide*.

- ◆ Check the NetBackup Problems report. Try to determine the file and why the error occurred. A possible cause is a permission problem with the file. For detailed troubleshooting information, create a debug log directory for the process that returned this status code. Then, retry the operation, and check the resulting debug log.

NetBackup Status Code: 13

Message: file read failed

Explanation: A read of a file or socket failed. Possible causes include:

- ◆ I/O error reading from the file system.
- ◆ Read of an incomplete or corrupt file.
- ◆ Socket read failing. A socket read failure can be caused by a network problem or a problem with the process that is writing to the socket.
- ◆ A problem specific to NetBackup ServerFree Agent (see recommended actions).

Recommended Action:

1. Check the NetBackup Problems report for clues on where and why the problem occurred.
2. For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.
3. For NetBackup ServerFree Agent only:

Status code 13 may appear in the `/usr/openv/netbackup/logs/bpbkar` log, and can indicate the following:

- ◆ The files to back up reside on an IDE drive as opposed to SCSI, and the offhost backup method was set to either NetBackup Media Server or Third-Party Copy Device. If you are using offhost backup, the disk containing the client files must be a SCSI or Fibre Channel device.

If the disk is an IDE drive, you may see the following in the `/usr/openv/netbackup/logs/online_util` log:

```
get_disk_info: FTL - /var/tmp/caa026fEU disk_inquiry failed.
Errno = 25: Inappropriate ioctl for device
```

and the following may appear in the `/usr/openv/netbackup/logs/bpbkar` log:

```
bpbkar: INF - Processing /var
bpbkar: ERR - get_disk_info() failed, status 13
bpbkar: ERR - tpc_get_disk_info() failed: err 13
```



```
bpbkcar: ERR - bpbkar FATAL exit status = 13: file read
failed
bpbkcar: INF - EXIT STATUS 13: file read failed
```

- ◆ The files to back up exist on a file system that is not mounted. The file system specified as the frozen image source must be mounted. If the frozen image source is not mounted but the mount point is present, NetBackup may try to take a frozen image of the directory above the directory that was specified as the frozen image source.

NetBackup Status Code: 14

Message: file write failed

Explanation: A write to a file or socket failed. Possible causes include:

- ◆ I/O error writing to the file system.
- ◆ Write to a socket failed. This can be caused by a network problem or a problem with the process reading from the socket.
- ◆ Writing to a full disk partition.

Recommended Action:

- ◆ Check the NetBackup Problems report for clues on where and why the problem occurred.
- ◆ For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.
- ◆ Make sure that routers, bridges, and other network devices are all at “full” duplex.
- ◆ Use a “sniffer” program to determine the number of packets being rejected and/or re-requested.
- ◆ On Windows systems, the client bpbkar log may contain a 10054 “Connection Reset Error” error (usually indicates a hardware error). Somewhere between the NetBackup client and server, the connection was reset. When NetBackup receives this error, it is unable to continue the backup. This error has been attributed to the following:
 - ◆ A hiccup in the network.
 - ◆ A bad network interface card on a NetBackup client.
 - ◆ A bad network interface card on the NetBackup server.
 - ◆ Faulty routers.
 - ◆ Other applications interfering with NetBackup connections.
- ◆ On Novell systems, status code 14 has also been attributed to network issues. Try a “sniffer” program, as suggested above.

NetBackup Status Code: 15

Message: file close failed

Explanation: A close of a file or socket failed.

Recommended Action: Check the NetBackup Problems report for clues on where and why the problem occurred. For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 16

Message: unimplemented feature

Explanation: The specified operation is unimplemented. This error should not occur through normal use of NetBackup.

Recommended Action: Save all error information and call customer support.

NetBackup Status Code: 17

Message: pipe open failed

Explanation: Occurs in NetBackup client menu and vault areas.

Recommended Action: None

NetBackup Status Code: 18

Message: pipe close failed

Explanation: Close of a pipe failed, when one process tries to start a child process.

Recommended Action: Check the NetBackup Problems report for clues on why the failure occurred. For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 19

Message: getservbyname failed

Explanation: A call to `getservbyname()` failed. The `getservbyname()` function uses the name of the service to find a service entry in the `services` file.

Recommended Action:



1. Check the NetBackup Problems report for clues on why the failure occurred.
2. On a Windows system, verify that the `%SystemRoot%\system32\drivers\etc\services` file shows the correct entries for the NetBackup internet processes: `bpcd`, `bpdsm`, and `bprd`.

Ensure that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Client Properties dialog match the settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface and click NetBackup Client Properties on the File menu. The values on the Network tab are written to the `services` file when the NetBackup Client service starts.

Also, see “Verifying Host Names and Services Entries” on page 25.
3. Check the level of network activity. An overloaded network can cause this error.
4. If the above actions do not reveal the problem, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 20

Message: invalid command parameter

Explanation: One or more command parameters were not valid. This error can occur when a master and its media servers or a master server and a client have different levels of NetBackup installed. For example, if a NetBackup master server has NetBackup 4.5 and the media server has NetBackup 3.4.

This error can also occur if the wrong parameters are used when executing a command line.

Recommended Action:

1. Check the NetBackup Problems report for clues.
2. If the error occurs when executing a command on the command line, verify that the parameters are valid.
3. For NetBackup ServerFree Agent:
 - ◆ If the following appears in the `/usr/openv/netbackup/logs/bptm` log,

```
bptm: cannot perform Third-Party-Copy for multiplexed backups  
send_brm_msg: ERROR 20  
bptm: EXITING with status 20
```



multiplexing was enabled on a third-party copy backup. The Third-Party Copy Device offhost backup method is incompatible with multiplexing (the writing of two or more concurrent backup jobs to the same storage device). You must disable multiplexing for any third-party copy backups. If multiplexing is enabled, the backup will fail.

- ◆ The media server may not have the correct `3pc.conf` file entry for the client disk needed for the backup. The following appears in the `/usr/opensv/netbackup/logs/bpbkar` log:

```
14:45:00.983 [15773] <4> bmap_mm_get_devid: GET_DEVICE_INDEX 1
EMC:SYMMETRIX:601092014000
14:45:00.986 [15773] <4> bpbkar child_send_keepalives: keepalive
child started, pid = 15822
14:47:02.029 [15773] <4> bmap_mm_get_devid: keepalive child:
15822 killed
14:47:02.030 [15773] <4> bmap_mm_get_devid: DEVICE_INDEX -1
14:47:02.031 [15773] <16> bmap_send_extend: ERR - can't obtain
device id string EMC:SYMMETRIX:601092014000
14:47:33.167 [15773] <16> bpbkar Exit: ERR - bpbkar FATAL exit
status = 227: no entity was found
14:47:33.167 [15773] <4> bpbkar Exit: INF - EXIT STATUS 227: no
entity was found
14:47:33.168 [15773] <2> bpbkar Exit: INF - Close of stdout
complete
```

This shows that a particular device cannot be found in the `3pc.conf` file on the media server (14:47:02.031 [15773] <16> `bmap_send_extend: ERR - can't obtain device id string EMC:SYMMETRIX:601092014000`). The problem is one of the following:

- ◆ The `3pc.conf` file on the media server is outdated. Recreate the `3pc.conf` file.
- ◆ The media server is not on the same fibre channel network as the third-party copy device and client disk. As a result, the `3pc.conf` file does not have a correct entry for the client disk. Run the `bptpcinfo` command with the `-x client_name` option; this adds the client disk to the `3pc.conf` file. For each disk added to the file by means of `bptpcinfo -x client_name`, you must add the device's world-wide name (wwn=), as explained in the *NetBackup ServerFree Agent System Administrator's Guide*.

4. Compare the NetBackup version level on the server to that on the clients:

- ◆ On Windows NetBackup servers, check the `install_path\netbackup\version.txt` file or the About NetBackup item on the Help menu.



- ◆ On Microsoft Windows clients, check the About NetBackup item on the Help menu.
 - ◆ On NetWare target clients, check the Version entry in the `bp.ini` file.
If the client software is earlier than 3.0, verify that the client is in a Standard type policy.
 - ◆ On Macintosh clients, check the version file in the bin folder in the NetBackup folder in the Preferences folder.
 - ◆ If the error is being displayed from a Java interface, tell them how to enable the debug print manager in the Java startup file. Retry and compare the parameters logged in the Java log with the parameters listed in the commands usage statement.
5. If the above actions do not reveal the problem, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 21

Message: socket open failed

Explanation: A socket could not be opened.

Recommended Action:

1. Check the NetBackup Problems report for clues on where and why the failure occurred. If you cannot determine the cause from the Problems report, create debug log directories for the processes that returned this status code. Then, retry the operation and check the resulting debug logs.
2. On Windows, verify that the recommended service packs are installed.

NetBackup Status Code: 22

Message: socket close failed

Explanation: A socket could not be closed.

Recommended Action:

1. Check the NetBackup Problems report for clues on where and why the failure occurred. If you cannot determine the cause from the Problems report, create debug log directories for the processes that could have returned this status code. Then, retry the operation and check the resulting debug logs.
2. On Windows, verify that the recommended service packs are installed.

NetBackup Status Code: 23

Message: socket read failed

Explanation: A read operation from a socket failed.

Recommended Action:

1. Check the NetBackup Problems report for clues on where and why the failure occurred. If you cannot determine the cause from the Problems report, create debug log directories for the processes that could have returned this status code. Then, retry the operation and check the resulting debug logs.

2. Corrupt binaries are one possible cause for this error. For example, in one instance, the following was seen in the bpsched debug log.

```
get_num_avail_drives: readline failed: socket read failed (23)
get_stunits: get_num_avail_drives failed with stat 23
```

Loading a fresh bptm from the install media resolved the problem.

3. On Windows, verify that the recommended service packs are installed.
4. This error may occur during a restore to a Novell client. Note the following possible actions:
 - ◆ By default, the value for Novell “Maximum Concurrent Disk Cache Writes” may be too low (for example, 50); Novell recommends setting it to 100. A value of 100 increases the speed and efficiency of disk cache writes by increasing the number of write requests that can be executed at one time.
 - ◆ Change to or add the following settings in the Novell `sys:system\autoexec.ncf` file:


```
SET Maximum Packet Receive Buffers = 4000
SET Maximum Directory Cache Buffers = 4000
SET Maximum Concurrent Disk Cache Writes = 2000
SET Maximum Concurrent Directory Cache Writes = 2000
SET Maximum Physical Receive Packet Size = 1514
```
 - ◆ On NT/2000 master servers, check the `LIST_FILES_TIMEOUT` value and ensure that this value is at least 1800.

5. For NetBackup for EMC Fastrax: Increase the `CLIENT_READ_TIMEOUT` and `CLIENT_CONNECT_TIMEOUT` values in the server's `/usr/opensv/netbackup/bp.conf` file and retry the operation. Although the optimal time-out values for your system may be different, the following values may suffice:

```
CLIENT_READ_TIMEOUT = 3000
```



CLIENT_CONNECT_TIMEOUT = 3000

NetBackup Status Code: 24

Message: socket write failed

Explanation: A write operation to a socket failed.

Recommended Action:

1. Check the NetBackup Problems report for clues on where and why the failure occurred. If you cannot determine the cause from the Problems report, create debug log directories for the processes that could have returned this status code. Then retry the operation and check the resulting debug logs.
2. A possible cause could be a high network load. For example, this has been seen in conjunction with Cannot write to STDOUT when a Windows system that is monitoring network load has detected a high load and sent an ICMP packet to other systems that says the route being used by those systems was disconnected. The log messages were similar to the following:

```
01/31/96 14:05:23 ruble crabtree.null.com from client
crabtree.null.com: ERR - Cannot write to STDOUT. Err no= 242: No route
to host
01/31/96 14:05:48 ruble crabtree.null.com successfully wrote backup
id crabtree.null.com_0823125016, copy 1, fragment 1, 440864 Kbytes at
628.538 Kbytes/sec
01/31/96 14:05:51 netbackup crabtree.null.com CLIENT
crabtree.null.com POLICY Remote3SysFullW SCHED Sirius EXIT STATUS 24
(socket write failed)
```

3. On Windows, verify that the recommended service packs are installed.
4. This error may occur during a restore to a Novell client. Note the following possible actions:
 - ◆ By default, the value for Novell “Maximum Packet Receive Buffers” may be too low (such as 100). The restore performance may be improved by changing this value to 2000. To change it, issue “SET Maximum Packet Receive Buffers=<value>” at the console, or enter the value in either of the following Novell files: `sys:system\startup.ncf` or `sys:system\autoexec.ncf`.
 - ◆ Change to or add the following settings in the Novell `sys:system\autoexec.ncf` file:

```
SET Maximum Packet Receive Buffers = 4000
SET Maximum Directory Cache Buffers = 4000
SET Maximum Concurrent Disk Cache Writes = 2000
```

```
SET Maximum Concurrent Directory Cache Writes = 2000
SET Maximum Physical Receive Packet Size = 1514
```

NetBackup Status Code: 25

Message: cannot connect on socket

Explanation: A process timed out while connecting to another process for a particular operation. This problem can occur when a process tries to connect to the NetBackup Request Manager service or the NetBackup Database Manager service and the service is not running. It can also occur if the network or server is heavily loaded and has slow response time, or if an evaluation license key for NetBackup BusinessServer or DataCenter has expired.

Recommended Action:

1. On the Windows master server, verify that the NetBackup Request Manager and NetBackup Database Manager services are running. If these services are not running, start them.

If the above services are running, examine the All Log Entries report for the time of the failure to determine where the failure occurred.

- ◆ If you cannot view the report, or you get a “cannot connect on socket” error when trying to view it, verify again that the NetBackup Database Manager service is running. Then, create a debug log directory for bpdbm, retry the operation, and check the resulting debug log.
- ◆ If you can view the report and have not found an entry related to this problem, create debug log directories for the related processes that were running when the error first appeared (this process will frequently be bpbm). Then, retry the operation and check the resulting debug logs.

2. Verify that the server list specifies the correct master server.

- ◆ On Windows systems, the master server is designated as CURRENT on the Servers tab in the Specify NetBackup Machines dialog. To display this dialog box, start the Backup, Archive, and Restore interface and click Specify NetBackup Machines on the Actions menu.
- ◆ On Macintosh systems, the master server is the first SERVER entry in the bp.conf file.
- ◆ On NetWare target and OS/2 clients, the master server name is the first SERVER entry in the bp.ini file.

If you change the server list on a master server, stop and restart the NetBackup Database Manager and NetBackup Request Manager services.



- ◆ Make sure all recommended NetBackup patches have been installed. Check the VERITAS support web site for current patch information. (Go to www.support.veritas.com, then select “NetBackup” followed by “files and updates”).
- ◆ If failure occurs when executing a user-directed backup from a client, make sure a user-directed backup schedule exists at the master server.
- ◆ When working with NetBackup database extensions, make sure that the applicable database product has the correct permissions allowing NetBackup to write to the progress log on the client.

3. Check the `services` file.

On Windows, verify that the `%SystemRoot%\system32\drivers\etc\services` file has the correct entries for `bpcd`, `bpbdbm`, and `bprd`.

Also, verify that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Client Properties dialog match the settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface and click NetBackup Client Properties on the File menu. The values on the Network tab are written to the `services` file when the NetBackup Client service starts.

Also, see “Verifying Host Names and Services Entries” on page 25.

- 4. On Windows, verify that the recommended service packs are installed.
- 5. When the base NetBackup BusinessServer or DataCenter license key expires, daemons (such as `bprd` and `bpbdbm`) will terminate on the NetBackup server. If these daemons are not running, you are likely to encounter status code 25 errors in the Administration GUIs. Install a valid base NetBackup license key, restart the daemons, and restart the GUI.

NetBackup Status Code: 26

Message: client/server handshaking failed

Explanation: A process on the server encountered an error when communicating with the client. This error indicates that the client and server were able to initiate communications, but encountered difficulties in completing them. This problem can occur during a backup or a restore.

Recommended Action: Determine which activity encountered the handshake failure by examining the All Log Entries report for the appropriate time period. Determine the client and server that had the handshake failure.



For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 27

Message: child process killed by signal

Explanation: A child of the process reporting this error was killed. This can occur because the backup job was terminated or the child process was terminated by another error. This problem can also occur if a NetBackup process was terminated through Task Manager or another utility.

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create a debug log directory for the process that you suspect of returning this status code. Then, retry the operation and check the resulting debug log.

NetBackup Status Code: 28

Message: failed trying to fork a process

Explanation: A CreateProcess failed. This may be due to:

- ◆ An overloaded system
- ◆ Insufficient swap space or physical memory
- ◆ Too many processes running on the system

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create debug log directories for the processes that you suspect of returning this status code. Then, retry the operation and check the resulting debug logs.

NetBackup Status Code: 29

Message: failed trying to exec a command

Explanation: A command could not be executed. This can occur because the permissions of the command do not allow it to be executed, or there is lack of system resources such as memory and swap space.

Recommended Action:

1. Check the NetBackup All Log Entries report for clues on where and why the failure occurred.
2. Check the permissions on the command to be executed.



3. For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: NetBackup Status Code: 31

Message: could not set user id for process

Explanation: Could not set the user ID of a process to that of the requesting user. NetBackup executes client processes as the requesting user.

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create a debug log directory for the process that you suspect of returning this status code. Then, retry the operation and check the resulting debug log.

NetBackup Status Code: 32

Message: could not set group id for process

Explanation: Could not set the group ID of a process to the requesting user group. NetBackup executes client processes with the group ID of the requesting user.

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create a debug log directory for the process that you suspect of returning this status code. Then, retry the operation and check the resulting debug log.

NetBackup Status Code: 33

Message: failed while trying to send mail

Explanation: An E-mail notification of backup, archive, or restore results has failed. The E-mail could not be sent to the administrator's address as specified by the E-mail global attribute.

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create a debug log directory for the process that you suspect of returning this status code. Then, retry the operation and check the resulting debug log.

NetBackup Status Code: 34

Message: failed waiting for child process

Explanation: The bpsched process encountered a failure while waiting for a child process to complete.

Recommended Action: Check the NetBackup All Log Entries report for clues on where and why the failure occurred. For detailed troubleshooting information, create a debug log for the process that you suspect of returning this status code. Then, retry the operation and check the resulting debug log.

NetBackup Status Code: 35

Message: cannot make required directory

Explanation: Could not create a required directory. Possible causes are:

- ◆ A process does not have permission to create the directory
- ◆ The path to the directory is not valid
- ◆ An IO error occurs
- ◆ There was no space available on the device containing the directory

Recommended Action:

1. Check the NetBackup All Log Entries report to determine which directory could not be created and why it could not be created. In particular, check for a full disk partition.
2. Check the permissions on the parent directory and verify that NetBackup services are started with a “Logon as” account that has permission to create the directory.
3. For detailed troubleshooting information, create a debug log directory for the process that returned this status code, retry the operation, and check the resulting debug log.

NetBackup Status Code: 36

Message: failed trying to allocate memory

Explanation: Allocation of system memory failed. This error occurs when there is insufficient system memory available. This could be caused by the system being overloaded with too many processes and there is not enough physical and virtual memory.

Recommended Action: Free up memory by terminating unneeded processes that consume a lot of memory. Add more swap space or physical memory.

NetBackup Status Code: 37

Message: operation requested by an invalid server



Explanation: A request was made to the NetBackup Request Manager service or NetBackup Database Manager service by an invalid media server or Windows NetBackup Remote Administration Console.

Recommended Action: Examine the NetBackup All Log Entries report for the time of this error to determine which system was trying to connect to the master server.

If the server is a valid media server, verify that the storage unit for the media server is defined. Also, verify that the server or Windows NetBackup Remote Administration Console has a server list entry on the master server.

Add the media server to the list on the Servers tab in the Master Server Properties dialog (see “Using the Host Properties Window” on page 40).

If a server or Windows NetBackup Remote Administration Console has more than one host name (for example, if it has multiple network interfaces), verify that the master server has a server list entry for each of them.

If you change the server list on a Windows master server, stop and then restart the NetBackup Request Manager and NetBackup Database Manager services.

NetBackup Status Code: NetBackup Status Code: 39

Message: client name mismatch

Explanation: The name that the client used in a request to the NetBackup server did not match the client name configured in the policy on the server.

Recommended Action: Change either the NetBackup client name setting on the client (see the applicable NetBackup users guide) or the one in the policy configuration on the server so the two match.

NetBackup Status Code: 40

Message: network connection broken

Explanation: The connection between the client and the server was broken. This status code can also appear if the connection is broken between the master and media server during a backup.

Recommended Action:

1. Try pinging the client from the server. If this is not possible, check for loose connections or other network problems.
2. Verify that the server list settings are correct on both the client and the server. If the backup involves a media server, verify that these entries are correct on both the master and media server. For example, if a media server does not have a server list entry for the master, it does not accept connections from the master.

- ◆ On Windows, the master server is designated on the Servers tab in the Master Server Properties dialog. To display this dialog, see “Using the Host Properties Window” on page 40.
- ◆ On Macintosh systems, the master server is the first `SERVER` entry in the `bp.conf` file.
- ◆ On NetWare target and OS/2 clients the master server name is the first `SERVER` entry in the `bp.ini` file.

If you change the server list on a master server, stop and restart the NetBackup Database Manager and NetBackup Request Manager services.

3. Status code 40 can also be due to the operator denying a mount request.

NetBackup Status Code: 41

Message: network connection timed out

Explanation: The server did not receive any information from the client for too long a period of time.

Recommended Action:

1. On Windows clients, check for the following problems with the `bpbkar` client process.

The `bpbkar` client process is not hung, but due to the files and directories it is scanning, it has not replied to the server within the Client read timeout or Client connect timeout period. This has been seen to occur during incremental backups when directories have thousands of unmodified files.

For this case, use Host Properties on the NetBackup server to change Client connect timeout or Client read timeout. These settings are on the Timeouts and Universal Settings tabs, respectively, in the Master Server Properties dialog (see “Using the Host Properties Window” on page 40). The default for these timeouts is 300 seconds.

You can also monitor CPU utilization to determine if this condition exists.

2. On Windows systems, try the following:

- ◆ Disable the following file:

`install_path\Veritas\NetBackup\bin\admincmd\tracker.exe`

- ◆ Repair hard drive fragmentation. You could try an application called Diskeeper Lite, which is part of the Windows NT Resource Kit.
- ◆ Make sure there is enough space available in `\temp`.



3. If the server cannot connect to the client, create `bpcd` or `bpbkcar` (Windows only) debug log directories on the client, retry the operation, and check the resulting logs. If these logs do not provide a clue, create a `bpbrm` debug log on the server, retry the operation again, and check the resulting debug log.

If the `bpbrm` log has entries similar to the following:

```
bpbrm hookup_timeout: timed out waiting during the client hookup  
bpbrm Exit: client backup EXIT STATUS 41: network connection timed out
```

then the problem is in the routing configuration on the server.

Verify that the client IP address is correct in the name service that is being used.

Also, see “Resolving Network Communication Problems” on page 21.

4. Make sure all recommended NetBackup patches have been installed. Check the VERITAS support web site for current patch information. (Go to www.support.veritas.com, then select “NetBackup” followed by “files and updates”.)
5. Add the `CLIENT_READ_TIMEOUT` values to the master server, media server and client when a NetBackup database extension product is installed. The values should all be the same for each server. The value set is dependent on the size of the database being backed up. See the *NetBackup System Administrator's Guide* for more information on `CLIENT_READ_TIMEOUT`.
6. Make sure enhanced authentication is configured correctly. See the chapter on enhanced authentication in the *NetBackup System Administrator's Guide*.

For example, the following could result in status code 41: host A is configured to use enhanced authentication with host B, but host B is not configured to use enhanced authentication with host A. In this case, connections from host B to host A are likely to fail with status code 41. Connections from host A to B are likely to fail with authentication errors (status code 160).

NetBackup Status Code: 42

Message: network read failed

Explanation: An attempt to read data from a socket failed.

Recommended Action:

1. Verify that both the client and the server are operational.
2. Perform “Resolving Network Communication Problems” on page 21.
3. Check the Problems report for clues.

NetBackup Status Code: 43

Message: unexpected message received

Explanation: The client and server handshaking was not correct.

Recommended Action:

1. Verify that the correct version of software is running on the client and the server.
2. Enable detailed debug logging:
 - ◆ On the server, create a `bpbrm` debug log directory.
 - ◆ On clients, create a `bpcd` debug log directory (created automatically on Macintosh clients).
 - ◆ Increase the amount of debug information included in the logs as explained in the debug log topics in Chapter 3.
3. Retry the operation and examine the logs.

Note If you are using `bpstart_notify` scripts on Windows clients, verify that messages are not being written to `stdout` or `stderr`.

NetBackup Status Code: 44

Message: network write failed

Explanation: An attempt to write data to a socket failed.

Recommended Action:

1. Check the Problems report for information about the error.
2. Verify that the client and servers are operational and connected to the network.
3. Create a debug log directory for the process that reported the problem and the operation. Examine the resulting debug log file for detailed troubleshooting information.
4. Perform “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 45

Message: request attempted on a non reserved port

Explanation: An attempt was made to access a client from a nonreserved port.



Recommended Action: Verify that the latest software is installed on the client and server.

- ◆ On Windows NetBackup servers, check the *install_path\netbackup\version.txt* file or the About NetBackup item on the Help menu.
- ◆ On Microsoft Windows clients, check the About NetBackup item on the Help menu.
- ◆ On NetWare target clients, check the Version entry in the *bp.ini* file.
- ◆ If this is a NetBackup for NetWare client and has a version of NetBackup earlier than 3.0, verify that the client is in a Standard type policy.
- ◆ On Macintosh clients, check the version file in the bin folder in the NetBackup folder in the Preferences folder.

NetBackup Status Code: 46

Message: server not allowed access

Explanation: The server is trying to access a client but access is blocked. Possible causes are:

- ◆ The server is not listed on the client as a valid server.
- ◆ The client has been configured to require encrypted backups, but the encryption attribute for the backup policy on the server has not been selected.
- ◆ The evaluation license for the NetBackup Encryption product has expired on the server, but the NetBackup client has been configured to require encrypted backups. As a result, the server attempted to make a non-encrypted backup of the client; since the client is configured to require encryption, the backup failed.

Recommended Action:

- ◆ If the server is a valid server but is not listed on the client, add its name to the client's server list:
 - ◆ On Windows clients, add the server on the Servers tab in the Specify NetBackup Machines dialog box. To display this dialog box, start the Backup, Archive, and Restore interface on the client and click Specify NetBackup Machines on the Actions menu.
 - ◆ On Macintosh clients, add a SERVER entry in the *bp.conf* file.
 - ◆ On NetWare target and OS/2 clients, add a SERVER entry in the *bp.ini* file.

If you continue to have problems, review "Resolving Network Communication Problems" on page 21 and "Verifying Host Names and Services Entries" on page 25.
- ◆ To make non-encrypted backups of the client, set CRYPT_OPTION on the client to *allowed* or *denied*. For more information, refer to the *NetBackup Encryption System Administrator's Guide*.

- ◆ If the NetBackup encryption evaluation license has expired on the server and you want to continue encrypting backups of the client, you must purchase a permanent encryption license key and add it to the server. After you add the permanent encryption license key, check the attributes of the backup policy to make sure that encryption is selected.

To check the validity of an evaluation license key, do the following:

On Windows: go to the Help menu on the NetBackup Administration window on the NetBackup server and select License Keys. If the evaluation key is not listed in the NetBackup License Keys window, the key has expired. Use this window to add the new permanent encryption key.

NetBackup Status Code: 47

Message: host is unreachable

Explanation: An attempt to connect to another machine failed.

Recommended Action:

1. Verify that the name service (or services) being used by the client is configured to correctly resolve the host names of the NetBackup server.
2. Verify that the name service (or services) being used by the server is configured to correctly resolve the host name of the NetBackup client.
3. Try to ping the client from the server and the server from the client.
4. If you continue to have problems, perform “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 48

Message: client hostname could not be found

Explanation: The system function `gethostbyname()` failed to find the client’s host name.

Recommended Action:

1. Verify that the client name is correct in:
 - ◆ The NetBackup policy configuration on the master server.
 - ◆ The General tab in the NetBackup Client Properties dialog box and the Clients tab in the Specify NetBackup Machines dialog box (on Microsoft Windows and NetWare nontarget clients). To display these dialog boxes, start the Backup,



Archive, and Restore interface on the client. For the General tab, click NetBackup Client Properties on the File menu; for Clients tab, click Specify NetBackup Machines on the File menu.

- ◆ The `bp.conf` file on Macintosh clients.
 - ◆ The `bp.ini` file on OS/2 and NetWare target clients.
2. On clients and servers, verify that the name service is set up to correctly resolve the NetBackup client names.

NetBackup Status Code: 49

Message: client did not start

Explanation: The client failed to start up correctly.

Recommended Action:

1. Verify that software is installed on the client and it is the correct version. If necessary, reinstall the client software.
2. Check for full file systems on the client.
3. Enable detailed debug logging on the client:
 - ◆ Create `bpcd` and `bpbkar` (Windows only) debug log directories.
 - ◆ Increase the debug or log level as explained in the debug log topics in Chapter 3.
4. Retry the operation and examine the resulting logs.
5. On SGI IRIX 6.2/6.4 systems, clients may be missing the `libdbm.so` shared library. Refer to the SGI/IRIX install CD-ROM for the `oe.sw.dmi` package.

NetBackup Status Code: 50

Message: client process aborted

Explanation: The client backup aborted. One instance when this code appears is if a NetBackup master or media server is shut down or rebooted when a backup or restore is in process.

Recommended Action:

1. Enable detailed debug logging:
 - ◆ Create a `bpbkar` debug log directory (Windows only).

- ◆ Create a `bpcd` debug log directory (this log is created automatically on Macintosh clients.)
 - ◆ Increase the debug or log level as explained in the debug log topics in Chapter 3.
2. Retry the operation and examine the resulting logs.
 3. This problem can sometimes be due to a corrupt binary.
On a Windows client, check the `bpnetd.exe`, `bpcd.exe`, `bpbkar32.exe`, and `tar32.exe` executables located in the *install_path*\NetBackup\bin folder on the client. Reinstall the client if these executables are not the same size as on other Windows clients or are not at the same release level or do not have the same NetBackup patches applied as other Windows clients.

NetBackup Status Code: 51

Message: timed out waiting for database information

Explanation: The catalog process did not respond within five minutes.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. Verify that there is space in the file system that contains the NetBackup catalogs.
3. Create `bpbrm` and `bpdbm` debug log directories on the server and retry the operation.
4. Look in the debug log files to find more information on the problem.

NetBackup Status Code: 52

Message: timed out waiting for media manager to mount volume

Explanation: The requested volume was not mounted before the timeout expired. This error can also occur if the volume happens to be a cleaning tape but was not specified as a cleaning tape.

Another possible cause: if the last available drive has a mount request for a non-backup (such as a restore), then a backup requiring the same drive is initiated before the mount completes. This is due to the drive not being reported as busy until the mount completes.

Recommended Action:



1. Verify that the requested volume is available and an appropriate drive is ready and in the UP state.
2. If this occurs during a read operation (restore, duplicate, verify), the drives could be busy. Try increasing the media mount timeout specified by the NetBackup global attribute in order to allow more time for mounting and positioning the media.
3. Verify that the tape is not a cleaning tape that is configured as a regular volume.
4. When the robot is controlled by an Automated Cartridge System, verify that the ACSLS system is up.
5. If this is an initial installation, refer to “To Resolve Common Configuration Problems” on page 11.
6. On Windows, check the Event Viewer Application log for error messages that indicate why the tape mount did not complete.

NetBackup Status Code: 53

Message: backup restore manager failed to read the file list

Explanation: The backup and restore manager (bpbrm) could not read the list of files to back up or restore.

Recommended Action: Verify that the server software has been installed correctly on all NetBackup servers. If that is not the problem:

1. Create bpbrm and bpsched debug log directories on the server.
2. On a Windows NetBackup server, set the Verbose logging level option on the Universal Settings tab in the Master Server Properties dialog. To display this dialog, see “Using the Host Properties Window” on page 40.
3. Retry the operation and check the resulting debug logs for detailed troubleshooting information.

NetBackup Status Code: 54

Message: timed out connecting to client

Explanation: The server could not complete the connection to the client. The accept winsock call timed out after 60 seconds.

Recommended Action:



1. For a Macintosh or NetWare target client, verify that the server is not trying to connect when a backup or restore is already in progress on the client. These clients can handle only one NetBackup job at a time.

On a Macintosh, you can check for activity by examining the `NetBackupListen` file in the following folder on the startup disk of the Macintosh client:

```
:System Folder:Preferences:NetBackup:logs:inetd:log.mmddyy
```

2. Perform “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 56

Message: client’s network is unreachable

Explanation: An error was returned that the host was unreachable by the client (WSAENETUNREACH) when performing a system call.

Recommended Action: Try to ping the client from the server. Check the IP address for the client. If you still have problems, talk to your network administrator.

NetBackup Status Code: 57

Message: client connection refused

Explanation: The client refused a connection on the port number for `bpcd`. This can occur because there is no process listening on the `bpcd` port or there are more connections to the `bpcd` port than the network subsystem can handle with the `listen()` call.

Recommended Action:

1. For Windows NetBackup servers:
 - a. Make sure the NetBackup client software is installed.
 - b. Verify that the `bpcd` and `bprd` port numbers in the `%SystemRoot%\system32\drivers\etc\services` file on the server matches the setting on the client.
 - c. Verify that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Client Properties dialog match the `bpcd` and `bprd` settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface on the server and click NetBackup Client Properties on the File menu.

The values on the Network tab are written to the `services` file when the NetBackup Client service starts.



- d. Verify that the NetBackup client service is running.
- e. On Windows systems, for NetBackup 3.0 to NB3.1.1, the `install_path\winnt\system32\drivers\etc\services` file may not have correct information. The following entries are correct:

bpcd	13782/tcp
bprd	13720/tcp
- f. Use the following command to see if the master server returns correct information for the client:

```
install_path\Veritas\NetBackup\bin\admincmd\bpcintcmd -pn
```

2. For a Macintosh or NetWare target client, verify that the server is not trying to connect when a backup or restore is already in progress on the client. These clients can handle only one NetBackup job at a time.
3. Perform “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 58

Message: can't connect to client

Explanation: The server was unable to connect to the client.

Recommended Action: Perform “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 59

Message: access to the client was not allowed

Explanation: The master or media server is trying to access the client, but the server is not recognized by the client as a valid server.

Recommended Action:

1. If the server is a valid server, verify that it is in the server list on the client. If necessary add it as follows:
 - ◆ On Windows clients, add the server on the Servers tab in the Specify NetBackup Machines dialog box. To display this dialog, start the Backup, Archive, and Restore interface on the client and click Specify NetBackup Machines on the Actions menu.
 - ◆ On Macintosh clients, add a SERVER entry in the `bp.conf` file.
 - ◆ On NetWare target and OS/2 clients add a SERVER entry in the `bp.ini` file.



If you add or modify server entries on the master server, you must stop and then restart the NetBackup Request Manager and NetBackup Database Manager services.

2. On Windows clients, enable `bpinetd` debug logging as follows:
 - a. Create a `bpinetd` debug log directory on the client.
 - b. Increase the debug or log level as explained in the debug log topics in Chapter 3.
 - c. Retry the backup and examine the resulting logs to determine the cause of the failure.
3. On all but Macintosh clients, enable `bpcd` debug logging as follows:
 - a. Create a `bpcd` debug log directory on the client.
 - b. Increase the debug or log level as explained in the debug log topics in Chapter 3.
 - c. Retry the backup and examine the resulting logs to determine the cause of the failure.
4. On Macintosh clients, check the `inetd` and `bpcd` debug logs. Both logs are created automatically.
 - ◆ Check the `inetd` log to see if `NetBackupListen` is running.
 - ◆ Check the `bpbkar` and `tar` messages in the `bpcd` log file.

To increase the amount of information included in the logs, set the `loglevel` parameter in the `mac.conf` file to a higher value.
5. Check the `bpcd` debug log to determine the server's peername and what comparisons are being made.

The `bpcd` process compares NetBackup server list entries to the peername of the server attempting the connection and rejects the connection if the names are different. If necessary, change the server list entry on the client to match the peername.
6. On Windows clients, check the following:
 - ◆ Verify that NetBackup for Windows software was installed under a Windows administrator account.

If NetBackup is under another type of account, reinstall it under an administrator account. The installation will complete successfully under a non-administrator account but the NetBackup Client service is not added to Windows and the NetBackup server cannot access the client.



- ◆ Verify that the Windows TCP/IP service specifies the domain server that resolves names for the subnet that contains the NetBackup servers.
- 7. If the preceding steps do not resolve this problem, see “Resolving Network Communication Problems” on page 21.
- 8. If NetBackup is using multiple network interfaces with slave servers, make sure the interface names appear in the client’s `/usr/opensv/netbackup/bp.conf` file.

NetBackup Status Code: 63

Message: process was killed by a signal

Explanation: A kill signal was sent to the client process.

Recommended Action: This is usually caused by someone intentionally terminating a backup.

NetBackup Status Code: 64

Message: timed out waiting for the client backup to start

Explanation: The client did not send a ready message to the server within the allotted time.

Recommended Action:

1. On all but Macintosh clients, enable `bpcd` debug logging as follows:
 - a. Create a `bpcd` debug log directory on the client.
 - b. Increase the debug or log level as explained in the debug log topics in Chapter 3.
2. On Macintosh clients, check the `inetd` and `bpcd` debug logs. Both logs are created automatically.
 - ◆ Check the `inetd` log to see if `NetBackupListen` is running.
 - ◆ Check the `bpbkar` and `tar` messages in the `bpcd` log file.

To increase the logging level, set the `loglevel` parameter in the `mac.conf` file to a higher value.
3. On a Windows client, create the `bpbkar` debug log directory on the client.
4. On Windows clients, verify that the NetBackup Client service is running.
5. Retry the backup and examine the debug logs for clues on the cause of the failure.



NetBackup Status Code: 65

Message: client timed out waiting for the continue message from the media manager.

Explanation: The tape manager, `bptm` reported that the media did not load and position within the allotted time.

Recommended Action: Verify that the requested volume is available and the required device is in an UP state.

For detailed debug information:

1. Create a `bptm` debug log directory on the server.
2. On a Windows NetBackup server, set the Verbose logging level option on the Universal Settings tab in the Master Server Properties dialog (see “Using the Host Properties Window” on page 40).
3. Retry the operation and check the `bptm` debug log file for information on the drive, robot, and tape that is causing the timeout.
4. On a Windows NetBackup server (master or media), check the Event Viewer Application log for error messages that indicate why the tape mount did not complete.

NetBackup Status Code: 66

Message: client backup failed to receive the CONTINUE BACKUP message

Explanation: The client `bpbkar` process did not receive the message from the server that indicates that the server is ready to continue.

Recommended Action: Verify that the server did not crash. If that is not the problem and you need more information:

1. On Windows clients, enable `bpbkar` debug logging.
 - a. Create a `bpbkar` debug log directory.
 - b. On a Windows client, set Verbose on the Troubleshooting tab in the NetBackup Configuration dialog box. To display this dialog box, start the Backup, Archive, and Restore interface on the client and click Configure on the Actions menu.
2. On other PC clients except Macintosh, create a debug log directory for `bpcd` (the `bpcd` log is created automatically on Macintosh).

To increase the amount of information that appears in the logs, see the logging topics in Chapter 3.



3. On the master server create `bpsched` and `bpbrm` debug log directories. If there are media servers involved, create a `bpbrm` debug log directory on them.
4. Retry the operation and check the resulting debug logs.

NetBackup Status Code: 67

Message: client backup failed to read the file list

Explanation: The client could not read the list of files to back up.

Recommended Action: First, verify that the server did not crash. If that is not the problem and you need more information:

1. Set up debug logging:
 - a. On the server, create a `bpbrm` debug log directory.
 - b. On Windows clients, create a `bpbkarr` debug log directory.
 - c. On other PC clients except Macintosh, create a debug log directory for `bpcd` (the `bpcd` log is created automatically on Macintosh).

To increase the amount of information that appears in the logs, see the logging topics in Chapter 3.

2. Retry the operation and check the resulting debug logs.

NetBackup Status Code: 68

Message: client timed out waiting for the file list

Explanation: The client did not receive the list of files to back up within the allotted time. This list comes from the server.

Recommended Action: First, verify that the server did not crash. If that is not the problem and you need more information:

1. Set up debug logging:
 - a. On the server, create a debug log directory for `bpbrm`.
 - b. On Windows clients, create a `bpbkarr` debug log directory.
 - c. On other PC clients except Macintosh, create a debug log directory for `bpcd` (the `bpcd` log is created automatically on Macintosh).

To increase the amount of information that appears in the logs, see the logging topics in Chapter 3.

2. Retry the operation and check the resulting debug logs.

NetBackup Status Code: 69

Message: invalid file list specification

Explanation: The file list received from the server had invalid entries.

Recommended Action:

1. Check the policy file list. If wildcards are used, verify there are matching bracket characters ([and]). If the file list contains UNC (Universal Naming Convention) names, ensure they are properly formatted.
2. For NetBackup ServerFree Agent only:
If this was an offhost backup (NetBackup Media Server or Third-Party Copy Device), code 69 may indicate that the file list contains the ALL_LOCAL_DRIVES entry. NetBackup does not support the ALL_LOCAL_DRIVES entry for offhost backup. Remove the ALL_LOCAL_DRIVES entry from the file list.

NetBackup Status Code: NetBackup Status Code: 71

Message: none of the files in the file list exist

Explanation: The files in the file list did not match any of the files on the client. This error can occur when there is only one file in the file list and the file cannot be backed up due to an I/O error.

Recommended Action:

1. Verify that the correct file list is specified for this client.
2. On Windows clients, verify that the account used to start the NetBackup Client service has read access to the files.

If you are backing up a network drive or a UNC (universal naming convention) path, use the Services application in the Windows Control Panel to verify that the NetBackup Client service does not start under the SYSTEM account. The SYSTEM account cannot access network drives.

To back up network drives or UNC paths, change the NetBackup Client service startup to log in as a user that has permission to access network drives.
3. Check the All Log Entries report for clues.



4. Set up debug logging:

- ◆ On Windows clients, create a debug log directory for bpbkar.
- ◆ On other PC clients except Macintosh, create a debug log directory for bpcd (the bpcd log is created automatically on Macintosh).

To increase the amount of information that appears in the logs, see the logging topics in Chapter 3.

5. Retry the operation and check the resulting debug logs.

6. On Novell systems, check the following:

- ◆ For the nontarget version of NetBackup for NetWare, the backup policy type must be “NetWare”, and the files list should include a forward slash (/) only. There should be nothing else in the files list.

To check the policy type and files list, start Backup Policy Management and right-click the name of a policy. Click the Attributes tab to check the policy type; click the Files tab to check the contents of the files list.

- ◆ For the target version, the backup policy type must be “Standard”, and the policy files list must be formatted as follows:

/target_name

where a forward slash precedes the variable *target_name*.

To check the policy type and files list, start Backup Policy Management and right-click the name of a policy. Click the Attributes tab to check the policy type; click the Files tab to check the contents of the files list.

Note For the target version, the following NetWare message may be another indicator of incorrect policy type (this message would appear in the Novell client’s bpcd log):

unable to connect to service, scheduled access not specified

Make sure the policy type is set to “Standard”.

NetBackup Status Code: 72

Message: the client type is incorrect in the configuration database

Explanation: The policy type attribute in the policy configuration indicates that the client is one type, but the installed software is for another type.

Recommended Action: Verify that the policy type attribute for the policy is correct.



NetBackup Status Code: 73

Message: bpstart_notify failed

Explanation: The bpstart_notify script returned a nonzero exit code.

Recommended Action: Check the bpstart_notify script on the client to see if it performs as desired.

NetBackup Status Code: 74

Message: client timed out waiting for bpstart_notify to complete

Explanation: The bpstart_notify script on the client took too long.

Recommended Action: Try to speed up the bpstart_notify script or set Backup Start Notify Timeout on the server to a value that is larger than the default. Use the Master Server Properties window to set Backup Start Notify Timeout (see “Using the Host Properties Window” on page 40).

NetBackup Status Code: 75

Message: client timed out waiting for bpend_notify to complete

Explanation: The bpend_notify script on the client took too long.

Recommended Action: Try to speed up the bpend_notify script or set Backup End Notify Timeout on the server to a value that is larger than the default. Use the Master Server Properties window to set Backup End Notify Timeout (see “Using the Host Properties Window” on page 40).

NetBackup Status Code: 77

Message: execution of the specified system command returned a nonzero status

Explanation: An immediate command returned a nonzero status.

Recommended Action:

1. Verify that the command is specified correctly.
2. For NetBackup ServerFree Agent only:

The policy file list may contain files that do not reside *within a file system* that was designated as the frozen image source. For a frozen image method to be applied to the backup of individual files, the frozen image source must be a *file system* (not a raw partition or Volume Manager volume) and the files in the policy file list must reside within that file system.
3. Execute the command manually to see if the desired result is produced.



4. For detailed troubleshooting information, set up debug logging:
 - a. On UNIX and Windows clients, create a debug log directory for `bpbkar`.
 - b. On other PC clients except Macintosh, create a debug log directory for `bpcd` (the `bpcd` log is created automatically on Macintosh).

To increase the amount of information that appears in the logs, see the logging topics in Chapter 3.
 - c. Retry the operation and check the resulting debug log.

NetBackup Status Code: 78

Message: afs/dfs command failed

Explanation: Indicates an AFS `vos` command failure.

Recommended Action:

1. Check the NetBackup Problems Report for additional information on why the command failed.
2. The `bpbkar` debug log shows the command that was executed. Create a debug log directory for `bpbkar`. Retry the operation and retry the resulting debug log.
3. Try executing the `vos` command manually to duplicate the problem.

NetBackup Status Code: 80

Message: Media Manager device daemon (`ltid`) is not active

Explanation: The NetBackup Device Manager service is not running.

Recommended Action:

1. Use the Activity Monitor or the Services application in the Windows Control Panel to see if the NetBackup Device Manager service is running. If it is not running, start it. To enable verbose logging, place `VERBOSE` on a line by itself in the `install_path\Volmgr\vm.conf` file before starting the service.

Note The NetBackup Device Manager service is used only if devices are attached to the system.

NetBackup Status Code: 81

Message: Media Manager volume daemon (`vmd`) is not active



Explanation: The tape manager (bptm) could not communicate with the NetBackup Volume Manager service. This communication is required for most operations.

Recommended Action: On Windows, verify that both the NetBackup Device Manager service and the NetBackup Volume Manager service are running. Start them if necessary.

Note The NetBackup Device Manager service is used only if devices are attached to the system.

NetBackup Status Code: 82

Message: media manager killed by signal

Explanation: The tape manager (bptm) or disk manager (bpdm) was terminated by another process or a user.

Recommended Action: This should not occur in normal operation. If you want to terminate an active backup, use the NetBackup Activity Monitor.

NetBackup Status Code: 83

Message: media open error

Explanation: The tape manager (bptm) or disk manager (bpdm) could not open the device or file that the backup or restore must use.

Recommended Action:

1. For additional information, check the following:
 - ◆ NetBackup Problems report
 - ◆ Event Viewer Application log
2. Typically, this status code indicates a drive configuration problem that allows more than one process at a time to open the device.

 On Windows, the problem could be that the Media Manager device configuration was modified but the NetBackup Device Manager service was not restarted. Verify the configuration and restart the NetBackup Device Manager service.
3. Make sure the tapes are not write protected.
4. For detailed troubleshooting information:



- a. Create a debug log directory for `bpdm` (if the device is disk) or `bptm` (if the device is tape).
- b. On Windows, enable verbose logging by adding `VERBOSE` on a line by itself in the `install_path\Volmgr\vm.conf` file. Then, stop and restart the NetBackup Device Manager service.
- c. Retry the operation and check the resulting debug log files.
- d. On Windows systems, look at the `install_path\Veritas\NetBackup\db\media\errors` log for a drive that is frequently producing errors.

NetBackup Status Code: 84

Message: media write error

Explanation: The system's device driver returned an I/O error while NetBackup was writing to removable media or a disk file.

Recommended Action:

1. For NetBackup ServerFree Agent only:

If the following message appears in the `/usr/openv/netbackup/bptm` log, and the values for `key`, `asc`, and `ascq` are all *zero* (0x0) as shown in this example message:

```
tape error occurred on extended copy command, key = 0x0, asc = 0x0,
ascq = 0x0
```

your host-bus adapter and its driver are probably not supported by NetBackup 4.0V. The host-bus adapters and drivers supported in the release are listed in Chapter 2 of the *NetBackup Release Notes*.

2. For additional information, check the following:
 - ◆ NetBackup Problems report to determine the device or media that caused the error
 - ◆ Event Viewer Application and System logs
3. If NetBackup was writing backups to a disk file, verify that the disk has enough space for the backup.
4. If the media is tape, check for:
 - ◆ A defective or dirty drive, in which case, clean it or have it repaired (refer to the `tpclean` command for robotic drives).



- ◆ The wrong media type. Verify that the media matches the drive type you are using.
- ◆ Defective media. If this is the case, use the `bpmedia` command to set the volume to the FROZEN state so it is not used for future backups.
- ◆ Incorrect drive configuration. Verify the Media Manager and system configuration for the drive.

This often results in the media being frozen with a message, “too many data blocks written, check tape/drive block size configuration.”

NetBackup Status Code: 85

Message: media read error

Explanation: The system device driver returned an I/O error while NetBackup was reading from tape or a disk file.

Recommended Action:

1. For additional information, check the following:
 - ◆ NetBackup Problems report to determine the device or media that caused the error
 - ◆ Event Viewer Application and System logs
2. Check for the following:
 - ◆ A defective or dirty drive. Clean it or have it repaired (see the `tpclean` command for cleaning).
 - ◆ Incorrect drive configuration. Verify the Media Manager and system configuration for the drive.
 - ◆ Defective media. In this case, you may not be able to recover all the data on the media. Use the `bpmedia` command to set the volume to the FROZEN state so it is not used for future backups.
 - ◆ The wrong media type. Verify that the media matches the drive type you are using.

NetBackup Status Code: 86

Message: media position error

Explanation: The system's device driver returned an I/O error while NetBackup was positioning media (tape).

Recommended Action:

1. For additional information, check the following:
 - ◆ NetBackup Problems report to determine the device or media that caused the error
 - ◆ Event Viewer Application and System logs
2. Check for the following:
 - ◆ A defective or dirty drive. Clean it or have it repaired (see the `tpclean` command for cleaning).
 - ◆ Incorrect drive configuration. Verify the Media Manager and system configuration for the drive.
 - ◆ Defective media. In this case, some data may be lost. Use the `bpmedia` command to set the volume to the FROZEN state so it is not used for future backups.
 - ◆ The wrong media type. Verify that the media matches the drive type you are using.

NetBackup Status Code: 87

Message: media close error

Explanation: The system's device driver returned an I/O error while NetBackup was closing a tape.

Recommended Action:

1. For additional information, check the following:
 - ◆ NetBackup Problems report to determine the device or media that caused the error
 - ◆ Event Viewer Application and System logs
2. Check for the following:
 - ◆ A defective or dirty drive. Clean it or have it repaired (see the `tpclean` command for cleaning).
 - ◆ Defective media. In this case, some data may be lost. Use the `bpmedia` command to set the volume to the FROZEN state so it is not used for future backups.

NetBackup Status Code: 88

Message: Auspex SP/Backup failure

Explanation: NetBackup detected a problem when backing up an Auspex FastBackup client.



Recommended Action: Check the All Log Entries report. If more details are required, create `bptm` and `bpbem` debug log directories on the server. Then, retry the operation and check the resulting log files. This error is usually due to a configuration problem.

NetBackup Status Code: 90

Message: media manager received no data for backup image

Explanation: The tape manager (`bptm`) or disk manager (`bpdm`) received no data when performing a backup or archive. This can occur for incremental backups where no data was backed up because no files have changed.

Recommended Action:

1. Check the All Log Entries report.
2. For detailed debug information, create `bpdm` or `bptm` debug log directories on the server. If the client is Windows, also create a `bpbkar` debug log directory on the client. Retry the operation and check the resulting debug logs.

NetBackup Status Code: 91

Message: fatal NB media database error

Explanation: The tape manager (`bptm`) received an error while reading or updating its media catalog.

Recommended Action:

1. Check the All Log Entries report for more information.
2. Check the NetBackup Media Lists report to see if the catalog is intact. If the catalog is not intact, consider reloading it from the latest NetBackup catalog backup volume.
3. Verify that the disk partition on which the catalog resides has enough space.
4. If the above actions do not explain the problem, check the NetBackup Problems report.
5. For detailed troubleshooting information, create a `bptm` debug log directory on the server and retry the operation. Check the resulting debug log file.
6. Contact customer support and send appropriate problem and debug log sections.

NetBackup Status Code: 92

Message: media manager detected image that was not in tar format



Explanation: When performing a restore, the tape manager (bptm) or disk manager (bpdm) could not find a tar header at the offset it expected.

Recommended Action:

1. Perform a bpverify of the affected image to determine if it is written correctly.
2. Check the NetBackup Problems report for additional information about the error.
3. Verify the Media Manager and system configuration for the drive.
4. Error code 92 has been encountered on some relabeled and value-added 8-mm tape drives where the drive's microcode incorrectly processes a "forward space record" SCSI command.
5. If the problem is not one of the above, create a debug log directory for either bpdm or bptm and retry the operation. Check the resulting debug log file.

NetBackup Status Code: 93

Message: media manager found wrong tape in drive

Explanation: When loading a volume for a backup or restore, the tape manager (bptm) found a volume loaded that did not have the expected tape header. This can indicate that volumes in a robot are not in the slots indicated in the Media Manager volume configuration.

Recommended Action:

- ◆ If the volume is in a robot and the robot supports barcodes, perform a Compare Contents with Volume Configuration. The resulting report shows which media ID was found and validates its slot number with what is in the Media Manager volume configuration. Then, either change the physical location in the robot or change the volume configuration to show the correct slot.
- ◆ If the volume was mounted on a nonrobotic drive, verify that the correct volume was mounted and assigned.

NetBackup Status Code: 94

Message: cannot position to correct image

Explanation: When searching for a backup image to restore, the tape manager (bptm) did not find the correct backup ID at the expected position on the volume. This can indicate a drive hardware problem.

Recommended Action:



1. Try the restore on another drive if possible.
2. For additional information, check the following:
 - ◆ NetBackup Problems report to determine the device or volume that caused the error
 - ◆ Event Viewer Application and System logs
3. For detailed troubleshooting information, create a debug log directory for `bptm` and retry the operation. Check the resulting debug log files.

NetBackup Status Code: 95

Message: requested media id not found in NB media database and/or MM volume database

Explanation: An operation was requested on a media ID for which NetBackup does not have a record. An example of this is using `bpmedia` to suspend or freeze a media ID that does not exist.

Recommended Action: Run a NetBackup Media List report to determine the valid media IDs. Then, retry the command with a valid media ID.

NetBackup Status Code: 96

Message: unable to allocate new media for backup, storage unit has none available

Explanation: The tape manager (`bptm`) could not allocate a new volume for backups. This indicates that the storage unit has no more volumes available in the volume pool for this backup.

Recommended Action: Check the NetBackup Problems report to determine the storage unit that is out of media.

1. If the storage unit is a robot and there are empty slots, add more volumes (remember to specify the correct volume pool).
 - ◆ If there are no empty slots, move some media to nonrobotic and then add new volumes.
 - ◆ If you are having difficulty keeping track of your available volumes, try the `available_media` script:

On Windows, the script is in:

`install_path\NetBackup\bin\goodies\available_media.cmd`



This script lists all volumes in the Media Manager volume configuration, and augments that list with information on the volumes currently assigned to NetBackup.

2. If the storage unit and volume pool appear to have media, verify the following:

- ◆ Volume is not FROZEN or SUSPENDED.

Check for this condition by using the NetBackup Media List report. If the volume is frozen or suspended, use the `bpmedia` command to unfreeze or unsuspend it (if that is desired).

- ◆ Volume has not expired or exceeded its maximum number of mounts.

- ◆ Volume Database Host name for the device is correct.

If you change the Volume Database Host name, stop and restart the NetBackup Device Manager service.

- ◆ The correct host is specified for the storage unit in the NetBackup configuration.

The host connection should be the server (master or media) that has drives connected to it.

- ◆ The Media Manager volume configuration has media in the correct volume pool and unassigned or active media is available at the required retention level.

Use the NetBackup Media List report to show the retention levels, volume pools, and status (active and so on) for all volumes. Use the NetBackup Media Summary report to check for active volumes at the correct retention levels.

3. In some configurations, the NetBackup `bptm` process is rejected when requesting media from the NetBackup Volume Manager service because that service cannot determine the name of the host that is making the request.

This can be due to incorrect network configuration involving:

- ◆ Multiple network interfaces
- ◆ Running DNS and not having reverse addressing configured

4. Create `bptm` and `vmd` debug log directories and retry the operation.

5. Examine the `bptm` debug log to verify that `bptm` is connecting to the correct system. If an error is logged, examine the `vmd` log.

On Windows, the `vmd` log is:

`install_path\Volmgr\debug\daemon\xxxxxx.log`

6. If this is a new storage unit, and this is the first attempt to use it, stop and restart NetBackup on the master server.



Note The bptm debug logs (in verbose mode) usually show the NetBackup media selection process.

NetBackup Status Code: 97

Message: requested media id is in use, cannot process request

Explanation: An operation was requested on a media ID that is in use. An example of this is attempting to suspend or freeze a volume while it is being used for a backup or restore.

Recommended Action: Retry the command when the volume is not in use. Use the Device Monitor to determine if the volume is in use.

NetBackup Status Code: 98

Message: error requesting media (tpreq)

Explanation: The tape manager (bptm) received an error when requesting a media mount from the NetBackup Device Manager service.

Recommended Action: Check the NetBackup Problems report to determine the reason for the failure. The most common cause is that the NetBackup Device Manager service on Windows is not running. Start it if necessary.

NetBackup Status Code: 99

Message: NDMP backup failure

Explanation: None of the paths in your NDMP policy file list was backed up successfully.

Recommended Action: Check the NetBackup All Log Entries report for more information. A possible cause for this error is that none of the backup paths exist on the NDMP host.

NetBackup Status Code: 100

Message: system error occurred while processing user command

Explanation: A system call failed in bparchive, bpbackup, bplist, or bprestore.

Recommended Action:

1. Enable debug logging for bparchive, bpbackup, bplist, or bprestore (as appropriate) by creating debug log directories for them.
2. Retry the operation and check the resulting logs.



If the logs do not reveal the problem, use the command line version of the command and correct any problems that are reported on stderr.

NetBackup Status Code: NetBackup Status Code: 102

Message: failed closing mail pipe

Explanation: The process that sends mail could not close the pipe to the server.

Recommended Action: Verify that mail is configured on the client. For detailed troubleshooting information, create a bpcd debug log directory and retry the operation. Check the resulting bpcd debug log.

NetBackup Status Code: 103

Message: error occurred during initialization, check configuration file

Explanation: None

Recommended Action: None

NetBackup Status Code: 104

Message: invalid file pathname

Explanation: None

Recommended Action: None

NetBackup Status Code: 105

Message: file pathname exceeds the maximum length allowed

Explanation: The path name built by using the current working directory exceeds the maximum path length allowed by the system.

Recommended Action: Shorten the current working directory path length.

NetBackup Status Code: 106

Message: invalid file pathname found, cannot process request

Explanation: One of the file paths to be backed up or archived is not valid.

Recommended Action: Verify that full path names are used, and they are less than the maximum path length for the system. Also, verify that the files exist and the permissions allow NetBackup to access them.

NetBackup Status Code: 110

Message: Cannot find the NetBackup configuration information

Explanation: On Windows, NetBackup could not read the registry entries that were created during installation. On UNIX, the `/usr/opensv/netbackup/bp.conf` file does not exist.

Recommended Action: On Windows, reinstall NetBackup software on the client. On UNIX, create a `/usr/opensv/netbackup/bp.conf` file with at least the following lines:

```
SERVER = server_name
CLIENT_NAME = client_name
```

NetBackup Status Code: 111

Message: No entry was found in the server list

Explanation: On UNIX, the `SERVER = server_name` line is missing in the `bp.conf` file. On Windows, the server list contains no entries.

Recommended Action:

- ◆ On a UNIX client, add the following line to the top of the `/usr/opensv/netbackup/bp.conf` file:
`SERVER = server_name`
- ◆ On a Microsoft Windows or nontarget NetWare client, add the server name on the Servers tab in the Specify NetBackup Machines dialog box. To display this dialog, start the Backup, Archive, and Restore interface on the client and click Specify NetBackup Machines on the Actions menu.
- ◆ On an OS/2 or NetWare target client, add the server name to the `bp.ini` file.
- ◆ On a Macintosh client, add the `SERVER = server_name` line to the `bp.conf` file in the NetBackup folder in the Preferences folder.

NetBackup Status Code: 112

Message: no files specified in the file list

Explanation: A restore was requested with no files in the file list.

Recommended Action: Specify at least one file to be restored.

NetBackup Status Code: 113

Message: EC_badop

Explanation: None



Recommended Action: None

NetBackup Status Code: 114

Message: EC_error

Explanation: None

Recommended Action: None

NetBackup Status Code: 115

Message: EC_end

Explanation: None

Recommended Action: None

NetBackup Status Code: 120

Message: cannot find configuration database record for requested NB database backup

Explanation: The program that backs up the NetBackup internal catalogs could not find the attributes that indicate which media IDs to use or paths to back up. This error should not occur under normal circumstances.

Recommended Action:

1. Check the NetBackup Problems report for additional information about the error.
2. For detailed troubleshooting information, create `admin` and `bpdbm` debug log directories and retry the operation. Check the resulting debug logs.
3. Contact customer support and send appropriate problem and debug log sections detailing the error.

NetBackup Status Code: 121

Message: no media is defined for the requested NB database backup

Explanation: NetBackup attempted to back up its internal catalogs and there were no media IDs defined in the catalog backup configuration.

Recommended Action: Add the media IDs to the catalog backup configuration. Verify that the media IDs are in the NetBackup volume pool.

NetBackup Status Code: 122

Message: specified device path does not exist



Explanation: The NetBackup internal catalogs were backed up by using the `bpbackupdb` command line and specifying a device path that does not exist.

Recommended Action: Retry the command using a valid device file name.

NetBackup Status Code: 123

Message: specified disk path is not a directory

Explanation: NetBackup attempted to back up its internal catalogs and the backup attributes were set to dump to a disk. However, the disk file path already exists and is not a directory.

Recommended Action: Specify a different disk path for the catalog backup or delete the file that already exists.

NetBackup Status Code: 124

Message: NB database backup failed, a path was not found or is inaccessible

Explanation: One or more of the paths specified in the catalog backup configuration could not be backed up.

Recommended Action:

1. Check the NetBackup Problems report for additional information about the error. A possible cause is that the path does not exist.
2. After determining which path could not be accessed, correct the path names in the catalog backup configuration.

NetBackup Status Code: 125

Message: another NB database backup is already in progress

Explanation: Only one NetBackup catalog backup may be active at any given time.

Recommended Action: None.

NetBackup Status Code: 126

Message: NB database backup header is too large, too many paths specified

Explanation: Too many paths were specified in the NetBackup catalog backup configuration to fit in a fixed-size media header. This error should not occur under normal circumstances.

Recommended Action: Delete some of the paths from the catalog backup configuration.



NetBackup Status Code: 127

Message: specified media or path does not have a valid NB database backup header

Explanation: The `bprecover` command was issued and the media ID specified does not have valid catalog backup data.

Recommended Action: Validate that the correct media ID is being used.

NetBackup Status Code: 128

Message: NB database recovery failed, a process has encountered an exceptional condition

Explanation: One or more catalogs specified for recovery could not be restored. For more detail, refer to the error message issued just above this status code in the output from the `bprecover` command.

Recommended Action:

1. After fixing the problem reported in the error message in the `bprecover` output, refer to “Recovering the NetBackup Catalogs” on page 409 to identify which NetBackup services (Windows) or daemons (UNIX) should be shut down prior to attempting the NetBackup database recovery. The NetBackup services should be shut down except for the NetBackup Client Service, which must be running for the database recovery to succeed.
2. Check the NetBackup Problems report for additional information about the error. Some possible causes are:
 - ◆ A disk may be full.
 - ◆ The NetBackup catalog tape may be corrupt.

NetBackup Status Code: 130

Message: system error occurred

Explanation: An error occurred that prevents the product from operating in a consistent fashion. This error is usually related to a system call.

Recommended Action:

1. Check the NetBackup Problems report for additional information about the error.
2. For detailed troubleshooting information, create `bpdbm`, `bpsched`, `bptm`, and `bprd` debug log directories on the master server and retry the operation. Check the resulting debug logs.

NetBackup Status Code: 131

Message: client is not validated to use the server

Explanation: The client name, as determined from the connection to the server, did not match any client name in the NetBackup configuration and there was no `altnames` configuration for this client on the master server. A client and server that have multiple network connections can encounter this problem if the name by which the client is configured is not the one by which its routing tables direct connections to the server.

Recommended Action:

1. Examine the NetBackup Problems report.
2. Create a debug log directory for `bprd` and retry the operation. Check the resulting debug log to determine the connection and client names.
Depending on the request type (restore, backup, and so on.), you may need or want to:
 - ◆ Change the client's configured name.
 - ◆ Modify the routing tables on the client.
 - ◆ On the master server, set up an `altnames` directory and file for this client (see the *NetBackup System Administrator's Guide for Windows*).
3. Review "Verifying Host Names and Services Entries" on page 25.

NetBackup Status Code: 132

Message: user is not validated to use the server

Explanation: None

Recommended Action: None

NetBackup Status Code: 133

Message: invalid request

Explanation: One of two explanations exist.

- ◆ A request was made that is unrecognized. This usually results from different versions of NetBackup software being used together.
- ◆ If a client receives this error in response to a list or restore request, it means that the `DISALLOW_CLIENT_LIST_RESTORE` or `DISALLOW_CLIENT_RESTORE` option exists in the registry on a Windows NetBackup server. These options deny list and restore requests from all NetBackup clients.



Recommended Action:

1. If you suspect that the software versions are the problem, verify that all NetBackup software is at the same version level.
 - ◆ On Windows NetBackup servers, check the `install_path\netbackup\version.txt` file or the About NetBackup item on the Help menu.
 - ◆ On Microsoft Windows clients, check the About NetBackup item on the Help menu.
 - ◆ On NetWare target clients, check the Version entry in the `bp.ini` file.
If the client software is earlier than 3.0, verify that the client is in a Standard type policy.
 - ◆ On Macintosh clients, check the version file in the bin folder in the NetBackup folder in the Preferences folder.
2. If the server is denying list and restore requests, remove the `DISALLOW_CLIENT_LIST_RESTORE` and `DISALLOW_CLIENT_RESTORE` options from the registry on a Windows NetBackup server. Then, stop and restart the NetBackup Request Manager service.
3. For detailed troubleshooting information, create `bpdbm`, `bprd`, and `admin` debug log directories. Then, retry the operation and check the resulting debug logs.

NetBackup Status Code: 134

Message: unable to process request because the server resources are busy

Explanation: Status code 134 is an informational message indicating that all drives in the storage unit are currently in use. If this occurs, NetBackup automatically tries another storage unit; if one is not available, NetBackup queues the job with a status of 134 and retries it later.

Recommended Action: Disable automatic retry using another storage unit and create the following file on the NetBackup media server prior to running the backups:

```
/usr/openv/volmgr/DISABLE_RESOURCES_BUSY
```

If you have already attempted the backup and see this error, then create the file and rerun the backups.

NetBackup Status Code: 135

Message: client is not validated to perform the requested operation

Explanation: This is usually caused by a request to restore files to a client other than the one that made the request and the request did not come from the administrator on a NetBackup server.

Recommended Action: Retry the operation as the administrator on the master server. Also see status code 131.

NetBackup Status Code: 140

Message: user id was not superuser

Explanation: The process was started by a user or process that did not have administrator privileges.

Recommended Action: If desired, give administrator privileges to the user or process and retry the operation.

NetBackup Status Code: 141

Message: file path specified is not absolute

Explanation: The file specification must be an absolute path.

Recommended Action: Correct the file specification and retry the command.

NetBackup Status Code: 142

Message: file does not exist

Explanation: This code is reserved for future use.

Recommended Action: None.

NetBackup Status Code: 143

Message: invalid command protocol

Explanation: An ill-formed request was made to the NetBackup Request Manager service. This can be due to mismatched versions of the product, corrupted network communication, or to a non-NetBackup process sending data across the port for the service.

Recommended Action: Examine the NetBackup error logs to determine the system that was the source of the data and on that system determine the process that initiated the request. If it was a NetBackup process, verify that the process or command is compatible with the version of software on the server.



NetBackup Status Code: 144

Message: invalid command usage

Explanation: This status code is due to a NetBackup process being started with improper options or an incompatibility in the product.

Recommended Action: Either correct the command or verify that all NetBackup binaries are at the same version level.

NetBackup Status Code: 145

Message: daemon is already running

Explanation: There is another copy of the process executing.

Recommended Action: Terminate the current copy of the process and then restart the process.

NetBackup Status Code: 146

Message: cannot get a bound socket

Explanation: The service could not bind to its socket. A system call failed when the service attempted to bind to its configured port number. This is usually caused by another process having acquired the port before the service started.

Recommended Action:

1. Examine the NetBackup Problems and All Log Entries reports.
2. Create bprd and bpdbm debug log directories and retry the operation. Check the resulting logs to see the system error message resulting from the attempt.

If another process has the port, use other system commands to determine the process. Based on this research, either change the port number in your `services` file or map or terminate the process that has acquired the port.

To identify a bprd or bpdbm problem, look for lines similar to the following in the debug log for the respective process:

```
<16> getsockbound: bind() failed, Address already in use (114)
<32> listen_loop: cannot get bound socket. errno = 114
<4> terminate: termination begun...error code = 146
```

Similar entries can appear in the reports.

3. If the problem persists longer than ten minutes, it is possible that it will be necessary to reboot the server.

NetBackup Status Code: 147

Message: required or specified copy was not found

Explanation: The requested copy number of a backup or archive image cannot be found.

Recommended Action: Correct the request to specify a copy number that does exist.

NetBackup Status Code: 148

Message: daemon fork failed

Explanation: A NetBackup service could not create a child process due to an error received from the system. This is probably an intermittent error based on the availability of resources on the system.

Recommended Action:

1. Restart the service at a later time and investigate system problems that limit the number of processes.
2. Check the Event Viewer Application and System logs.

NetBackup Status Code: 149

Message: master server request failed

Explanation: None

Recommended Action: None

NetBackup Status Code: 150

Message: termination requested by administrator

Explanation: The process is terminating (or has terminated) as a direct result of a request from an authorized user or process.

Recommended Action: None.

NetBackup Status Code: 151

Message: Backup Exec operation failed

Explanation: The Global Data Manager console has reported that a Backup Exec job (backup, archive, or restore) did not complete normally.

Recommended Action: Consult the Backup Exec job history on the Backup Exec server for details.



NetBackup Status Code: 152

Message: required value not set

Explanation: An incomplete request was made to the `bpdbm` process (NetBackup Database Manager service). This usually occurs because different versions of software are being used together.

Recommended Action:

1. Verify that all software is at the same version level.
2. For detailed troubleshooting information, create `bpdbm` and `admin` debug log directories and retry the operation. Check the resulting debug logs.

NetBackup Status Code: 153

Message: server is not the master server

Explanation: This status code is reserved for future use.

Recommended Action: None.

NetBackup Status Code: 154

Message: storage unit characteristics mismatched to request

Explanation: A backup was attempted and the storage unit selected for use had characteristics that were not compatible with the backup type.

Recommended Action: Verify that the characteristics of the storage unit involved are appropriate for the backup attempted:

- ◆ For NetBackup ServerFree Agent only:
The policy storage unit was set to `Any_available` and the offhost backup method was set to `Third-Party Copy Device` or `NetBackup Media Server`. Do not choose `Any_available`. A particular storage unit (such as `nut-4mm-robot-t14-0`) must be specified when `Third-Party Copy Device` or `NetBackup Media Server` is specified as the offhost backup method.
- ◆ For an NDMP policy type, verify that a storage unit of type NDMP is defined and the NDMP host value matches the host name of the client. For example, if the NDMP policy specifies `toaster` as the client, the configuration for the storage unit must specify `toaster` as the NDMP host.
- ◆ For a policy type other than NDMP, verify that the policy specifies a Media Manager or Disk type storage unit.

NetBackup Status Code: 158

Message: failed accessing daemon lock file

Explanation: The process could not lock its lock file because an error was received from a system call. This lock file synchronizes process activities (for example, preventing more than one daemon from executing at a time).

Recommended Action:

1. Examine the NetBackup error log to determine why the system call failed and correct the problem. It could be a permission problem.
2. If the error log does not show the error, create a debug log directory for `bprd`, `bpdbm`, or `bpsched` (depending on which process encountered the error) and retry the operation. Examine the resulting debug log.

NetBackup Status Code: 159

Message: licensed use has been exceeded

Explanation: A configuration limit has been exceeded. An example is number of drives allowed per server.

Recommended Action: To determine the cause, examine the NetBackup error logs for the command that was being executed.

NetBackup Status Code: 160

Message: authentication failed

Explanation: A problem was encountered when two systems were attempting to authenticate one another.

Recommended Action: See the *NetBackup System Administrator's Guide for Windows* for more information on the files and commands mentioned here.

1. Ensure that the authentication libraries exist:

Windows:

```
install_path\NetBackup\lib\libvopie.dll
install_path\NetBackup\lib\libnoauth.dll
```

UNIX (except HP-UX):

```
/usr/opensv/lib/libvopie.so
/usr/opensv/lib/libnoauth.so
```

UNIX (HP-UX only):



```
/usr/opensv/lib/libvopie.sl  
/usr/opensv/lib/libnoauth.sl
```

Macintosh:

```
:System Folder:Extensions:libvopie.dll  
:System Folder:Extensions:libnoauth.dll
```

2. Check the `methods_allow.txt` files on the systems that are having problems to ensure that authentication is enabled. The files are in the following locations:

Windows:

```
install_path\NetBackup\var\auth
```

Macintosh:

```
:System Folder:Preferences:NetBackup:var:auth
```

If one system reports authentication failed (status code 160) and the other system reports network connection timed out (status code 41), you may have enabled authentication in the first system's `methods_allow.txt` file but not in the second system's `methods_allow.txt` file.

3. On the systems that are having the authentication problem, remove the remote host that is not being authenticated from the `methods_allow.txt` file.

For example, if host A and host B are having the problem, remove host A from the file on host B and vice versa.

Retry the operation.

- ◆ If the problem still exists, it indicates connection problems not related to authentication.
- ◆ If connections are now successful, proceed to the next step.

4. Execute `bpauthsync -vopie` on the master server to resynchronize the key files on the systems.

```
install_path\NetBackup\bin\admincmd\bpauthsync -vopie -servers  
-clients
```

5. Add back the names removed in step 3 and retry the operation.
6. Create debug log directories for the processes involved in authentication between NetBackup systems. These include:
 - ◆ On the server, create debug log directories for `bprd`, `bpdbm`, `bpcd`.
 - ◆ On the client, create debug log directories for `bpbackup`, `bprestore`, `bpbkar` (Windows only).

Retry the operation and check the logs.

NetBackup Status Code: 161

Message: Evaluation software has expired. See www.veritas.com for ordering information.

Explanation: The time allowed for the NetBackup evaluation software has ended.

Recommended Action: Obtain a licensed copy of NetBackup.

NetBackup Status Code: 162

Message: Incorrect server platform for license

Explanation: The platform identifier in the license key does not match the platform type on which the key was installed.

Recommended Action: Ensure that you are using a license key that was intended for the platform on which you are installing.

NetBackup Status Code: 164

Message: unable to mount media because it is in a DOWN drive or misplaced

Explanation: A restore was attempted and the volume required for the restore was in a DOWN drive in a robot. Or, the slot that should contain the volume is empty.

Recommended Action:

- ◆ If volume is in a DOWN drive, remove it and place it in its designated slot. Then, retry the restore.
- ◆ If the volume is in the wrong slot, use a robot inventory option to reconcile the contents of the robot with the Media Manager volume configuration.

NetBackup Status Code: 165

Message: NB image database contains no image fragments for requested backup id/copy number

Explanation: A restore was attempted and NetBackup has no record of fragments associated with the backup ID that has the files.

Recommended Action: Check the NetBackup Problems report for additional information about the error. For detailed troubleshooting information, create a debug log directory for either `bpdm` or `bptm` (whichever applies) and retry the operation. Check the resulting debug log.



NetBackup Status Code: 166

Message: backups are not allowed to span media

Explanation: An end of media (EOM) was encountered while the backup image was being written. The backup was terminated because the NetBackup `DISALLOW_BACKUPS_SPANNING_MEDIA` option was present in the registry. The backup will be retried automatically with a different volume if this is allowed by the backup tries attribute in the NetBackup global attribute configuration.

Recommended Action: None.

NetBackup Status Code: 167

Message: cannot find requested volume pool in Media Manager volume database

Explanation: A backup to a nonrobotic drive was attempted and the tape manager (bptm) could not find or add the specified volume pool.

Recommended Action: Verify the Media Manager volume configuration. Check the NetBackup Problems report for more information about the error. For detailed troubleshooting information, create a bptm debug log directory and retry the operation. Check the resulting debug log.

NetBackup Status Code: 168

Message: cannot overwrite media, data on it is protected

Explanation: A catalog backup was attempted to a volume that could not be overwritten because it contains data that NetBackup, by default, does not overwrite (tar, cpio, ANSI, and so on).

Recommended Action: Replace the volume with a new one or set the NetBackup `ALLOW_MEDIA_OVERWRITE` option to the appropriate value.

NetBackup Status Code: 169

Message: media id is either expired or will exceed maximum mounts

Explanation: A backup or catalog backup was attempted and the volume selected for use has reached its maximum number of mounts as specified in the Media Manager volume configuration. For a regular backup, the volume is automatically set to the SUSPENDED state and not used for further backups. For a NetBackup catalog backup, the operation terminates abnormally.

Recommended Action: If the volume was suspended, wait until it expires and then replace it. For NetBackup catalog backups, replace the media.

NetBackup Status Code: 170**Message:** third-party copy backup failure

Explanation: Usually indicates a problem with the `3pc.conf` file or the `mover.conf` file. (For detailed causes, see recommended actions.) For more information on these files, refer to “Creating Configuration Files for Offhost Backup” in NetBackup Configuration chapter of the *NetBackup ServerFree Agent System Administrator's Guide*.

Recommended Action:

- ◆ If a *non* third-party copy device is listed in `3pc.conf` file, correct or remove the non third-party copy device entry.
- ◆ An incorrect `lun` is specified in the `3pc.conf` file, or the device does not exist. Correct the `3pc.conf` file as appropriate.
- ◆ An appropriate `mover.conf` file (with or without file-name extension) could not be found. In this case, the `/usr/openv/netbackup/logs/bptm` log may also show the following:

```
09:51:04 [22281] <2> setup_mover_tpc: no mover.conf.vertex_std_tpc
or mover.conf file exists, cannot perform TPC backup
09:51:04 [22281] <16> bptm: unable to find or communicate with
Third-Party-Copy mover for policy vertex_std_tpc
```

Make sure that an appropriate `mover.conf` file exists in `/usr/openv/netbackup` on the media server. This file can be any of the following:

- ◆ `mover.conf.policy_name` file, where *policy_name* exactly matches the name of the policy.
- ◆ `mover.conf.storage_unit_name`, where *storage_unit_name* exactly matches the name of the storage unit selected in the Backup Policy Management Policy attributes dialog (such as `nut-4mm-robot-tl4-0`).
- ◆ `mover.conf` file (no extension) for configurations that have only one third-party copy device.

Note that NetBackup looks for an appropriate `mover.conf` file in the above order.

- ◆ The SCSI pass-through path of the third-party copy device, as entered in the `mover.conf` file (with or without file-name extension), does not exist. In this case, the `/usr/openv/netbackup/logs/bptm` log may also show the following:

```
09:50:12 [22159] <16> setup_mover_tpc: open of passthru path
/dev/sg/cXtXlX failed, No such file or directory
09:50:12 [22159] <16> bptm: unable to find or communicate with
Third-Party-Copy mover for policy vertex_std_tpc
```

Correct the SCSI pass-through path of the third-party copy device that is entered in the `mover.conf` file.



- ◆ The third-party copy device returned an error.

If you see either of the following messages in `/usr/openv/netbackup/logs/bptm log`:

```
cannot process extended copy error due to truncated  
sense data, may be HBA problem
```

```
disk error occurred on extended copy command, key = 0x0,  
asc = 0x0, ascq = 0x0      (where key, asc and ascq are all zero)
```

your host-bus adapter (HBA) and its driver may need to be updated, or may not be supported by NetBackup ServerFree Agent. The host-bus adapters and drivers supported in the release are listed in Chapter 2 of the *NetBackup Release Notes*.

- ◆ For additional troubleshooting details, refer to the Troubleshooting chapter of the *NetBackup ServerFree Agent System Administrator's Guide*.

NetBackup Status Code: 171

Message: media id must be 6 or less characters

Explanation: An operation, such as using `bpmedia` to suspend or freeze a media ID, was attempted and the media ID specified was longer than six alpha-numeric characters.

Recommended Action: Retry the command with a valid media ID.

NetBackup Status Code: 172

Message: cannot read media header, may not be NetBackup media or is corrupted

Explanation: When loading a volume for a backup or restore, the tape manager (`bptm`), did not find the expected tape header. This can mean that a volume in a robotic device is not in the slot number shown in the Media Manager volume configuration or that a read error (I/O error) occurred.

Recommended Action:

1. If the volume is in a robot that supports barcodes, verify the robot contents by using a Media Manager robot inventory option.
2. If the volume was mounted on a nonrobotic drive, verify that the correct volume was mounted and assigned.
3. Check the NetBackup Problems report. If a fatal read error occurred, attempt the operation again using another drive, if possible.

4. If your configuration has multiple servers / HBAs with access to your tape services (most likely, an SSO configuration), make sure the SCSI Reserve / Release is configured correctly. For more information, refer to the *NetBackup SAN Shared Storage Option System Administrators Guide for UNIX and Windows*.

NetBackup Status Code: 173

Message: cannot read backup header, media may be corrupted

Explanation: When searching for a backup image to restore, the tape manager (bptm) could not find the correct backup ID at the position on the media where NetBackup expected it to be. This can indicate a drive hardware problem.

Recommended Action:

1. Check the NetBackup Problems report for clues as to what caused the error.
2. Try the restore on another drive if possible.
3. For detailed troubleshooting information, create a debug log directory for bptm and retry the operation. Check the resulting debug log.

NetBackup Status Code: 174

Message: media manager - system error occurred

Explanation: An abnormal condition occurred causing a tape manager(bptm) or disk manager (bpdm) failure. This should not occur under normal circumstances.

Recommended Action:

1. Check the NetBackup Problems report to see if it shows the cause of the problem. If you see a Problems report message similar to
"attempting to write 32767 bytes, not a multiple of 1024"
save all logs and call VERITAS customer support.
2. If you see the problem with only one client, verify that the client binaries are correct, especially those for bpcd.
3. Can you read or write any other images on this media?
If so, check the following reports for clues:
 - ◆ Images on Media report
 - ◆ Media Contents report



4. Verify the following:
 - ◆ The media by using the NetBackup image verify option.
 - ◆ That you are using the correct media type for the device.
5. Check the Event Viewer Application log.
6. For detailed debug information, create a debug log directory for either `bptm` or `bpdm` (whichever applies) and retry the operation. Check the resulting debug log.

NetBackup Status Code: 175

Message: not all requested files were restored

Explanation: When restoring files from an image, the `bptm` or `bpdm` process detected a fatal error condition and terminated the restore before it completed. This should not occur under normal circumstances.

Recommended Action:

1. Check the NetBackup Problems report and the status on the client for additional information about the error
2. For detailed troubleshooting information, create a debug log directory for either `bptm` or `bpdm` (whichever applies) and retry the operation. Check the resulting debug log.

NetBackup Status Code: 176

Message: cannot perform specified media import operation

Explanation: The tape manager (`bptm`) detected an error condition when attempting to import a specific backup image. Possible reasons for this are:

- ◆ Media ID is already active in the NetBackup media catalog on this server
- ◆ Media ID is not in the Media Manager volume configuration
- ◆ Fatal tape manager (`bptm`) error occurred
- ◆ Total image was not obtained from Phase 1 of import

Recommended Action:

1. Check the NetBackup Problems report to find the exact cause of the failure.
2. Try the following:
 - ◆ If the media ID is already active, duplicate all images on the original media ID to another volume. Then, manually expire the original media and redo the import.

- ◆ If the media ID is not present in the Media Manager volume configuration, add it.
- ◆ If a fatal `bptm` error occurred, verify that the NetBackup Volume Manager service is active.
- ◆ If the entire image is not present, perform import phase 1 on the media IDs that have the remainder of the image.

NetBackup Status Code: 177

Message: could not deassign media due to Media Manager error

Explanation: The tape manager (`bptm`) could not successfully deassign a media ID.

Recommended Action:

1. Check the NetBackup Problems report for the cause of the problem.
2. Verify that the NetBackup Volume Manager service is active.
3. For detailed troubleshooting information, create a debug log directory for `bptm` and retry the operation. Check the resulting debug log.

NetBackup Status Code: 178

Message: media id is not in NetBackup volume pool

Explanation: NetBackup attempted a backup of its catalogs and the media ID specified for the catalog backup was not in the NetBackup volume pool. Volumes for catalog backups must be in the NetBackup volume pool.

Recommended Action: Check the Media Manager volume configuration to verify that the media IDs are present and in the NetBackup volume pool.

NetBackup Status Code: 179

Message: density is incorrect for the media id

Explanation: An operation such as “list contents” was attempted on an invalid media ID, such as a cleaning tape. Another possibility is that a media ID in the NetBackup catalog backup configuration does not match the media type entered in the Media Manager volume configuration.

Recommended Action: Check the volume configuration and the NetBackup catalog backup configuration and correct any problems found.

NetBackup Status Code: 180

Message: tar was successful



Explanation: `tar` returned a successful exit status.

Recommended Action: None.

NetBackup Status Code: 181

Message: `tar` received an invalid argument

Explanation: One of the parameters passed to `tar` was not valid.

- ◆ **Recommended Action:** On a Windows client, create a `tar` debug log directory, retry the operation, and check the log.
- ◆ On a Macintosh client, check the version file that is in the `bin` folder in the NetBackup folder in the Preferences folder. If the software is not at the correct level, install the correct software as explained in the installation guide.

NetBackup Status Code: 182

Message: `tar` received an invalid file name

Explanation: `tar` cannot write to the file that is specified with the `-f` parameter.

Recommended Action:

1. Create a `bpcd` debug log directory on the client (on a Macintosh NetBackup creates the log automatically).
2. On a Windows client, create a `tar` debug log directory.
3. Increase the debug or log level as explained in the debug log topics in Chapter 3.
4. Rerun the operation, check the resulting debug logs for the parameters passed to `tar` and call customer support.

NetBackup Status Code: 183

Message: `tar` received an invalid archive

Explanation: The data passed to `tar` was corrupt.

Recommended Action:

1. Create a `bpcd` debug log directory on the client (on a Macintosh NetBackup creates the log automatically).
2. On a Windows client, create a `tar` debug log directory.
3. Increase the debug or log level as explained in the debug log topics in Chapter 3.



4. Retry the operation and check the resulting debug logs.
5. Reboot the client to see if it corrects the problem.

NetBackup Status Code: 184

Message: tar had an unexpected error

Explanation: A system error occurred in `tar`.

Recommended Action:

1. Create a `bpcd` debug log directory on the client (on a Macintosh NetBackup creates the log automatically).
2. Increase the debug or log level as explained in the debug log topics in Chapter 3.
3. On a Windows client, create a `tar` debug log directory.
4. Retry the operation and check the resulting debug logs.
5. Reboot the client to see if it corrects the problem.

NetBackup Status Code: 185

Message: tar did not find all the files to be restored

Explanation: There were files in the `tar` file list that were not in the image.

Recommended Action:

1. Create a `bpcd` debug log directory on the client (on a Macintosh NetBackup creates the log automatically).
2. Increase the debug or log level as explained in the debug log topics in Chapter 3.
3. On a Windows client, create a `tar` debug log directory.
4. Retry the operation.
5. Check the resulting debug logs for the parameters passed to `tar` and call customer support.

NetBackup Status Code: 186

Message: tar received no data



Explanation: The media manager did not send data to `tar`.

Recommended Action:

1. Retry the operation and check the status on the client for error messages that reveal the problem.
2. Verify that the tape is available and readable.
3. Verify that the drive is in an UP state. Use the Device Monitor.
4. For detailed troubleshooting information:
 - a. Create a `bptm` debug log on the server.
 - b. On a Windows client, create a `tar` debug log.
 - c. Retry the operation and check the resulting debug logs.

NetBackup Status Code: 189

Message: the server is not allowed to write to the client's filesystems

Explanation: The client is not allowing writes from the server.

Recommended Action: Perform the following to perform restores or install software from the server.

- ◆ On a Microsoft Windows or NetWare nontarget client, select Allow server-directed restores on the General tab in the NetBackup Configuration dialog box. To display this dialog box, start the Backup, Archive, and Restore interface on the client and click Configure on the Actions menu.
- ◆ On a Macintosh client, delete `DISALLOW_SERVER_FILE_WRITES` from the `bp.conf` file in the NetBackup folder in the Preferences folder.
- ◆ On a NetWare target client, set `ALLOW_SERVER_WRITE` to yes in the `bp.ini` file.

NetBackup Status Code: 190

Message: found no images or media matching the selection criteria

Explanation: A verify, duplicate, or import was attempted and no images matching the search criteria were found in the NetBackup catalog.

Recommended Action: Change the search criteria and retry.



NetBackup Status Code: 191

Message: no images were successfully processed

Explanation: A verify, duplicate, or import was attempted and failed for all selected images.

Recommended Action: Check the NetBackup Problems report for the cause of the error. To obtain detailed troubleshooting information, create an `admin debug log` directory and retry the operation. Check the resulting debug log.

NetBackup Status Code: 194

Message: the maximum number of jobs per client is set to 0

Explanation: The NetBackup Maximum jobs per client global attribute is currently set to 0. Setting the value to 0 disables backups and archives.

Recommended Action: To enable backups and archives, change the Maximum jobs per client value to the desired nonzero setting. This attribute is on the Global NetBackup Attributes tab in the Master Server Properties dialog box. See “Using the Host Properties Window” on page 40.

NetBackup Status Code: 195

Message: client backup was not attempted

Explanation: A backup job was in the NetBackup scheduler’s worklist but was not attempted.

Recommended Action:

1. Retry the backup either immediately with a manual backup or allow the normal scheduler retries.
2. For additional information, check the All Log Entries report. For detailed troubleshooting information, create a `bpsched debug log` directory on the master server. After the next backup attempt, check the debug log.

Some actions to perform are:

- ◆ Verify that the NetBackup Volume Manager and NetBackup Device Manager services are running.
- ◆ Look for a problem in an earlier backup that made the media or storage unit unavailable.

NetBackup Status Code: 196

Message: client backup was not attempted because backup window closed



Explanation: A backup or archive operation that was queued by the backup scheduler was not attempted because the backup window was no longer open.

Recommended Action:

- ◆ If possible, change the schedule to extend the backup window for this policy and schedule combination so it does not occur again.
- ◆ If the backup must be run, use the Manual Backup command on the Policy menu in the Backup Policy Management window to perform the backup. Manual backups ignore the backup window.

NetBackup Status Code: 197

Message: the specified schedule does not exist in the specified policy

Explanation: A user backup or archive request has specified the exact policy and schedule to use when performing a backup. The policy exists but does not contain the schedule.

- ◆ On Microsoft Windows and NetWare nontarget clients, you can specify a policy or schedule on the Backups tab in the NetBackup Configuration dialog box. To display this dialog box, start the Backup, Archive, and Restore interface on the client and click Configure on the Actions menu.
- ◆ On Macintosh clients, you can specify a policy or schedule by using the `bp.conf` options, `BPBACKUP_POLICY` or `BPBACKUP_SCHED`.
- ◆ On NetWare target clients, you can specify a policy or schedule in the `bp.ini` file.

Recommended Action:

1. Check the client progress log (if available) to determine the policy and schedule that were specified.
2. Check the configuration on the master server to determine if the schedule is valid for the policy. If the schedule is not valid, either add the schedule to the policy configuration or specify a valid schedule on the client.

NetBackup Status Code: 198

Message: no active policies contain schedules of the requested type for this client

Explanation: A user backup or archive has been requested, and this client is not in a policy that has a user backup or archive schedule.

Recommended Action: Determine if the client is in any policy that has a schedule of the appropriate type (either user backup or archive).

- ◆ If the client is in such a policy, check the general policy attributes to verify that the policy is set to active.



- ◆ If the client is not in such a policy, either add a schedule of the appropriate type to an existing policy that has this client or create a new policy that has this client and a schedule of the appropriate type.

NetBackup Status Code: 199

Message: operation not allowed during this time period

Explanation: A user backup or archive has been requested and this client is not in a policy that has a user backup or archive schedule with an open backup window. This error implies that there is an appropriate policy and schedule combination for this client.

Recommended Action: Determine the policies to which this client belongs that also have a schedule of the appropriate type (either user backup or archive).

- ◆ If possible, retry the operation when the backup window is open.
- ◆ If the backup window is not open during appropriate time periods, adjust a backup window for a schedule in one of the policies.

NetBackup Status Code: 200

Message: scheduler found no backups due to run

Explanation: When checking the policy and schedule configuration, the NetBackup scheduler process (bpsched) did not find any clients to back up. This could be due to:

- ◆ No backup time windows are open (applies only to full and incremental schedules).
- ◆ Policies are set to inactive.
- ◆ The clients were recently backed up and are not due for another backup (based on Frequency setting for the schedules).
- ◆ Policies do not have any clients.

Recommended Action: Usually, this message can be considered informational and does not indicate a problem. However, if you suspect a problem:

1. Examine the NetBackup All Log Entries report to see if there are any messages in addition to one indicating that the scheduler found nothing to do.
2. Examine the policy configuration for all policies or the specific policy in question and determine if any of the reasons mentioned in the Explanation section above apply.
3. To obtain detailed troubleshooting information, create a bpsched debug log directory on the master server and retry the operation. Check the resulting debug log.



NetBackup Status Code: 201

Message: handshaking failed with server backup restore manager

Explanation: A process on the master server encountered an error when communicating with the media host (can be either the master or a media server). This error means that the master and media server processes were able to initiate communication, but encountered difficulties in completing them. This problem can occur during a backup, restore, or media list in a single or multiple server configuration.

Recommended Action:

1. Determine the activity that encountered the handshake failure by examining the NetBackup All Log Entries report for the appropriate time period. If there are media servers, determine if:
 - ◆ The handshake failure was encountered between the master and a media server.
or
 - ◆ Only the master server was involved.
2. If necessary, create the following debug log directories for the following:
 - ◆ bpcd on the NetBackup media host (can be either the master or a media server).
 - ◆ If the error was encountered during a backup operation, bpsched on the master server.
 - ◆ If the error was encountered during a restore operation, bprd on the master server.
 - ◆ If the error was encountered during a media list operation, admin in the NetBackup logs/admin directory on the master server.
3. Retry the operation and examine the resulting debug logs for information on why the error occurred.

NetBackup Status Code: 202

Message: timed out connecting to server backup restore manager

Explanation: A process on the master server timed out while trying to initiate communications with the media host (can be either the master or a media server). This problem can occur during a backup or restore in either a single or multiple server configuration.

Recommended Action: Determine which activity encountered the connection timeout failure by examining the All Log Entries report for the appropriate time period. If there are media servers, determine if the timeout occurred between the master and a media server or if only the master was involved.

1. Verify that the schedule specifies the correct storage unit.
2. Execute the `ping` command from one host to another by using the following combinations:
 - ◆ From the master server, ping the master and all media servers by using the host names found in the storage unit configuration.
 - ◆ From each of the media servers, ping the master server by using the host name specified in the NetBackup server list. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.
3. Verify that the master server can communicate with `bpcd` on the host that has the storage unit.

After each backup, the scheduler checks the storage unit to see how many drives are available (in case the backup caused a drive to be automatically downed). If `bpsched` cannot communicate with `bpcd`, it sets the number of available drives in that storage unit to 0 and further backups to that storage unit fail.

The available drives remain at 0 until the scheduler is initialized again. Therefore, even if `bpcd` seems to be operating correctly now, check the `bpsched` and `bpcd` debug logs (see below) for records of an earlier failure.

4. See “Testing Media Server and Clients” on page 19 and “Resolving Network Communication Problems” on page 21.
5. If necessary, create debug log directories for the following processes and retry the operation. Then, check the resulting debug logs on the master server:
 - ◆ If the error occurred during a backup operation, check the `bpsched` debug logs. Also, check the `bpcd` debug logs.
 - ◆ If the error occurred during a restore operation, check the `bprd` debug logs.

NetBackup Status Code: 203

Message: server backup restore manager’s network is unreachable

Explanation: A process on the master server could not connect to a particular host on the network when trying to initiate communication with the media host for a particular operation. This problem can occur during a backup or restore in either a single or multiple server configuration.

Recommended Action: Determine which activity encountered the network unreachable failure by examining the All Log Entries report for the appropriate time frame. If there is more than one NetBackup server (that is, one or more media servers) determine if the



network unreachable failure was encountered between the master and a media server or if only the master server was involved. Execute the `ping` command from one host to another by using the following combinations:

1. From the master server, ping the master and all media servers by using the host names in the storage unit configuration.
2. From each of the media servers, ping the master server host by using the host name specified in the NetBackup server list. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.
3. See “Testing Media Server and Clients” on page 19 and “Resolving Network Communication Problems” on page 21.
4. If necessary, create debug log directories for the following processes and retry the operation. Then, check the resulting debug logs on the master server:
 - ◆ If the error occurred during a backup, check the `bpsched` debug logs.
 - ◆ If the error occurred during a restore, check the `bprd` debug logs.

NetBackup Status Code: 204

Message: connection refused by server backup restore manager

Explanation: The media host refused a connection on the port number for `bpcd`. This error can be encountered during a backup or restore.

Recommended Action: Execute the `ping` command from one host to another by using the following combinations:

Note Also, see “Resolving Network Communication Problems” on page 21.

1. From the master server, ping the master and all media servers by using the host names in the storage unit configuration.
2. From each of the media servers, ping the master server by using the name specified in the NetBackup server list. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.
3. On Windows servers:
 - a. Verify that the `bpcd` entries are correct in:

`%SystemRoot%\system32\drivers\etc\services`



- b. Verify that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Configuration dialog match the settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface and click Configure on the Actions menu.

The values on the Network tab are written to the `services` file when the NetBackup Client service starts.
 - c. Stop and restart the NetBackup services.
4. See “Testing Media Server and Clients” on page 19 and “Resolving Network Communication Problems” on page 21.
5. If necessary, create debug log directories for the following processes and retry the operation. Then, check the resulting debug logs on the master server:
 - ◆ If the error occurred during a backup operation, check the `bpsched` debug logs.
 - ◆ If the error occurred during a restore operation, check the `bprd` debug logs.

NetBackup Status Code: 205

Message: cannot connect to server backup restore manager

Explanation: A process on the master server could not connect to a process on a host on the network while trying to initiate communication with the server that has the storage unit for a particular operation. This problem can occur during a backup or restore in either a single or multiple server configuration. This can also occur when the scheduler process (`bpsched`) is building its list of available storage units to use during backups.

Recommended Action: Execute the `ping` command from one host to another by using the following combinations:

Note Also, see “Resolving Network Communication Problems” on page 21.

1. From the master server, ping the master and all media servers by using the host names in the storage unit configuration.
2. From each of the media servers, ping the master server by using the name specified in the NetBackup server list. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.
3. On Windows servers:



- a. Verify that the `bpcd` entries are correct in the services file:
`%SystemRoot%\system32\drivers\etc\services`
 - b. Verify that the NetBackup Client Service Port number and NetBackup Request Service Port number on the Network tab in the NetBackup Configuration dialog match the settings in the `services` file. To display this dialog, start the Backup, Archive, and Restore interface and click Configure on the Actions menu.

 The values on the Network tab are written to the `services` file when the NetBackup Client service starts.
 - c. Stop and restart the NetBackup services.
4. See “Testing Media Server and Clients” on page 19 and “Resolving Network Communication Problems” on page 21.
 5. Create a `bpcd` debug log directory on the server that has the storage unit and retry the operation. Then, check for additional information in the resulting debug log.

NetBackup Status Code: 206

Message: access to server backup restore manager denied

Explanation: The master server is trying to start a process on another server (or itself) and the master server does not appear in the Netbackup server list on that server. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.

Recommended Action:

1. Verify that the master server appears as a server in its own server list as well as being listed on all media servers.

 If you change the server list on a master server, stop and restart the NetBackup Database Manager and NetBackup Request Manager services.
2. If necessary, create debug log directories for the following processes and retry the operation. Then, check the resulting debug logs on the master server:
 - ◆ If the error occurred during a backup operation, check the `bpsched` debug logs.
 - ◆ If the error occurred during a restore operation, check the `bprd` debug logs.

NetBackup Status Code: 207

Message: error obtaining date of last backup for client



Explanation: An error occurred when the backup scheduler (`bpsched`) tried to obtain the date of the last backup for a particular client, policy, and schedule combination.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. Examine the All Log Entries report for the appropriate time frame to gather more information about the failure.
3. For detailed troubleshooting information, create debug log directories for `bpsched` and `bpdbm` on the master server and retry the operation. Then, check the resulting debug logs.

NetBackup Status Code: 208

Message: failed reading user directed file list

Explanation: An error occurred when the backup scheduler (`bpsched`) attempted to read the list of files requested for a user backup or archive. This error indicates either a client-server communication problem, or a system problem on the master server where the NetBackup scheduler process (`bpsched`) is running.

Recommended Action: For detailed troubleshooting information, create debug log directories for `bpsched` and `bprd` on the master server and retry the operation. Then, check the resulting debug logs.

NetBackup Status Code: 209

Message: error creating or getting message queue

Explanation: An error occurred when the backup scheduler (`bpsched`) attempted to create an internal message queue construct for interprocess communication. This error indicates a problem on the master server.

Recommended Action: Create a `bpsched` debug log directory on the master server and retry the operation. Then, determine the type of system failure by examining the error message in the `bpsched` debug log.

NetBackup Status Code: 210

Message: error receiving information on message queue

Explanation: An error occurred when one of the backup scheduler (`bpsched`) processes attempted to receive a message from another `bpsched` process on an internal message queue construct. This error indicates a problem on the master server.



Recommended Action: Create a `bpsched` debug log directory on the master server and retry the operation. Then, determine the type of system failure by examining the error message in the `bpsched` debug log on the master server.

NetBackup Status Code: 211

Message: scheduler child killed by signal

Explanation: A backup scheduler (`bpsched`) child process, which interacts with the backup restore manager (`bpbrm`) on the media host, was terminated. This can occur because of system administrator action.

Recommended Action: Create a debug log directory for `bpsched` on the master server and retry the operation. Then, to determine the cause of the child termination, examine the messages in the `bpsched` debug log.

NetBackup Status Code: 212

Message: error sending information on message queue

Explanation: The backup scheduler (`bpsched`) encountered an error when attempting to attach to an already existing internal message queue construct for interprocess communication. This error indicates a problem on the master server.

Recommended Action: Create a `bpsched` debug log directory on the master server and retry the operation. Then, determine the type of system failure by examining the error message in the `bpsched` debug log.

NetBackup Status Code: 213

Message: no storage units available for use

Explanation: The NetBackup scheduler process (`bpsched`) did not find any of its storage units available for use. Either all storage units are unavailable or all storage units are configured for On demand only and the policy and schedule does not require a specific storage unit.

Recommended Action:

1. Examine the Backup Status and All Log Entries report for the appropriate time period to determine the policy or schedule that received the error.
2. Verify that the storage unit's drives are not down or waiting for media from a previous operation that did not complete.
3. Verify that all the storage units do not have their Maximum concurrent jobs attribute set to 0 (for disk storage units) and Maximum concurrent drives used for backup attribute set to 0 (for Media Manager storage units).



4. Verify that the robot number and host name in the storage unit configuration matches the Media Manager device configuration.
5. Determine if all storage units are set to On demand only for a policy and schedule combination that does not require a specific storage unit. If this is the case, either specify a storage unit for the policy and schedule combination or turn off On demand only for a storage unit.
6. Verify that the NetBackup Client service has been started on the Windows NetBackup media server.
7. For detailed troubleshooting information, create a `bpsched` debug log directory on the master server and retry the operation. Then, check the resulting debug log.

NetBackup Status Code: 214

Message: regular `bpsched` is already running

Explanation: The NetBackup scheduler (`bpsched`) performs periodic checking of the policy and schedule configuration to determine if there are new backups due. Error 214 indicates that when a new instance of NetBackup starts, it finds that a scheduler process is already checking the policy and schedule configuration.

Recommended Action: Usually, no action is required for this condition. However, *NEVER* kill `bpsched` before doing some checking. For example, `bpsched` could be calling `bpdbrm` (NetBackup Database Manager service) to clean up and compress the catalogs.

- ◆ To determine what the running `bpsched` is currently doing, examine the `bpsched` debug log on the master server. If necessary, enable `bpsched` debug logging by creating a `bpsched` debug log directory on the master server and retrying the operation.
- ◆ To check for backups do the following:
On a Windows NetBackup master server:
 1. Check for active or queued backups by using the Activity monitor.
 2. Check for active NetBackup processes by using the Activity monitor. This reveals if there are `bpbdr` or `bptm` processes running and if a backup is active.
 3. If there is no reason for `bpsched` to be running, then kill it from the Activity monitor.

NetBackup Status Code: 215

Message: failed reading global config database information



Explanation: During the periodic checking of the NetBackup configuration, the NetBackup scheduler process (bpsched) was unable to read the global configuration parameters.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. Attempt to view the global configuration settings. Use Host Properties (see “Using the Host Properties Window” on page 40).
3. For detailed troubleshooting information, create debug log directories for bpsched and bpdbm on the master server and retry the operation. Then, check the resulting debug logs.

NetBackup Status Code: 216

Message: failed reading retention database information

Explanation: During its periodic checking of the NetBackup configuration, the NetBackup scheduler process (bpsched) could not read the list of retention levels and values.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. For detailed troubleshooting information, create debug log directories for bpsched and bpdbm on the master server and retry the operation. Then, check the resulting debug logs.

NetBackup Status Code: 217

Message: failed reading storage unit database information

Explanation: During its periodic checking of the NetBackup configuration, the NetBackup scheduler process (bpsched) could not read the storage unit configuration.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. Attempt to view the storage unit configuration by using the NetBackup administration interface.
3. For detailed troubleshooting information, create debug logs for bpsched and bpdbm on the master server and retry the operation. Then, check the resulting debug logs.

Ensure that the correct master server is being specified for the connection.

NetBackup Status Code: 218

Message: failed reading policy database information

Explanation: During the periodic checking of the NetBackup configuration, the NetBackup scheduler process (`bpsched`) could not read the policy (backup policy) configuration.

Recommended Action:

1. Verify that the NetBackup Database Manager service is running.
2. Attempt to view the policy configuration by using the NetBackup administration interface.
3. For detailed troubleshooting information, create debug log directories for `bpsched` and `bpdbm` on the master server and retry the operation. Then, check the resulting debug logs.

Ensure that the correct master server is being specified for the connection.

NetBackup Status Code: 219

Message: the required storage unit is unavailable

Explanation: The policy or schedule for the backup requires a specific storage unit, which is currently unavailable. This error also occurs for other attempts to use the storage unit within the current backup session.

Recommended Action: Look in the Job Details window for the failed job. Or, examine the Backup Status and All Log Entries report for the appropriate time period to determine the class or schedule that received the error; then examine the specific class and schedule configuration to determine the required storage unit.

1. Verify that the schedule specifies the correct storage unit and the storage unit exists.
2. Verify that the NetBackup Device Manager service is running. Use either the Activity Monitor or the Services application in the Windows Control Panel.
3. Verify that the Maximum concurrent jobs attribute is not set to 0 (for a disk storage unit) and the Maximum concurrent drives attribute is not set to 0 (for a Media Manager storage unit).
4. If the storage unit is a tape, verify that at least one of the drives is in the UP state. Use the Device Monitor.



5. Verify that the robot number and host in the storage unit configuration matches what is specified in the Media Manager device configuration.
6. Verify that the master server can communicate with the `bpcd` process on the server that has the storage unit.

- a. Verify that `bpcd` is listening on the port for connections.

On a Windows NetBackup server, executing

```
netstat -a
```

prints out several lines of output. If `bpcd` is listening, one of those lines is similar to the following:

```
TCP      myhost:bpcd      0.0.0.0:0          LISTENING
```

Do this on the server where the storage unit is connected.

- b. If `bpcd` seems to be operating correctly, create `bpsched` and `bpcd` debug log directories and retry the operation. Check the resulting debug logs for records of an earlier failure.

After each backup, the scheduler checks the storage unit to see how many drives are available (in case the backup caused a drive to be automatically downed). If `bpsched` cannot communicate with `bpcd`, it sets the number of available drives in that storage unit to 0 and further backups to that storage unit during this backup session will fail.

The number of available drives remains at 0 until the scheduler is initialized again.

- c. If the cause of the problem is not obvious, perform some of the steps in “Resolving Network Communication Problems” on page 21.

NetBackup Status Code: 220

Message: database system error

Explanation: The `bpdbm` process (NetBackup Database Manager service) could not create a directory path for its configuration catalogs due to the failure of a system call. This is usually due to a permission problem or an “out of space” condition.

Recommended Action: Create a debug log directory for `bpdbm` and retry the operation. Check the resulting debug log for information.

NetBackup Status Code: 221

Message: continue



Explanation: This status code is used in coordinating communication between various NetBackup processes and normally does not occur. If the logs show that it is associated with a subsequent error, it usually indicates a communication problem. In this case, concentrate your troubleshooting efforts on the subsequent error.

Recommended Action: Determine the cause of the status code that follows this one.

NetBackup Status Code: 222

Message: done

Explanation: This status code is used in coordinating communication between various NetBackup processes and is normally not seen. If the error logs show that it is associated with a subsequent error, it usually indicates a communication problem. In this case, concentrate your troubleshooting efforts on the subsequent error.

Recommended Action: Determine the cause of the status code that follows this one.

NetBackup Status Code: 223

Message: an invalid entry was encountered

Explanation: A request to the `bpdbm` process (NetBackup Database Manager service) had invalid or conflicting information. This is usually a result of using software from different versions together, but can also be caused by incorrect parameters on a command.

Recommended Action: Verify that all NetBackup software is at the same version level and the command parameters are specified correctly. If neither of these is the problem, obtain detailed troubleshooting information by creating a `bpdbm` debug log directory and retrying the operation. Check the resulting debug log.

NetBackup Status Code: 224

Message: there was a conflicting specification

Explanation: A request to the `bpdbm` process (NetBackup Database Manager service) had conflicting information. This is usually a result of using software from different version levels together.

Recommended Action: Verify that all NetBackup software is at the same version level. If that is not the problem, obtain detailed troubleshooting information by creating `bpdbm` and `admin` debug log directories and retrying the operation. Check the resulting debug logs.

NetBackup Status Code: 225

Message: text exceeded allowed length



Explanation: A request containing text that exceeds a buffer size was made to the bpdgm process (NetBackup Database Manager service). This is usually a result of using software from different version levels together.

Recommended Action: Verify that all NetBackup software is at the same version level. If that is not the problem, create debug log directories for bpdgm and admin. Then, retry the operation and examine the resulting debug logs.

NetBackup Status Code: 226

Message: the entity already exists

Explanation: The configuration already has an entity with the same name or definition. For example, you see this status if you try to add a new policy when an existing policy has the same name or definition (attributes, clients, and so on).

Recommended Action: Correct your request and re-execute the command.

NetBackup Status Code: 227

Message: no entity was found

Explanation: The item requested was not in the catalog. For example, the entity could be a file or policy information.

Recommended Action:

1. A common cause for this problem is a query that has no matching images. Specify different parameters or options for the operation and try it again.
2. For NetBackup ServerFree Agent only:

- ◆ Check the `/usr/opensv/netbackup/logs/online_util` log on the client for the following messages:

```
onlfi_get_fsmmap_info: FTL - /usr/opensv/netbackup/fi.conf open
failed. Errno = 2: No such file or directory
```

```
onlfi_process_fs_list_fs_entry: FTL - No frozen image mapping
information for /vol1
```

This indicates that the frozen image configuration file was not found. The frozen image configuration file is created with the Frozen Image Client Configuration dialog as described in the “NetBackup Configuration” chapter of the *NetBackup ServerFree Agent System Administrator's Guide*.

- ◆ Check the `/usr/opensv/netbackup/logs/online_util` log for the following message:

```
onlfi_process_fs_list_fs_entry: FTL - No frozen image
```

```
mapping information for /voll
```

If you find this message but no “fi.conf open failed” message, the `fi.conf.master server` file was created, but the frozen image source has not been specified in the file. To specify a frozen image source, see the instructions in the “NetBackup Configuration” chapter of the *NetBackup ServerFree Agent System Administrator’s Guide*.

NetBackup Status Code: 228

Message: unable to process request

Explanation: An inconsistency exists in the catalog or a request was made that would be improper to satisfy.

Recommended Action:

1. If this involves a media server, verify that its server list specifies the correct master server. On a Windows server, the master is designated on the Servers tab in the Master Server Properties dialog. To access this dialog, see “Using the Host Properties Window” on page 40.
2. For detailed troubleshooting information, create a `bpdbm` debug log directory and retry the operation. Then, check the resulting debug log.

NetBackup Status Code: 229

Message: events out of sequence - image inconsistency

Explanation: A request was made which, if satisfied, would cause the image catalog to become inconsistent.

Recommended Action: Obtain detailed troubleshooting information by creating a debug log directory for `bpdbm`. Then, retry the operation, save the resulting debug log, and call customer support.

NetBackup Status Code: 230

Message: the specified policy does not exist in the configuration database

Explanation: The specified policy name does not exist.

Recommended Action: Correct your parameters or options and retry the operation.

NetBackup Status Code: 231

Message: schedule windows overlap



Explanation: The start and duration times specified for one day of the schedule overlap with another day of the schedule.

Recommended Action: Correct the schedule to eliminate the overlapping backup windows.

NetBackup Status Code: 232

Message: a protocol error has occurred

Explanation: This is an intermediate status code that usually precedes another status code. It indicates that either the `bpdbm` process (NetBackup Database Manager service) or the process communicating with it has received unexpected information.

Recommended Action: Create a debug log directory for `bpdbm`. Then, retry the operation, save the debug log, and call customer support.

NetBackup Status Code: 233

Message: premature eof encountered

Explanation: This is an intermediate status code that usually precedes another status code and is associated with a problem in network communication.

Recommended Action: During a restore, this means that `tar` (on the client) received a stream of data that was not what it expected.

If the communication failure is not due to an interrupt on a client system, save all error information and call customer support.

NetBackup Status Code: 234

Message: communication interrupted

Explanation: This is an intermediate status code that usually precedes another status code and is associated with a problem in network communication. A process, either server or client, received an interrupt signal.

Recommended Action: Save all error information and call customer support.

NetBackup Status Code: 235

Message: inadequate buffer space

Explanation: This code usually indicates a mismatch between server and client software versions.

Recommended Action:

1. Verify that all NetBackup software is at the same version level. Update earlier versions of NetBackup software.
 - ◆ On Windows NetBackup servers, check the `install_path\NetBackup\version.txt` file or the About NetBackup item on the Help menu.
 - ◆ On Microsoft Windows clients, check the About NetBackup item on the Help menu.
 - ◆ On NetWare target clients, check the Version entry in the `bp.ini` file.
If the client software is earlier than 3.0, verify that the client is in a Standard type policy.
 - ◆ On Macintosh clients, check the version file in the `bin` folder in the NetBackup folder in the `Preferences` folder.
2. If the problem persists, save all error information and call customer support.

NetBackup Status Code: 236

Message: the specified client does not exist in an active policy within the configuration database

Explanation: A client name was not specified or the specified client does not exist.

Recommended Action: Activate the required policy, correct the client name, or add the client to a policy that meets your needs. After making the correction, retry the operation.

NetBackup Status Code: 237

Message: the specified schedule does not exist in an active policy in the configuration database

Explanation: The specified schedule does not exist in the NetBackup configuration.

Recommended Action: Activate the required policy, correct the schedule name, or create a schedule in a policy that meets your needs. After making the correction, retry the operation.

NetBackup Status Code: 238

Message: the database contains conflicting or erroneous entries

Explanation: The catalog has an inconsistent or corrupted entry.

Recommended Action: Obtain detailed troubleshooting information for `bpdbm` (NetBackup Database Manager service) by creating a debug log directory for it. Then, retry the operation, save resulting debug log, and call customer support.



NetBackup Status Code: 239

Message: the specified client does not exist in the specified policy

Explanation: The specified client is not a member of the specified policy.

Recommended Action: Correct the client name specification, specify a different policy, or add the required client name to the policy. After making the correction, retry the operation.

NetBackup Status Code: 240

Message: no schedules of the correct type exist in this policy

Explanation: The appropriate schedule was not found in the specified policy. For example, a user backup specified a policy name but no user backup schedule exists in that policy.

Recommended Action: Specify a different policy or create a schedule of the needed type in the policy. After making the correction, retry the operation.

NetBackup Status Code: 241

Message: the specified schedule is the wrong type for this request

Explanation: The schedule that was specified for an immediate manual backup is not for a full nor an incremental backup. It must be one of these.

Recommended Action: Specify only full or incremental schedules for manual backups. If one does not exist in the policy, create one.

NetBackup Status Code: 242

Message: operation would cause an illegal duplication

Explanation: Processing the request would cause a duplicate catalog entry. This is usually due to a mistake in specifying media IDs for NetBackup catalog backups.

Recommended Action: Check the error reports to determine the specific duplication that would occur. Correct the settings for the operation and retry it.

NetBackup Status Code: 243

Message: the client is not in the configuration

Explanation: The specified client name was not in the catalog.

Recommended Action: Either correct the client name or add the client to the desired policy.

NetBackup Status Code: 244

Message: main bpsched is already running

Explanation: A bpsched process tried to become the main backup scheduler but another process is currently in this mode.

Recommended Action: None.

NetBackup Status Code: 245

Message: the specified policy is not of the correct client type

Explanation: A user backup specified a policy that is not the type required for the client.

Recommended Action: Retry the operation by specifying a policy that is the correct type for the client. If such a policy does not exist, create one.

NetBackup Status Code: 246

Message: no active policies in the configuration database are of the correct client type

Explanation: A user backup request was not satisfied because no active policies were the type required for the client.

Recommended Action: Create or activate an appropriate policy so the user backup request can be satisfied.

NetBackup Status Code: 247

Message: the specified policy is not active

Explanation: Backups for the specified policy are disabled because the policy is inactive.

Recommended Action: Activate the policy and retry the operation.

NetBackup Status Code: 248

Message: there are no active policies in the configuration database

Explanation: No active policy was found that would satisfy the request.

Recommended Action: Activate the appropriate policy and retry the operation.

NetBackup Status Code: 249

Message: the file list is incomplete

Explanation: The server timed out while waiting for the client to finish sending the file list, or a sequencing problem occurred.



Recommended Action: Obtain additional information by first creating debug logs and then attempting to recreate the error. The debug logs to create are as follows:

- ◆ On the server, `bptm`, `bpbm`, and `bpdbm`.
- ◆ On Windows clients, `bpbkar`.
- ◆ On other clients, `bpcd`.

Note To increase the amount of information included in the logs, see “Debug Logs on PC Clients” on page 46.

NetBackup Status Code: 250

Message: the image was not created with TIR information

Explanation: This is an internal error and should not be seen by customers.

Recommended Action: Obtain detailed troubleshooting information by creating debug logs for `bptm` and `bpdbm` on the server. Then, retry the operation and check the resulting debug logs.

NetBackup Status Code: 251

Message: the TIR information is zero length

Explanation: For a true-image backup, the client sent no file information to the master server. NetBackup discovered this condition when it attempted to write the TIR information to media.

Recommended Action:

1. Check the file list for the policy and the exclude and include lists on the client to verify that the client has files that are eligible for backup. For example, this status code can appear if the exclude list on the client excludes all files.
2. To obtain detailed troubleshooting information, create debug logs for `bptm` and `bpdbm` on the server. Then, retry the operation and check the resulting debug logs.

NetBackup Status Code: 252

Message: the error status has been written to `stderr`

Explanation: If a Vault job fails with a status code greater than 255, it exits with status 252; the actual Vault status code is written to `stderr`. This is because status codes greater than 255 are not supported by all operating systems. The Vault job then reports the actual status code found in `stderr` (for example, 256) as the job completion status, as seen in the Activity Monitor.

Recommended Action: For more information on a Vault status code, refer to the *NetBackup Troubleshooting Guide* or to the Activity Monitor's troubleshooter.

NetBackup Status Code: 254

Message: server name not found in the bp.conf file

Explanation: This error should not occur through normal use of NetBackup.

Recommended Action: Save all error information and call customer support.

NetBackup Status Code: 257

Message: cannot create log file

Recommended Action: When a vault session is started, vltrun needs to create log files in the following directories:

```
UNIX: /usr/opensv/netbackup/vault/sessions/vault_name
Windows: install_path\Netbackup\vault\sessions\vault_name
UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: install_path \NetBackup\vault\sessions\vault_name\sidxxx
```

(where xxx is the session id)

Ensure that the following directory exists, is writable by root, and that the disk is not full:

```
UNIX: /usr/opensv/netbackup/vault/sessions/vault_name
Windows: install_path\NetBackup\vault\sessions\vault_name
```

NetBackup Status Code: 258

Message: a child process failed for an unknown reason

Explanation: A child process of the vault job died with an invalid exit status.

Recommended Action: Contact customer support and send appropriate logs.

NetBackup Status Code: 263

Message: session id assignment failed

Explanation: The unique identifier to be assigned to the vault session is bad.

Recommended Action: Verify that the session id stored in the session.last file is valid.

```
UNIX:
/usr/opensv/netbackup/vault/sessions/vault_name/session.last
```



Windows:

`install_path\Netbackup\vault\sessions\vault_name\session.last`

Make sure that the file system is not full and that no one has inadvertently edited the `session.last` file. You can correct the problem by storing in the `session.last` file the highest session id that has been assigned to a session for this vault. If the problem persists, contact customer support and send the appropriate logs.

NetBackup Status Code: 265

Message: session id file is empty or corrupt

Explanation: The session id stored in the following file is bad.

UNIX:

`/usr/opensv/netbackup/vault/sessions/vault_name/session.last`

Windows:

`install_path\NetBackup\vault\sessions\vault_name\session.last`

Recommended Action: Ensure that the session id stored in the `session.last` file is not corrupt. Make sure that the file system is not full and that no one has inadvertently edited the file. You can correct the problem by storing in the `session.last` file the highest session id that has been assigned to a session for this vault. If the problem persists, contact customer support and send the appropriate logs.

NetBackup Status Code: 266

Message: cannot find robot, vault, or profile in the vault configuration

Explanation: The *profile name* or triplet *robot_name/vault_name/profile_name* specified on the vault command (`vltrun`, `vlteject`, `vltoffsitemedia`), or by means of `vltopmenu`, was not found in the vault configuration.

Recommended Action: Please rerun the command with the correct *profile_name* or triplet *robot_name/vault_name/profile_name*.

NetBackup Status Code: 267

Message: cannot find the local host name

Explanation: A vault job obtains the local host name via an OS call. This error occurs when the vault job is unable to get the local host name.

Recommended Action: Issue a `hostname` command at the OS command prompt. See the `hostname` (or `gethostbyname`) man page for an explanation of the conditions that would cause it to fail. Refer to the *OS System Administrator Guide* for more information

NetBackup Status Code: 268

Message: the vault session directory is either missing or inaccessible

Explanation: This error occurs when a vault job cannot access the following:

UNIX: /usr/opensv/netbackup/vault/sessions
 Windows: *install_path*\NetBackup\vault\sessions

This directory is created when vault is installed.

Recommended Action: Make sure you are running on the master server where vault is installed and configured. Also ensure that no one has accidentally removed the sessions directory or changed permission on the directory path so it is inaccessible to the vault job.

NetBackup Status Code: 269

Message: no vault session id was found

Explanation: This error is encountered when *vltopmenu* cannot find a *sidxxx* session id directory for the specified profile. It means that either no vault jobs were run for this profile or that the corresponding *sidxxx* session id directory (or directories) were removed from the following directory:

UNIX: /usr/opensv/netbackup/vault/sessions/*vault_name*
 Windows: *install_path*\NetBackup\vault\sessions*vault_name*

Recommended Action: You can either specify a different profile for which vault jobs have been run or exit *vltopmenu*, run a vault job for the specific profile and rerun *vltopmenu* and select the profile.

NetBackup Status Code: 270

Message: unable to obtain process id, getpid failed

Explanation: This error occurs when a vault process is unable to obtain its process id by means of the *getpid()* OS system call.

Recommended Action: Look at the system log for any unusual system problems. Wait for a while and try running the process again when system resources have been freed up.

NetBackup Status Code: 271

Message: the initialization of the vault configuration file failed

Explanation: This error occurs when configuration initialization code fails.

Recommended Action: Ensure that the following is accessible:

UNIX: /usr/opensv/netbackup/lib/libxerces-cl_4nmt.so
 Windows: *install_path*\NetBackup\lib\libxerces-cl_4nmt.so



NetBackup Status Code: 272

Message: execution of a vault notify script failed

Explanation: This error occurs when the vault process is unable to execute a vault notify script due to permissions problems or coding problems in the script or if an error is returned by the script.

Recommended Action: Ensure that the notify script is executable and runs without errors. You must debug the script by running it manually to eliminate coding errors.

NetBackup Status Code: 273

Message: invalid jobID

Explanation: This error should not occur.

Recommended Action: Contact customer support and send appropriate logs.

NetBackup Status Code: 275

Message: a session is already running for this vault

Explanation: This error occurs when you start a session for a vault and another session is already running for this vault. Only one session is allowed for a vault at any given time.

Recommended Action: Start the vault session after the previous session has completed.

NetBackup Status Code: 284

Message: error caused by invalid data in vault configuration file

Explanation: This error is returned by a vault job or a command when it cannot interpret the information extracted from the vault configuration file. For example, if the vault configuration file is corrupt or refers to non-existent or misconfigured objects.

Recommended Action: Ensure that your vault configuration is correct (that it refers to functional robots, media servers, volume pools, and so forth). Also ensure that the vault profile is defined in the configuration and has not been accidentally removed after the vault job was started. This can happen when more than one vault interface is changing the configuration at the same time. Examine the vault logs for detailed information about configuration problems. To correct the problem, you may need to restore the following file from a backup copy:

UNIX: `/usr/opensv/netbackup/db/vault/vault.xml`

Windows: `install_path\NetBackup\db\vault\vault.xml`

NetBackup Status Code: 285

Message: unable to locate vault directory



Explanation: This error is returned by a vault job or command when it cannot locate the following directory:

```
UNIX: /usr/opensv/netbackup/vault
Windows: install_path\NetBackup\vault
```

Recommended Action: The `vault` directory is created when the vault package is installed on the master server. Ensure that the vault job or command is started as root on the master server and that the `vault` directory has not been inadvertently removed or made inaccessible to root user.

NetBackup Status Code: 287

Message: failed attempting to copy (consolidated) report file

Explanation: This error occurs when a vault job is unable to copy the consolidated reports to the destination directory specified in the vault profile.

Recommended Action: Ensure that the destination directory specified in the profile exists and is writable by root. Also the vault job or command must be started with root privileges. Correct the path and/or permissions of the destination directory and rerun the vault job or command.

NetBackup Status Code: 288

Message: attempt to open a log file failed

Explanation: This error occurs when a vault job cannot create the `detail.log` file or `summary.log` file in the following directory:

```
UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: install_path \Netbackup\vault\sessions\vault_name\sidxxx
```

(where xxx is the session id.)

Recommended Action: Ensure that the above directory exists and has not been inadvertently removed after the vault job was started. Ensure that this directory is writable by root and that the disk is not full. Rerun the vault job after correcting the problem.

NetBackup Status Code: 289

Message: an error occurred when calling `vltcore`

Explanation: The error can occur during a normal vault job or when `vltject` is executed for a specific session or when `vltopmenu` is used to generate individual reports, if any of the following conditions exists:

- ◆ `vltcore` binary is removed



- ◆ `vltopmenu` binary is not executable
- ◆ the disk (on which NetBackup is installed) is full
- ◆ the following directory is removed or made inaccessible to root (where `xxx` is the session id):

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\netbackup\vault\sessions\vault_name\sidxxx`

Recommended Action: To identify which of the above conditions led to the failure, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` file in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

Correct the problem and rerun the vault job. If the problem persists, please contact customer support and send the appropriate logs.

NetBackup Status Code: 290

Message: one or more errors detected during eject processing

Explanation: This error occurs when more than one error is encountered during an eject procedure via `vltopmenu`. Any “eject” errors in the range 291 to 300 could have occurred in any of the sessions being ejected.

Recommended Action: For detailed information, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where `xxx` is the session id)

The media that was not ejected may need to be ejected manually by means of `vlteject` or `vltopmenu`, after the problem has been identified and corrected.

This error often indicates that the media were left in the offsite vault volume group but still physically reside in the robot or in the robotic MAP. To solve this problem, do one of the following:

- ◆ Manually remove any media that are in the offsite vault volume group but are still in the robotic library.



- ◆ Inventory the robotic library. This puts any media that were in the offsite vault volume group back into the robotic volume group. Then, rerun the vault sessions that failed.

NetBackup Status Code: 291

Message: number of media has exceeded capacity of MAP; must perform manual eject using `vltopmenu` or `vlteject`

Explanation: This error occurs when a vault job is run for a profile that has selected automatic eject mode and the number of media to be ejected exceeds the capacity of the MAP.

Recommended Action: Use `vltopmenu` to manually eject the media for the selected profile and session id. The `vltopmenu` option will let you eject the selected media, a MAP-full (or less) at a time.

NetBackup Status Code: 292

Message: eject process failed to start

Explanation: This error occurs when the eject processing cannot be started by the vault job or `vlteject` command or via `vltopmenu`.

Recommended Action: For detailed information about the problem, review the vault debug log in the following directory:

UNIX: `/usr/openv/netbackup/logs/vault`
Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/openv/netbackup/vault/sessions/vault_name/sidxxx`
Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where `xxx` is the session id)

Use the `robtest` utility to ensure that you can communicate with the vault robotic library. Once the problem is resolved, rerun the vault session, `vlteject` command, or `vltopmenu` command.

NetBackup Status Code: 293

Message: eject process has been aborted

Explanation: This error occurs when the eject processing has been aborted. This error could be encountered during a vault job or when using `vlteject` or the `vltopmenu` eject command.

This error can occur because of one of the following conditions:



- ◆ Could not open a pipe to vmchange -verify_eject call.
- ◆ Unexpected output from vmchange -verify_eject call.
- ◆ There are no MAP elements to eject media into.
- ◆ The robotic library had problems putting media into the MAP.
- ◆ The user hit Return in interactive mode without first removing the media from the MAP. In this case, the media that were in the MAP will be put back into their original slots in the robotic library.

Recommended Action: For detailed information about why the process was aborted, review the vault debug log in the following directory:

UNIX: /usr/opensv/netbackup/logs/vault
Windows: *install_path*\NetBackup\logs\vault

Also review the detail.log in each of the sidxxx directories that had problems:

UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: *install_path*\NetBackup\vault\sessions\vault_name\sidxxx

(where xxx is the session id)

This error often indicates that the media were left in the offsite vault volume group but still physically reside in the robot or in the robotic MAP. To solve this problem, do one of the following:

- ◆ Manually remove any media that are in the offsite vault volume group but are still in the robotic library.
- ◆ Inventory the robotic library. This puts any media that were in the offsite vault volume group back into the robotic volume group. Then, rerun the vault sessions that failed.

NetBackup Status Code: 294

Message: Database backup failed

Explanation: The catalog backup step failed during a vault job.

Recommended Action: For detailed information about why the process failed, review the vault debug log in the following directory:

UNIX: /usr/opensv/netbackup/logs/vault
Windows: *install_path*\NetBackup\logs\vault

Also review the detail.log in each of the sidxxx directories that had problems, to find the actual problem that caused the catalog backup (bpbackupdb) to fail:

UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: *install_path*\NetBackup\vault\sessions\vault_name\sidxxx

(where xxx is the session id)

Correct the problem and rerun the vault job.

NetBackup Status Code: 295

Message: eject process could not obtain information about the robot

Explanation: This error occurs when the eject process cannot collect information about the robotic library and its associated MAPs and volumes.

Recommended Action: For detailed information about why the process failed, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where xxx is the session id)

Correct the error and rerun the vault session, `vlteject` command, or `vltopmenu` eject command.

NetBackup Status Code: 297

Message: all volumes are not available to eject

Explanation: This error occurs when an attempt is made to eject a non-existent or bad media id during the eject phase of a vault session, `vlteject` command, or `vltopmenu` command.

Possible reasons for this occurring are:

- ◆ The bad media id was added by means of the `vlt_ejectlist_notify` script.
- ◆ The bad media id is already in the MAP or not in the robotic library.
- ◆ The bad media id is in a robotic drive.
- ◆ The bad media id is in transit in the robotic library.

Recommended Action: Remove or correct the bad media id from the `vlt_ejectlist_notify` script and rerun the vault session. If the bad media id is in the MAP or a drive or in transit, something is misconfigured.

NetBackup Status Code: 298

Message: the library is not ready to eject volumes



Explanation: This error occurs if the robotic library is not in a state to support ejecting media.

Possible reasons for this include:

- ◆ The library is currently ejecting media
- ◆ The library is pending ejecting media
- ◆ The library is currently injecting media
- ◆ The library is pending injecting media

Recommended Action: Wait until the robotic library can support the eject action and rerun the vault session, `vlteject` command, or `vltopmenu` command.

NetBackup Status Code: 299

Message: there is no available MAP for ejecting

Explanation: The robotic library you are vaulting from does not have a MAP available for use and so media cannot be ejected.

Recommended Action: Wait until the robotic library's MAP is available for use and rerun the vault session, `vlteject` command, or `vltopmenu` command.

NetBackup Status Code: 300

Message: vmchange eject verify not responding

Explanation: During the eject process, the `vmchange` command is called with a “-verify_eject” call until all of the volumes for the request are in the MAP. This command call failed or did not return the proper information to the vault eject process.

Recommended Action: For detailed information about why the process failed, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where xxx is the session id)

This error often indicates that the media were left in the offsite vault volume group but still physically reside in the robot or in the robotic MAP. To solve this problem, do one of the following:

- ◆ Manually remove any media that are in the offsite vault volume group but are still in the robot.



- ◆ Inventory the robot. This puts any media that were in the offsite vault volume group back into the robotic volume group. Then, rerun the vault sessions that failed.

NetBackup Status Code: 301

Message: vmchange api_eject command failed

Explanation: During the eject process, the vmchange command is called with an “-api_eject” call to begin the process of ejecting media. This command call failed.

Recommended Action: For detailed information about why the process failed, review the vault debug log in the following directory:

UNIX: /usr/opensv/netbackup/logs/vault
Windows: *install_path*\NetBackup\logs\vault

Also review the detail.log in each of the sidxxx directories that had problems:

UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: *install_path*\NetBackup\vault\sessions\vault_name\sidxxx

(where xxx is the session id)

Once the problem is resolved, rerun the vault session, vlteject command, or vltopmenu command.

NetBackup Status Code: 302

Message: error encountered attempting backup of catalog (Two Phase BU)

Explanation: This error occurs when the NetBackup command used for stage one of the two-stage catalog backup fails.

Recommended Action: For the actual error that caused the failure, review the vault debug log in the following directory:

UNIX: /usr/opensv/netbackup/logs/vault
Windows: *install_path*\NetBackup\logs\vault

Review the detail.log in each of the sidxxx directories that had problems:

UNIX: /usr/opensv/netbackup/vault/sessions/vault_name/sidxxx
Windows: *install_path*\NetBackup\vault\sessions\vault_name\sidxxx

(where xxx is the session id)

In addition, review the admin debug log in the following directory:

UNIX: /usr/opensv/netbackup/logs/admin
Windows: *install_path*\NetBackup\logs\admin

Correct the error and rerun the vault session.



NetBackup Status Code: 303

Message: error encountered executing Volume Manager command

Explanation: This error occurs when a volume manager command fails during a vault job.

Recommended Action: For the actual error that caused the volume manager command to fail, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where xxx is the session id)

Try running the volume manager command (with the same arguments as in the log file) to see the actual error. Ensure that the volume manager daemons are running. Also ensure that the robot is functional and you can communicate with it (for example, inventory the robot via the GUI).

NetBackup Status Code: 304

Message: specified profile not found

Explanation: This error occurs when the profile name specified on the vault command is not defined in the vault configuration.

Recommended Action: Please rerun the vault command with a profile name that is defined in the vault configuration.

NetBackup Status Code: 305

Message: duplicate profile specified, use full robot/vault/profile

Explanation: This error occurs when duplicate profile names have been defined in two or more vault configurations and only the profile name is specified on the vault command.

Recommended Action: You must rerun the vault command with the triplet *robot_name/vault_name/profile_name*. The triplet will uniquely identify the profile in your vault configuration.

NetBackup Status Code: 306

Message: errors encountered, partial success

Explanation: This error occurs when a vault job is partially successful, in other words, when not all images have been successfully duplicated and/or the catalog backup failed.



Recommended Action: For more information, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where `xxx` is the session id)

A common cause of failure is the lack of resources, such as no more media available in the specified pools for duplication and catalog backup. Correct the problem and rerun the vault job. Note that the NetBackup scheduler will retry a vault job that has terminated with this error.

NetBackup Status Code: 307

Message: eject process has already been run for the requested vault session

Explanation: This error occurs when `vlteject` is run to eject media for a session id for which media has already been ejected.

Recommended Action: Rerun `vlteject` for another session id for which media has not been ejected.

NetBackup Status Code: 308

Message: no images duplicated

Explanation: This error occurs when vault failed to duplicate any images.

Recommended Action: For more information, review the vault debug log in the following directory:

UNIX: `/usr/opensv/netbackup/logs/vault`
 Windows: `install_path\NetBackup\logs\vault`

Also review the `detail.log` in each of the `sidxxx` directories that had problems:

UNIX: `/usr/opensv/netbackup/vault/sessions/vault_name/sidxxx`
 Windows: `install_path\NetBackup\vault\sessions\vault_name\sidxxx`

(where `xxx` is the session id)

Look for the log entry that gives the total number of images processed. A common cause of failure is a lack of resources, such as no more media available in the specified pools for duplication. Correct the problem and rerun the vault job. Note that the NetBackup scheduler will retry a vault job that has terminated with this error. Review the admin debug log for `bpduplicate` entries and the `bptm` debug log.



NetBackup Status Code: 309

Message: report requested without eject being run

Explanation: This error occurs when a report is run that requires media to have been ejected first.

Recommended Action: Perform one of these actions:

- ◆ Rerun `vlteject` or `vltopmenu` to eject the media for the session before generating the reports.
- ◆ Reconfigure the profile to allow the eject step to be performed when the next vault session for this profile runs.
- ◆ Disable the report generation in the profile for reports that require media to be ejected.

NetBackup Status Code: 310

Message: invalid configuration for duplication to disk

Explanation: This error occurs when an invalid disk storage unit is configured in the vault profile used to duplicate images to disk, or when the profile is configured to create more than one copy and one of the copies is targeted for a disk storage unit. The latter configuration will be prevented by the vault interface and should not occur unless the vault configuration file has been manually altered.

Recommended Action: Ensure that a valid disk storage unit is configured in the profile by means of the duplication tab. Also ensure that the vault configuration file has not been manually altered.

NetBackup Status Code: 500

Message: NB-Java application server not accessible - maximum number of connections exceeded.

Explanation: Indicates that an attempted login failed because the maximum number of NetBackup-Java user services has been achieved. Although the number of allowed user services is very large (>100), it is possible to reach the maximum.

Recommended Action: Ask other users to log off (this limit is not configurable).

NetBackup Status Code: 501

Message: You are not authorized to use this application.

Explanation: The user is not authorized to use one of the NetBackup Java Administration utilities on the host specified in the login dialog.

Recommended Action: Check the `/usr/opensv/java/auth.conf` file on the host specified in the NetBackup-Java login dialog for the proper authorization. If the `auth.conf` file does not exist, it must be created with the proper entry for this user name. Refer to the *NetBackup System Administrator's Guide for UNIX* for more details on the `auth.conf` file.

NetBackup Status Code: 502

Message: No authorization entry exists in the `auth.conf` file for user name *username*. None of the NB-Java applications are available to you.

Explanation: The user name is not authorized to use any NetBackup-Java applications on the host specified in the login dialog.

Recommended Action: Check the `/usr/opensv/java/auth.conf` file on the machine (host name) specified in the NetBackup-Java login dialog for the proper authorization. If the file does not exist, it must be created with the proper entry for this user name. Refer to the *NetBackup System Administrator's Guide for UNIX* for more details on the `auth.conf` file.

NetBackup Status Code: 503

Message: Invalid username.

Explanation: For login to a UNIX host, the user name is not recognized by the NetBackup Java application server on the host where the login is requested.

For login to a Windows host, the NetBackup-Java authentication service on the host where the login is requested does not have sufficient privileges for granting the login request.

Recommended Action:

- ◆ For UNIX hosts: the user name must be a valid user name in the `passwd` file on the host specified in the login dialog.
- ◆ For Windows hosts: refer to the LogonUser function in the section titled Client/Server Access Control Functions of the *Windows NT Platform Software Developer's Kit* to determine the required privileges.

NetBackup Status Code: 504

Message: Incorrect password.

Explanation: For login to a UNIX host, the user name is recognized on the host where the login is requested, but the password supplied is incorrect.

For login to a Windows host, the attempt to log in the user has failed. The failure could be due to an unrecognized user in the specified domain.

Recommended Action:



- ◆ Enter the correct password.
- ◆ On Windows hosts: The exact error can be found in the `bpjava-msvc` log file. For more details, refer to the LogonUser function in the section Client/Server Access Control Functions of the *Windows NT Platform Software Developer's Kit*.

NetBackup Status Code: 505

Message: Can not connect to the NB-Java authentication service on (host) on the configured port - *configured_port_number*.

Explanation: The initial connection from the NetBackup-Java interface to its authentication service is on the port mentioned in the error message. The port is either being used by another application, or the NetBackup-Java interface and its application server are not configured with the same port. The default port is 13722.

Recommended Action:

1. Compare the `bpjava-msvc` entry in the `/etc/services` file with the `SERVER_PORT` entry in `/usr/opensv/java/nbj.conf` file. They must match.
2. Ensure that no other application is using the port configured for the NetBackup-Java interface.

NetBackup Status Code: 506

Message: Can not connect to the NB-Java user service on (host) on port *port_number*.

Explanation: Once the user name on the login dialog is validated for access by the NetBackup-Java authentication service, a NetBackup-Java user service is used for all other service requests from the NetBackup Administration interface. Communication between the NetBackup-Java interface and user service is attempted on the port number specified in the error message. Refer to the various port configuration options described in the *NetBackup System Administrator's Guide* (UNIX or Windows).

- ◆ On UNIX: the port configuration options are specified in the `/usr/opensv/netbackup/bp.conf` file.
- ◆ On Windows: from the NetBackup Administration Console, select Host Properties. Select Properties from the Actions menu. The General Server tab contains the port options. For more information, refer to the *NetBackup System Administrator's Guide for Windows*.

Recommended Action:

1. Restart the NetBackup-Java interface and log in again.
2. If the problem persists, enable detailed debug logging.

3. Restart the NetBackup Java Administration interface and examine the logs.

NetBackup Status Code: 507

Message: Socket connection to the NB-Java user service has been broken. Please retry your last operation.

Explanation: The connection was broken to the NetBackup Java application server that is running on the NetBackup host you are logged in to.

Recommended Action:

1. Retry the last operation.
2. If the problem persists, restart the NetBackup-Java interface and try again.
3. If the problem still persists, enable detailed debug logging as explained under “Enabling Detailed Debug Logging” in Chapter 3.
4. Restart the NetBackup-Java interface and examine the logs.

Note You may be having network or system problems unrelated to NetBackup.

NetBackup Status Code: 508

Message: Can not write file.

Explanation: This error is caused by one of the following:

- ◆ The NetBackup-Java user service has attempted to write to a file that does not have write permissions. The solution is to enable write privileges.
- ◆ The NetBackup-Java user service has attempted to write to a temporary file whose unique name cannot be constructed. This condition is unlikely, but could result from an exhaustion of system resources (from the filling of the name space).

Recommended Action: The specific details may be retrieved from the user service log files. Enable detailed debug logging as explained under “Enabling Detailed Debug Logging” in Chapter 3.

NetBackup Status Code: 509

Message: Can not execute program.

Explanation: The NetBackup-Java authentication or user service has reported an error relating to the creation (or demise) of a child job process. The NetBackup-Java service programs create separate jobs to accomplish specific tasks, as follows. The NetBackup-Java authentication service creates the NetBackup-Java user service. Upon



successful creation of and connection to the NetBackup-Java user service, all other child processes are created by the NetBackup-Java user service on behalf of requests made by the NetBackup-Java interface.

Note The cause of status code 509 can be found in the appropriate log file, either for `bpjava-msvc` or `bpjava-usvc`. The cause can be categorized as one of the following:

- ◆ A job (started by either the NetBackup-Java authentication service or user service) no longer exists, and did not report its result status.
- ◆ A job (started by either the NetBackup-Java authentication service or user service) cannot be monitored by the NetBackup-Java service. This is probably due to a lack of system resources (insufficient memory).
- ◆ The maximum number of non-transient activity monitor jobs (>100) have already been started.

Recommended Action:

1. If the problem persists, restart the NetBackup-Java interface and try again.
2. If the problem still persists, enable detailed debug logging as explained under “Enabling Detailed Debug Logging” in Chapter 3.
3. Restart the NetBackup-Java interface and examine the logs.

Note The error is probably the result of a system resource issue. When detailed debug logging has been enabled, the details may be retrieved from the `bpjava-msvc` or `bpjava-usvc` log files.

NetBackup Status Code: 510

Message: File already exists: *file_name*

Explanation: The NetBackup-Java user service has attempted to create a file that already exists.

Recommended Action: Remove the file, which can be identified in the user service log files. Refer to “Troubleshooting the Administration Console” on page 51.

NetBackup Status Code: 511

Message: NB-Java application server interface error: *Java exception*



Explanation: This is a generic error for all non-socket IO/connection-broken related errors (status code 507) that could occur when processing the data from the NetBackup-Java authentication or user services. The Java exception will provide some additional detail about the error.

This error usually results from system or network problems.

Recommended Action:

1. If the problem persists, restart the NetBackup-Java interface and try again.
2. If the problem still persists, enable detailed debug logging as explained under “Enabling Detailed Debug Logging” in Chapter 3.
3. Restart the NetBackup-Java interface and examine the logs.

Note The error is probably the result of a system resource issue. When detailed debug logging has been enabled, the details may be retrieved from the `bpjava-msvc` or `bpjava-usvc` log files.

NetBackup Status Code: 512

Message: Internal error - a bad status packet was returned by NB-Java application server that did not contain an exit status code.

Explanation: The NetBackup-Java authentication or user service returned a data packet indicating an error, but no status code or error message was contained within it.

Recommended Action:

1. If the problem persists, restart the NetBackup-Java interface and try again.
2. If the problem still persists, enable detailed debug logging as explained under “Enabling Detailed Debug Logging” in Chapter 3.
3. Restart the NetBackup-Java interface and examine the logs.

Note The error is probably the result of a system resource issue. When detailed debug logging has been enabled, the details may be retrieved from the `bpjava-msvc` or `bpjava-usvc` log files.

NetBackup Status Code: 513

Message: `bpjava-msvc`: the client is not compatible with this server version (*server_version*).



Explanation: The NetBackup-Java application server (on the remote host you are logging in to) is not the same version as the NetBackup-Java interface on your local host. The two are therefore incompatible.

Recommended Action:

- ◆ Log in to a different NetBackup remote host.
- ◆ Upgrade the NetBackup software on either the machine specified in the login dialog or on the local host where you started the NetBackup Java interface.

NetBackup Status Code: 514

Message: NB-Java: bpjava-msvc is not compatible with this application version (*application_version*). You may try login to a different NetBackup host or exit the application. The remote NetBackup host will have to be configured with the same version of NetBackup as the host you started the application on.

Explanation: The NetBackup-Java application server (on the remote host you are logging in to) is not the same version as the NetBackup-Java interface on your local host. The two are therefore incompatible.

Recommended Action:

- ◆ Log in to a different NetBackup remote host.
- ◆ Upgrade the NetBackup software on either the machine specified in the login dialog or on the local host where you started the NetBackup Java interface.

NetBackup Status Code: 516

Message: Could not recognize or initialize the requested locale - (*locale_NB-Java_was_started_in*).

Explanation: This status concerns the UNIX locale configuration (or Windows regional settings) defined on the host that was specified in the NB-Java login dialog. At login, the locale configuration is passed to the NB-Java authentication service. Status 516 is generated if the locale is not recognized or if the locale of the user service could not be initialized.

Recognition of a valid locale is determined by the rules in the `/usr/opensv/msg/.conf` file on UNIX and in the `install_path\msg\lc.conf` file on Windows. When the locale is validated, initialization of the locale in the user service's environment is attempted (by means of `setlocale`).

Recommended Action: On the host that was specified in the NB-Java login dialog, check the NetBackup configuration file mentioned above to ensure there is a mapping available for the indicated locale. (For information on locale configuration and mapping, refer to the

NetBackup System Administrator's Guide.) If there is a mapping, try to set the mapped locale on the host that was specified in the NB-Java login dialog. This system may not be configured properly.

NetBackup Status Code: 577

Message: Can not connect to the NB-Java user service via VNETD on (host) on port (configured_port_number)

Explanation: None

Recommended Action: None

Messages

This section lists the NetBackup error messages alphabetically. The status code is included in parentheses after the message. Refer to the previous list of status codes for explanations and recommended actions.

/usr/opensv/netbackup/bp.conf not found

(NetBackup Status Code 110)

a protocol error has occurred

(NetBackup Status Code 232)

access to server backup restore manager denied

(NetBackup Status Code 206)

access to the client was not allowed

(NetBackup Status Code 59)

a child process failed for an unknown reason

(NetBackup Status Code 258)

afs/dfs command failed

(NetBackup Status Code 78)



allocation failed

(NetBackup Status Code 10)

all volumes are not available to eject

(NetBackup Status Code 297)

an entry in the filelist expanded to too many characters

(NetBackup Status Code 70)

an error occurred when calling vltcore

(NetBackup Status Code 289)

an extension package is needed but was not installed

(NetBackup Status Code 9)

an invalid entry was encountered

(NetBackup Status Code 223)

another NB database backup is already in progress

(NetBackup Status Code 125)

archive file removal failed

(NetBackup Status Code 4)

a session is already running for this vault

(NetBackup Status Code 275)

attempt to open a log file failed

(NetBackup Status Code 288)

authentication failed

(NetBackup Status Code 160)

Auspex SP/Backup failure

(NetBackup Status Code 88)

Backup Exec operation failed

(NetBackup Status Code 151)

backup restore manager failed to read the file list

(NetBackup Status Code 53)

backups are not allowed to span media

(NetBackup Status Code 166)

bpjava-msvc: the client is not compatible with this server version (*server_version*)

(NetBackup Status Code 513)

bpstart_notify failed

(NetBackup Status Code 73)

can't connect to client

(NetBackup Status Code 58)

cannot connect on socket

(NetBackup Status Code 25)

cannot connect to server backup restore manager

(NetBackup Status Code 205)

Can not connect to the NB-Java authentication service on the configured port - *configured_port_number*

(NetBackup Status Code 505)

Can not connect to the NB-Java user service on port *port_number*

(NetBackup Status Code 506)



Can not connect to the NB-Java user service via VNETD on (host) or port (configured_port_number)

(NetBackup Status Code 577)

cannot create log file

(NetBackup Status Code 257)

Can not execute program

(NetBackup Status Code 509)

cannot find configuration database record for requested NB database backup

(NetBackup Status Code 120)

cannot find requested volume pool in Media Manager volume database

(NetBackup Status Code 167)

cannot find the boot, vault, or profile in the vault configuration

(NetBackup Status Code 266)

cannot find the local host name

(NetBackup Status Code 267)

cannot get a bound socket

(NetBackup Status Code 146)

cannot make required directory

(NetBackup Status Code 35)

cannot overwrite media, data on it is protected

(NetBackup Status Code 168)

cannot perform specified media import operation

(NetBackup Status Code 176)

cannot position to correct image

(NetBackup Status Code 94)

cannot read backup header, media may be corrupted

(NetBackup Status Code 173)

cannot read media header, may not be NetBackup media or is corrupted

(NetBackup Status Code 172)

Can not write file

(NetBackup Status Code 508)

child process killed by signal

(NetBackup Status Code 27)

client backup failed to read the file list

(NetBackup Status Code 67)

client backup failed to receive the CONTINUE BACKUP message

(NetBackup Status Code 66)

client backup was not attempted

(NetBackup Status Code 195)

client backup was not attempted because backup window closed

(NetBackup Status Code 196)

client cannot read the mount table

(NetBackup Status Code 60)

client connection refused

(NetBackup Status Code 57)



client did not start

(NetBackup Status Code 49)

client hostname could not be found

(NetBackup Status Code 48)

client is not validated to perform the requested operation

(NetBackup Status Code 135)

client is not validated to use the server

(NetBackup Status Code 131)

client name mismatch

(NetBackup Status Code 39)

client process aborted

(NetBackup Status Code 50)

client timed out waiting for bpend_notify to complete

(NetBackup Status Code 75)

client timed out waiting for bpstart_notify to complete

(NetBackup Status Code 74)

client timed out waiting for the continue message from the media manager

(NetBackup Status Code 65)

client timed out waiting for the file list

(NetBackup Status Code 68)

client's network is unreachable

(NetBackup Status Code 56)

client/server handshaking failed

(NetBackup Status Code 26)

communication interrupted

(NetBackup Status Code 234)

connection refused by server backup restore manager

(NetBackup Status Code 204)

continue

(NetBackup Status Code 221)

could not deassign media due to Media Manager error

(NetBackup Status Code 177)

could not get group information

(NetBackup Status Code 38)

could not get passwd information

(NetBackup Status Code 30)

could not set group id for process

(NetBackup Status Code 32)

could not set user id for process

(NetBackup Status Code 31)

daemon fork failed

(NetBackup Status Code 148)

daemon is already running

(NetBackup Status Code 145)



Messages

Database backup failed

(NetBackup Status Code 294)

database system error

(NetBackup Status Code 220)

density is incorrect for the media id

(NetBackup Status Code 179)

done

(NetBackup Status Code 222)

duplicate profile specified, use full robot/vault/profile

(NetBackup Status Code 305)

EC_badop

(NetBackup Status Code 113)

EC_end

(NetBackup Status Code 115)

EC_error

(NetBackup Status Code 114)

eject process could not obtain information about the robot

(NetBackup Status Code 295)

eject process failed to start

(NetBackup Status Code 292)

eject process has already been run for the requested vault session

(NetBackup Status Code 307)



eject process has been aborted

(NetBackup Status Code 293)

error caused by invalid data in vault configuration file

(NetBackup Status Code 284)

error creating or getting message queue

(NetBackup Status Code 209)

error encountered attempting backup of catalog (Two Phase BU)

(NetBackup Status Code 302)

error encountered executing Volume Manager command

(NetBackup Status Code 303)

error obtaining date of last backup for client

(NetBackup Status Code 207)

error occurred during initialization, check configuration file

(NetBackup Status Code 103)

error receiving information on message queue

(NetBackup Status Code 210)

error requesting media (tpreq)

(NetBackup Status Code 98)

error sending information on message queue

(NetBackup Status Code 212)

errors encountered, partial success

(NetBackup Status Code 306)



evaluation software has expired. See www.veritas.com for ordering information

(NetBackup Status Code 161)

events out of sequence - image inconsistency

(NetBackup Status Code 229)

execution of a vault notify script failed

(NetBackup Status Code 272)

execution of the specified system command returned a nonzero status

(NetBackup Status Code 77)

failed accessing daemon lock file

(NetBackup Status Code 158)

failed attempting to copy (consolidated) report file

(NetBackup Status Code 287)

failed closing mail pipe

(NetBackup Status Code 102)

failed opening mail pipe

(NetBackup Status Code 101)

failed reading policy database information

(NetBackup Status Code 218)

failed reading global config database information

(NetBackup Status Code 215)

failed reading retention database information

(NetBackup Status Code 216)

failed reading storage unit database information

(NetBackup Status Code 217)

failed reading user directed filelist

(NetBackup Status Code 208)

failed trying to allocate memory

(NetBackup Status Code 36)

failed trying to exec a command

(NetBackup Status Code 29)

failed trying to fork a process

(NetBackup Status Code 28)

failed waiting for child process

(NetBackup Status Code 34)

failed while trying to send mail

(NetBackup Status Code 33)

fatal NB media database error

(NetBackup Status Code 91)

File already exists: *file_name*

(NetBackup Status Code 510)

file close failed

(NetBackup Status Code 15)

file does not exist

(NetBackup Status Code 142)



Messages

file open failed

(NetBackup Status Code 12)

file path specified is not absolute

(NetBackup Status Code 141)

file pathname exceeds the maximum length allowed

(NetBackup Status Code 105)

file read failed

(NetBackup Status Code 13)

file write failed

(NetBackup Status Code 14)

found no images or media matching the selection criteria

(NetBackup Status Code 190)

getservbyname failed

(NetBackup Status Code 19)

handshaking failed with server backup restore manager

(NetBackup Status Code 201)

host is unreachable

(NetBackup Status Code 47)

inadequate buffer space

(NetBackup Status Code 235)

Incorrect password

(NetBackup Status Code 504)



Incorrect server platform identifier

(NetBackup Status Code: 162)

Internal error - a bad status packet was returned by NB-Java application server that did not contain an exit status code

(NetBackup Status Code 512)

invalid command parameter

(NetBackup Status Code 20)

invalid command protocol

(NetBackup Status Code 143)

invalid command usage

(NetBackup Status Code 144)

invalid configuration for duplication to disk

(NetBackup Status Code 310)

invalid file pathname

(NetBackup Status Code 104)

invalid file pathname found, cannot process request

(NetBackup Status Code 106)

invalid filelist specification

(NetBackup Status Code 69)

invalid jobID

(NetBackup Status Code 273)

invalid request

(NetBackup Status Code 133)



Messages

Invalid username

(NetBackup Status Code 503)

licensed use has been exceeded

(NetBackup Status Code 159)

logic error encountered

(NetBackup Status Code 256)

main bpsched is already running

(NetBackup Status Code 244)

master server request failed

(NetBackup Status Code 149)

media close error

(NetBackup Status Code 87)

media id is either expired or will exceed maximum mounts

(NetBackup Status Code 169)

media id is not in NetBackup volume pool

(NetBackup Status Code 178)

media id must be 6 or less characters

(NetBackup Status Code 171)

Media Manager device daemon (ltid) is not active

(NetBackup Status Code 80)

Media Manager volume daemon (vmd) is not active

(NetBackup Status Code 81)



media manager detected image that was not in tar format

(NetBackup Status Code 92)

media manager found wrong tape in drive

(NetBackup Status Code 93)

media manager killed by signal

(NetBackup Status Code 82)

media manager received no data for backup image

(NetBackup Status Code 90)

media manager - system error occurred

(NetBackup Status Code 174)

media open error

(NetBackup Status Code 83)

media position error

(NetBackup Status Code 86)

media read error

(NetBackup Status Code 85)

media write error

(NetBackup Status Code 84)

NB database backup failed, a path was not found or is inaccessible

(NetBackup Status Code 124)

NB database backup header is too large, too many paths specified

(NetBackup Status Code 126)



NB database recovery failed, a process has encountered an exceptional condition

(NetBackup Status Code 128)

NB image database contains no image fragments for requested backup id/copy number

(NetBackup Status Code 165)

NB-Java application server interface error: *Java exception*

(NetBackup Status Code 511)

NB-Java application server not accessible - maximum number of connections exceeded

(NetBackup Status Code 500)

NB-Java: bpjava-msvc is not compatible with this application version (*application_version*). You may try login to a different NetBackup host or exit the application. The remote NetBackup host will have to be configured with the same version of NetBackup as the host you started the application on.

(NetBackup Status Code 514)

NDMP backup failure

(NetBackup Status Code 99)

network connection broken

(NetBackup Status Code 40)

network connection timed out

(NetBackup Status Code 41)

network read failed

(NetBackup Status Code 42)

network write failed

(NetBackup Status Code 44)

no active policies contain schedules of the requested type for this client

(NetBackup Status Code 198)

no active policies in the configuration database are of the correct client type

(NetBackup Status Code 246)

No authorization entry exists in the auth.conf file for username *username*. None of the NB-Java applications are available to you.

(NetBackup Status Code 502)

no entity was found

(NetBackup Status Code 227)

no files specified in the file list

(NetBackup Status Code 112)

no images duplicated

(NetBackup Status Code 308)

no images were successfully processed

(NetBackup Status Code 191)

no media is defined for the requested NB database backup

(NetBackup Status Code 121)

no profile was specified

(NetBackup Status Code 274)

no schedules of the correct type exist in this policy

(NetBackup Status Code 240)

no storage units available for use

(NetBackup Status Code 213)



no vault session id was found

(NetBackup Status Code 269)

none of the files in the file list exist

(NetBackup Status Code 71)

none of the requested files were backed up

(NetBackup Status Code 2)

not all requested files were restored

(NetBackup Status Code 175)

number of media has exceeded the capacity of MAP

(NetBackup Status Code 291)

one or more errors detected during consolidated eject processing

(NetBackup Status Code 290)

operation not allowed during this time period

(NetBackup Status Code 199)

operation requested by an invalid server

(NetBackup Status Code 37)

operation would cause an illegal duplication

(NetBackup Status Code 242)

pipe close failed

(NetBackup Status Code 18)

premature eof encountered

(NetBackup Status Code 233)

process called but nothing to do

(NetBackup Status Code 296)

process was killed by a signal

(NetBackup Status Code 63)

regular bpsched is already running

(NetBackup Status Code 214)

report requested without eject being run

(NetBackup Status Code 309)

request attempted on a non reserved port

(NetBackup Status Code 45)

requested media id is in use, cannot process request

(NetBackup Status Code 97)

requested media id was not found in NB media database and/or MM volume database

(NetBackup Status Code 95)

required or specified copy was not found

(NetBackup Status Code 147)

required value not set

(NetBackup Status Code 152)

schedule windows overlap

(NetBackup Status Code 231)

scheduler child killed by signal

(NetBackup Status Code 211)



scheduler found no backups due to run

(NetBackup Status Code 200)

server backup restore manager's network is unreachable

(NetBackup Status Code 203)

server is not the master server

(NetBackup Status Code 153)

server name not found in the bp.conf file

(NetBackup Status Code 254)

server not allowed access

(NetBackup Status Code 46)

SERVER was not specified in /usr/opensv/netbackup/bp.conf

(NetBackup Status Code 111)

Session id assignment failed

(NetBackup Status Code 263)

Session id file is empty or corrupt

(NetBackup Status Code 265)

socket close failed

(NetBackup Status Code 22)

Socket connection to the NB-Java user service has been broken. Please retry your last operation.

(NetBackup Status Code 507)

socket open failed

(NetBackup Status Code 21)

socket read failed

(NetBackup Status Code 23)

socket write failed

(NetBackup Status Code 24)

specified device path does not exist

(NetBackup Status Code 122)

specified disk path is not a directory

(NetBackup Status Code 123)

specified media or path does not contain a valid NB database backup header

(NetBackup Status Code 127)

specified profile not found

(NetBackup Status Code 304)

storage unit characteristics mismatched to request

(NetBackup Status Code 154)

system call failed

(NetBackup Status Code 11)

system error occurred

(NetBackup Status Code 130)

system error occurred while processing user command

(NetBackup Status Code 100)

tar did not find all the files to be restored

(NetBackup Status Code 185)



Messages

tar had an unexpected error

(NetBackup Status Code 184)

tar received an invalid archive

(NetBackup Status Code 183)

tar received an invalid argument

(NetBackup Status Code 181)

tar received an invalid file name

(NetBackup Status Code 182)

tar received no data

(NetBackup Status Code 186)

tar was successful

(NetBackup Status Code 180)

termination requested by administrator

(NetBackup Status Code 150)

text exceeded allowed length

(NetBackup Status Code 225)

the archive failed to back up the requested files

(NetBackup Status Code 7)

the backup failed to back up the requested files

(NetBackup Status Code 6)

the client is not in the configuration

(NetBackup Status Code 243)



the client type is incorrect in the configuration database

(NetBackup Status Code 72)

the database contains conflicting or erroneous entries

(NetBackup Status Code 238)

the entity already exists

(NetBackup Status Code 226)

the file list is incomplete

(NetBackup Status Code 249)

the error status has been written to stderr

(NetBackup Status Code 252)

the image was not created with TIR information

(NetBackup Status Code 250)

the initiation of the vault configuration file failed

(NetBackup Status Code 271)

the library is not ready to eject volumes

(NetBackup Status Code 298)

the maximum number of jobs per client is set to 0

(NetBackup Status Code 194)

the requested operation was partially successful

(NetBackup Status Code 1)

the requested operation was successfully completed

(NetBackup Status Code 0)



the required storage unit is unavailable

(NetBackup Status Code 219)

the restore failed to recover the requested files

(NetBackup Status Code 5)

the server is not allowed to write to the client's filesystems

(NetBackup Status Code 189)

the specified policy does not exist in the configuration database

(NetBackup Status Code 230)

the specified policy is not active

(NetBackup Status Code 247)

the specified policy is not of the correct client type

(NetBackup Status Code 245)

the specified client does not exist in an active policy within the configuration database

(NetBackup Status Code 236)

the specified client does not exist in the specified policy

(NetBackup Status Code 239)

the specified schedule does not exist in an active policy in the configuration database

(NetBackup Status Code 237)

the specified schedule does not exist in the specified policy

(NetBackup Status Code 197)

the specified schedule is the wrong type for this request

(NetBackup Status Code 241)

the TIR information is zero length

(NetBackup Status Code 251)

the vault session directory is either missing or inaccessible

(NetBackup Status Code 268)

there are no active policies in the configuration database

(NetBackup Status Code 248)

there is no available MAP for ejecting

(NetBackup Status Code 299)

there was a conflicting specification

(NetBackup Status Code 224)

third-party copy backup failure

(NetBackup Status Code 170)

timed out connecting to client

(NetBackup Status Code 54)

timed out connecting to server backup restore manager

(NetBackup Status Code 202)

timed out waiting for database information

(NetBackup Status Code 51)

timed out waiting for media manager to mount volume

(NetBackup Status Code 52)

timed out waiting for the client backup to start

(NetBackup Status Code 64)



unable to allocate new media for backup, storage unit has none available

(NetBackup Status Code 96)

unable to determine the status of rbak

(NetBackup Status Code 8)

unable to locate vault directory

(NetBackup Status Code 285)

unable to mount media because its in a DOWN drive or misplaced

(NetBackup Status Code 164)

unable to obtain process id, getpid failed

(NetBackup Status Code 270)

unable to process request

(NetBackup Status Code 228)

unable to process request because the server resources are busy

(NetBackup Status Code 134)

unexpected message received

(NetBackup Status Code 43)

unimplemented error code

(NetBackup Status Code 276 - 280)

unimplemented feature

(NetBackup Status Code 16)

user id was not superuser

(NetBackup Status Code 140)

user is not validated to use the server

(NetBackup Status Code 132)

valid archive image produced, but no files deleted due to non-fatal problems

(NetBackup Status Code 3)

vault configuration file not found

(NetBackup Status Code 259)

vault internal error 260

(NetBackup Status Code 260)

vault internal error 261

(NetBackup Status Code 261)

vault internal error 262

(NetBackup Status Code 262)

vault internal error 286

(NetBackup Status Code 286)

vltCore Error

(NetBackup Status Code 281)

vltCore System Error

(NetBackup Status Code 282)

vltCore UnhandledError

(NetBackup Status Code 283)

vmchange api_eject command failed

(NetBackup Status Code 301)



Messages

vmchange eject verify not responding

(NetBackup Status Code 300)

wbak exited abnormally

(NetBackup Status Code 62)

wbak was killed

(NetBackup Status Code 61)

You are not authorized to use this application

(NetBackup Status Code 501)



Media Manager Status Codes and Messages

5

This chapter lists Media Manager status codes and messages. In each of the following subsections, the status codes are listed in numerical order, followed by an explanation and recommended action.

- ◆ Media Manager Status Codes
- ◆ Device Configuration Status Codes
- ◆ Format Optical Status Codes
- ◆ Device Management Status Codes
- ◆ Robotic Status Codes
- ◆ Robotic Error Codes

At the end of this chapter is a section titled “Messages,” which lists all Media Manager messages alphabetically. Following each message is a pointer to the section in this chapter that contains detailed information about the message.

Status Codes

Note The term *media server*, as distinct from *master server* or *server*, does not apply to the NetBackup BusinessServer product. When troubleshooting a BusinessServer installation, please ignore any references to media server.

Media Manager Status Codes

These status codes appear in exit status and command output for most Media Manager commands, media and device management user interfaces, and system or debug logs.

Media Manager Status Code: 1

Message: request completed

Explanation: A requested operation was completed. The operation may have been one of several related operations for a particular task.



Recommended Action: None.

Media Manager Status Code: 2

Message: system error

Explanation: A system call failed. This status code is used for a generic system call failure that does not have its own status code.

Recommended Action:

1. Check for other error messages in the command or interface output to determine which system call failed. Enable debug logging, retry the operation, and check the debug log files for more specific error messages.
2. Check the system application log for error and warning messages.
3. Verify that the system is not running out of virtual memory. If virtual memory is the problem, shut down unused applications or increase the amount of virtual memory. To increase virtual memory on Windows:
 - a. Display the Control Panel.
 - b. Double-click System.
 - c. On the Performance tab, set Virtual Memory to a higher value. (On Windows 2000, select Performance Options from the Advanced tab.)
4. Verify that all product binaries are properly installed.
5. Verify that there are no unexpected Media Manager processes running by executing `vmps`. Some processes are expected to remain running, though some processes that are not going away could indicate a more serious problem, such as a hung system call.

Media Manager Status Code: 3

Message: must be root user to execute command

Explanation: The process was started by a user or process that did not have root privileges (on UNIX) or administrator privileges (on Windows).

Recommended Action: If desired, give the user or process administrator privileges (on Windows) or root privileges (on UNIX) and retry the operation.

Media Manager Status Code: 4

Message: invalid command usage



Explanation: A Media Manager command was executed with improper options or there is an incompatibility between components or versions of the product.

Recommended Action:

1. Examine command output, debug logs, and system logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the usage statement for expected usage and compare with the parameters being sent to start the new process.
3. Verify that all Media Manager binaries are at a compatible version level.

Media Manager Status Code: 5

Message: daemon resources are busy

Explanation: A requested operation could not be processed because resources were busy.

Recommended Action: Check the status of any resources used by the requested operation. On a robotic inventory request, verify that the inventory operation completes within the allotted time (7 minutes for robot types ACS, LMF, RSM, TLH, TLM, TS8, TSD, TSH, and 32 minutes for other robot types).

Media Manager Status Code: 6

Message: invalid protocol request

Explanation: An invalid request was sent to a Media Manager robotic process or operator request process.

Recommended Action:



1. Examine command output, debug logs, and system logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the target components (for example, `vmid` and robotic processes on local or remote hosts) and verify that all Media Manager binaries are at compatible version level.

Media Manager Status Code: 7

Message: daemon terminated

Explanation: The process is inactive or is terminating (or has terminated) from an event or signal, or as a direct result of a request from an authorized user or process.

Recommended Action: If the targeted product component is needed but has terminated, restart the daemons/services on the targeted host.

Media Manager Status Code: 8

Message: invalid media ID

Explanation: A process performing a media-related operation encountered an empty or incorrectly formatted media identifier, or was passed a media ID that could not be operated on as requested.

Recommended Action:

1. Examine command output and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the media ID, where requested, is not blank.

3. Ensure that the specified media IDs contain valid characters only: alphanumeric characters, and the period (.), plus sign (+), and underscore (_). A hyphen (-) is also a valid character when not the first character in the media ID.
4. If the media is for optical disk, ensure that the media ID of the optical partner is specified and contains only valid characters.
5. If the media ID is for optical disk in a TLM robot, ensure that the format of the ID and partner are "Axxxxxx" and "Bxxxxx," respectively.
6. If media are specified to be ejected from a library, ensure that they exist in the volume database and are associated with the correct robot number.
7. Ensure that the media ID is from 1 to 6 characters in length.
8. Ensure that a valid media and seed were specified.
9. If the operation is an inventory request for an ACS robot, use the `robtest` utility to verify that the ACS interface is returning cleaning media IDs both in the query volume list and in the query cleaning volume list.

Media Manager Status Code: 9

Message: invalid media type

Explanation: A process performing a media-related operation encountered an unknown, missing, or incompatible media type specifier.

Recommended Action:

1. If running a robot inventory on a robot of type ACS, LMF, RSM, TLH, or TLM, ensure that the vendor media type returned from the robot control software is supported and recognized by the version of Media Manager that is installed.
2. If using a command line interface directly, verify that a valid media type has been passed, according to `vmadd(1m)` command line documentation, which applies to all Media Manager command line interfaces.
3. Ensure that an operation valid only for cleaning media has not been requested on a media ID that does not correspond to cleaning tape.
4. Ensure that the media type in all barcode rules is a valid media type or the ordinal zero (0), to represent the default media type.



Media Manager Status Code: 10

Message: invalid barcode

Explanation: A process performing a media-related operation encountered an unknown, missing, or incompatible barcode.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the barcode, where requested, is not blank.
3. Ensure that the specified barcodes contain valid characters only: alphanumeric characters, and the period (.), plus sign (+), and underscore (_). A hyphen (-) is also a valid character when not the first character in the media ID.
4. Ensure that the number of characters in the barcode does not exceed the maximum allowed for the robot type.
5. Ensure that the barcode tag in all barcode rules is a subset of a valid, supported barcode format.

Media Manager Status Code: 11

Message: invalid description

Explanation: The volume description exceeds 25 ASCII characters in length, or contains unprintable characters.

Recommended Action: When adding or changing a volume record or barcode rule record, ensure that the description field contains only printable characters and is not longer than 25 ASCII characters.

Media Manager Status Code: 12

Message: invalid robot type



Explanation: A requested operation encountered a case where a specified robot type or a volume's robot type differed from the type of robot required to perform the operation in the current configuration.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a robot type that supports the volume's media type.
3. Check the volume database and ensure that the specified robot type agrees with that for all volumes having the specified robot number.
4. If a robot type is required for the requested operation, ensure that a robot type has been specified.

Media Manager Status Code: 13

Message: invalid robot number

Explanation: The robot number was not specified or was not within the allowable range.

Recommended Action: Specify a robot number in the range of 0 to 32767.

Media Manager Status Code: 14

Message: invalid robot host

Explanation: A requested operation encountered a case where the robot control host was either not specified, not valid for the given robot type, not in an acceptable format, or exceeded the allowed length of a robot control host name.

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. If possible, re-attempt the requested operation using another user interface that supports the type of request.

Media Manager Status Code: 15

Message: invalid volgroup

Explanation: A requested operation encountered a case where the volume group was either not specified, not in an acceptable format, or exceeded the allowed length of a volume group.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a volume group where one is required, ensuring that it is no longer than 25 ASCII characters in length, without containing any whitespace or unprintable characters.

Media Manager Status Code: 16

Message: invalid robot coord1

Explanation: A requested operation encountered a missing or out-of-range robot slot number, or a move by volume group residence was attempted when the volume had not originated from a valid robotic library slot.

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a slot number (robot coordinate 1) where required, ensuring that it is within the allowable range of slot numbers for the given robot type.

Media Manager Status Code: 17

Message: invalid robot coord2

Explanation: A requested operation encountered a missing or invalid robot coordinate 2 (used for the optical platter side), or a move by volume group residence was attempted when the volume had not been previously associated with a valid robot coordinate 2 (optical platter side).

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a robot coordinate 2 value of zero (0) for non-optical media, or specify either A or B to represent the platter side for optical media.

Media Manager Status Code: 18

Message: cannot allocate requested memory

Explanation: Allocation of system memory failed. This error occurs when there is insufficient system memory available. The system may have too little physical and virtual memory to handle the current load of processes.

Recommended Action: Free up memory by terminating unneeded processes that consume a lot of memory. Add more swap space or physical memory.



Media Manager Status Code: 19

Message: invalid volume database host

Explanation: A requested operation encountered a missing or invalid volume database host, or a request was sent to a host running a version of the product that does not support the requested operation.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a valid volume database host on which a version of `vmc`, the volume daemon (or NetBackup Volume Manager service), or operator request daemon/process is running that supports the requested operation.

Media Manager Status Code: 20

Message: protocol error

Explanation: Message communications (handshaking) was not correct.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Retry the operation and examine the logs. Ensure that there are no embedded whitespaces in fields that do not allow embedded whitespace.



Media Manager Status Code: 21

Message: cannot obtain daemon lockfile

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) could not obtain an internal software lock.

Recommended Action: Check for the existence and permissions of the lock file itself and the lock file directory, which is `/usr/opensv/volmgr/misc/vmd.lock` (UNIX) or `install_path\Volmgr\misc\vmd.lock` (Windows). Create the directory/folder and adjust the permissions as needed so that vmd can obtain the lock, which is `/usr/opensv/volmgr/misc/vmd.lock` (UNIX) or `install_path\Volmgr\misc\vmd.lock` (Windows).

Media Manager Status Code: 22

Message: database initialization failed

Explanation: Initialization problems were encountered in the robotic test utility while trying to read the device databases. This is a generic return code for device database-related issues.

Recommended Action: Check the command output for detailed errors. Use the `tpconfig` interface or another device management interface to verify database access and integrity.

Media Manager Status Code: 23

Message: database close operation failed

Explanation: An error occurred when vmd attempted to close the volume database.

Recommended Action: Examine the daemon debug log for a more detailed message on the system error, as follows.

1. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
2. Retry the operation and examine the logs.

Media Manager Status Code: 24

Message: database already open

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) was about to open the volume database, but found that it was already open.



Recommended Action: Check to see if the volume database locking mechanism is working correctly, and send requests such as volume queries to vmd to see if it is functioning correctly. Try stopping and starting vmd to clear the unexpectedly open file descriptor.

Media Manager Status Code: 25

Message: failed making the database directory

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) could not create the database directory/folder.

Recommended Action: Determine why the directory `/usr/opensv/volmgr/database` (UNIX) or folder `install_path\Volmgr\database` (Windows) cannot be created. On Windows, check which account the NetBackup Volume Manager service is running under and compare it against the security properties of the database folder.

Media Manager Status Code: 26

Message: database open operation failed

Explanation: A database file could not be opened.

Recommended Action: Check for the existence and permissions of the `volDB` file in the `/usr/opensv/volmgr/database` directory (UNIX) or `install_path\Volmgr\database` folder (Windows). Also check for the existence and permissions of the following files in the `/usr/opensv/share` directory (UNIX) or `install_path\NetBackup\share` folder (Windows):

- ◆ `external_robotics.txt`
- ◆ `external_densities.txt`
- ◆ `external_drivetypes.txt`
- ◆ `external_mediatypes.txt`
- ◆ `external_attributes.txt`

Media Manager Status Code: 27

Message: database read record operation failed

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) encountered a read error while reading a volume database record.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. The volume database may be corrupted. Restore an older volume database from a saved version or from catalog backups.

Media Manager Status Code: 28

Message: database read operation read too few bytes

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) encountered a record that was smaller than expected while reading a volume database record.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. The volume database may be corrupted. Restore an older volume database from a saved version or from catalog backups.

Media Manager Status Code: 29

Message: database lock operation failed

Explanation: vmd (the Media Manager volume daemon on UNIX) encountered a system call error while attempting to lock the volume database. This error code applies to UNIX servers only.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon, or start `vmd` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Execute `vmops` to ensure that `vmd` and `vmdb_dump` are not both running at the same time.
3. Ensure that no other process has a lock on the database file
`/usr/opensv/volmgr/database/volDB`.

Media Manager Status Code: 30

Message: database seek operation failed

Explanation: `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) encountered a read error while seeking (positioning) within the volume database.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. The volume database may be corrupted. Restore an older volume database from a saved version or from catalog backups.

Media Manager Status Code: 31

Message: database unlock operation failed

Explanation: `vmd` (the Media Manager volume daemon on UNIX) encountered a system call error while attempting to unlock the volume database.

Recommended Action:



1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon, or start `vmd` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Execute `vmops` to ensure that `vmd` and `vmdb_dump` are not both running at the same time.
3. Ensure that no other process is locking or unlocking the database file `/usr/opensv/volmgr/database/volDB`.

Media Manager Status Code: 32

Message: database write record operation failed

Explanation: `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) encountered an error while writing a volume database record.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and available file system space for writing to the database `/usr/opensv/volmgr/database/volDB` (UNIX) or `install_path\Volmgr\database\volDB` (Windows).

Media Manager Status Code: 33

Message: database write operation wrote too few bytes



Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) encountered an error while writing a volume database record, where the record was only partially written.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmd` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Examine the available file system space for writing to the database
`/usr/opensv/volmgr/database/volDB` (UNIX) or
`install_path\volmgr\database\volDB` (Windows).

Media Manager Status Code: 34

Message: media ID not unique in database

Explanation: A volume entry being added to or changed in the volume database had a media ID (or optical partner ID) specified which was a duplicate of the media ID for another volume already in the volume database. All volumes in a volume database must have a unique media ID.

Recommended Action:

1. Examine the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmd` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. When adding volumes to the volume database, specify a media ID that is unique.

Media Manager Status Code: 35

Message: volume does not exist in database



Explanation: A requested operation encountered a case where a volume query did not return a volume entry matching the search criteria.

Recommended Action:

1. Examine the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmc` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that volumes are properly configured on the volume database host that matches the volume database host configured for the robot or set of standalone drives. Use `tpconfig -d` and `tpconfig -lsavdbhost` to list the configured volume database hosts. Select the current server (the one you are administering) to be the same as the host which is the correct volume database host for a targeted device.
3. Update the volume or device configurations, specify the correct volume database host, modify volume properties, or adjust search criteria as needed so that the volume query can find a matching volume.

Media Manager Status Code: 36

Message: barcode not unique in database

Explanation: A volume entry being added to or changed in the volume database had a barcode specified which was a duplicate of the barcode for another volume already in the volume database. All volumes in a volume database must have a unique barcode.

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmc` with the verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Query for or sort volume records by barcode to identify the existing volume entry with the same barcode as that specified for the volume entry being added or changed.

Media Manager Status Code: 37

Message: robotic volume position is already in use

Explanation: A volume entry being added to or changed in the volume database had a robotic coordinate (slot number, or slot number and platter side) which was a duplicate of the robotic coordinate for another volume already in the volume database. All volumes in a volume database must have unique robotic coordinates.

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmd` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Query for or sort volume records by slot number to identify the existing volume entry with the same robotic coordinate as that specified on the volume entry being added or changed (if using optical disk, display the optical platter side).
3. Change (update or move volume) or delete the existing volume entry if it does not reflect the correct robotic coordinate corresponding to the volume's storage position in the robotic library. If a volume is currently in a drive, the volume database should still reflect the volume's home slot.

Media Manager Status Code: 39

Message: network protocol error

Explanation: An attempt to read data from a socket failed.

Recommended Action:



1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the protocol error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmc` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that the server being connected to is operational.

Media Manager Status Code: 40

Message: unexpected data received

Explanation: Message communications (handshaking) was not correct.

Recommended Action:

1. Verify that the correct version of software is running on all servers.
2. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmc` with the verbose option, if available.
3. Retry the operation and examine the logs.
4. Ensure that there are no embedded whitespaces in fields that do not allow embedded whitespace.

Media Manager Status Code: 41

Message: invalid media ID for naming mode

Explanation: A request to add multiple volumes with a first media ID and a media ID style failed because the media ID specified was not compatible with the media ID naming style provided.

Recommended Action: Provide a first media ID that fits the selected style. For example, if the media ID style is two characters and four digits, the least significant four characters in the first media ID must be digits in the range 0 to 9. Alternatively, select a media ID style that fits the specified first media ID.



Media Manager Status Code: 42

Message: cannot connect to robotic software daemon

Explanation: A connection to a robotic software daemon/process could not be established. This can occur when a process tries to connect to the robotic process that is not running. It can also occur if the network or server is heavily loaded and has slow response time.

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmc` with the verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the robotic process by looking at the robot type, and at the robot host on the robotic request or the robot host field of the volume being operated on.
3. Verify that the robotic process used for robotic control is available (see table “Media Manager Daemons and Programs” on page 459), and start the robotic process if necessary.
4. Ensure that there is only one configured robot control host for each LMF, TL8, TLD, and TLH robot and that all volumes in the volume configuration have a robot host that matches the configured robot control host.
5. Change the volumes or reconfigure the robot in the device configuration as needed.
6. Check the system log on the robot control host to see if the robotic process is processing requests during the time when connections to it are attempted.

Media Manager Status Code: 43

Message: failed sending to robotic software daemon

Explanation: An attempt to write data to a robotic software daemon/process socket failed.

Recommended Action:



1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the robotic process by looking at the robot type, and at the robot host on the robotic request or the robot host field of the volume being operated on. Verify that the robotic process used for robotic control is available and handling requests (see table "Media Manager Daemons and Programs" on page 459).
3. Identify the robot control host by checking the device configuration. There should be only one configured robot control host for each LMF, TL8, TLD, and TLH robot and all volumes in the volume configuration should have a robot host that matches the configured robot control host.
4. Check the system log on the robot control host to see if the robotic process is processing requests during the time when communications with it are attempted. Perform "Resolving Network Communication Problems" on page 21.

Media Manager Status Code: 44

Message: failed receiving from robotic software daemon

Explanation: An attempt to read data from a robotic software daemon/process socket failed.

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Identify the targeted robotic process by looking at the robot type, and at the robot host on the robotic request or the robot host field of the volume being operated on. Verify that the robotic process used for robotic control is available and handling requests (see table “Media Manager Daemons and Programs” on page 459).
3. Identify the robot control host by checking the device configuration. There should be only one configured robot control host for each LMF, TL8, TLD, and TLH robot and all volumes in the volume configuration should have a robot host that matches the configured robot control host.
4. Check the system log on the robot control host to see if the robotic process is processing requests during the time when communications with it are attempted. Perform “Resolving Network Communication Problems” on page 21.

Media Manager Status Code: 45

Message: failed changing terminal characteristics

Explanation: A system call failed when an attempt was made to change the mode for terminal input between cooked and raw.

Recommended Action: Examine the user interface output for the system error associated with the failed system call and troubleshoot according to operating system vendor recommendations.

Media Manager Status Code: 46

Message: unexpected data from robotic software daemon

Explanation: Message communications (handshaking) between a process and a robotic software daemon/process failed.

Recommended Action:

1. Verify that the correct version of software is running on all servers.
2. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or by executing the command's verbose option, if available.
3. Retry the operation and examine the logs.
4. Ensure that there are no embedded whitespaces in fields that do not allow embedded whitespace.



5. Check the system log on the robot control host for errors logged by the robotic software.

Media Manager Status Code: 47

Message: no entries changed

Explanation: A requested operation was completed, but no changes to the volume configuration or Media Manager configuration file were made. The administrator may have aborted an operation instead of continuing with proposed changes, or the configuration file may have already included the configuration entry that was being added.

Recommended Action:

1. No action is needed if the administrator aborted the change operation.
2. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.

Media Manager Status Code: 48

Message: no entries deleted

Explanation: A delete volume(s) operation completed, but no changes were made to the volume configuration.

Recommended Action:

1. No action is needed, unless volumes that were requested to be deleted were not in fact deleted.
2. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.



- a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
- b. Retry the operation and examine the logs.

Media Manager Status Code: 49

Message: no entries inserted

Explanation: An insert volume(s) operation completed, but no volumes were added to the volume configuration.

Recommended Action:

1. No action is needed unless volumes that were requested to be inserted were not actually inserted.
2. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.

Media Manager Status Code: 50

Message: invalid change-entry request

Explanation: A request to change volume information was sent to vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows), but an older version of vmd is installed on the volume database host which does not support the type of change operation requested.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the usage statement for expected usage and compare with the parameters being sent to start the new process.
3. Ensure that change volume requests from a newer release version level are not sent to `vmd` on an older, incompatible version level.

Media Manager Status Code: 51

Message: cannot auto-eject this robot type

Explanation: A request to change volume residence with media eject was sent to `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows), but the volume's robot type does not support automated media eject.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that change volume residence requests (with eject for the robot type involved with a newer release version level) are not sent to `vmd` on a system running an older, incompatible software version level.

Media Manager Status Code: 52

Message: cannot auto-inject this robot type



Explanation: A request to change volume residence with media inject was sent to `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows), but the volume's robot type does not support automated media inject.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that change volume residence requests (with inject for the robot type involved with a newer release version level) are not sent to `vmd` on a system running an older, incompatible software version level.

Media Manager Status Code: 53

Message: invalid volume move mode

Explanation: A robotic-related request was made specifying a media movement option that is not supported by all affected software components.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the robotic request is sent to a system running a release version of software that supports the particular request.

Media Manager Status Code: 54

Message: robot number and robot type mismatch



Explanation: A request was made to add or change volumes in the volume configuration. The robot number to be associated with a volume is already in use, and is associated with another volume in a robot with the same number but of another robot type.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that robot numbers are unique for each physical robot in all device configurations using the same volume database host. Delete and re-add a robot using a unique robot number if duplicate robot numbers are in use, or specify a different volume database host for one of the duplicate robot numbers. Use a media management interface to identify robot numbers currently in use for all volumes in the volume configuration. If using a command line interface, specify the correct robot type for the robot number associated with the request.

Media Manager Status Code: 55

Message: robot number and volume group mismatch

Explanation: A request was made to add or change volumes in the volume configuration, and the robot number and volume group associated with the volume configuration changes are in conflict with the requirements for volume groups. All volumes in a volume group are required to have the same residence, which includes having the same robot number.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Ensure that the specified robot number and volume group are compatible. If volumes in the volume group have a given robot number (for example, 0), then volumes with a different robot number (for example, 1) cannot be added to that volume group. Volumes cannot be moved directly from one robotic volume group to another robotic volume group since the intermediate steps (some volume entries changed, some not) would cause a conflict with robot numbers. Choose a different volume group on the request, or let the volume group be automatically selected. Volume group selection depends on the specific interface being used.

Media Manager Status Code: 56

Message: invalid database version header

Explanation: `vmdb` could not find a recognizable volume database version in the volume database, and cannot initialize with the database currently in place. (`vmdb` is the Media Manager volume daemon on UNIX and the NetBackup Volume Manager service on Windows.)

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon, or start `vmdb` with the `verbose` option.
 - b. Retry the operation and examine the logs.
2. From catalog backups or another source if available, restore an earlier version of the database file, `/usr/opensv/volmgr/database/volDB` (UNIX) or `install_path\Volmgr\database\volDB` (Windows), and restart `vmdb`.

Media Manager Status Code: 57

Message: error auto-generating volume group

Explanation: A request was made to add or change volumes in the volume configuration using automatic generation of the volume group name. A unique volume group name could not be generated because the available combinations were used up.

Recommended Action: Consolidate volumes into volume groups within the targeted robot number so that a new volume group can be automatically generated, or provide a specific volume group name.

Media Manager Status Code: 58

Message: daemon cannot obtain socket

Explanation: vmd could not bind to its socket. (vmd is the Media Manager volume daemon on UNIX and the NetBackup Volume Manager service on Windows.) A system call failed when vmd attempted to bind to its configured port number. This is usually caused by another process having acquired the port before the vmd daemon or service started.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. If another process has the port, use other system commands to determine the process. Based on the result, either change the port number in your services file or map, or terminate the process that has acquired the port.
3. UNIX only: Another possible cause for this error is terminating vmd with the kill command. If you have to stop vmd, the recommended method is to use the Terminate Media Manager Volume Daemon option on the Special menu in vmadm (or the equivalent command line request, vmctrldbm -t). Using the kill command to stop this process can leave it unable to bind to its assigned port the next time it is restarted. When the socket problem has occurred, the daemon debug log contains lines similar to the following:

```
unable to obtain bound socket, Address already in use (125)
```

Media Manager Status Code: 59

Message: daemon failed accepting connection

Explanation: vmd could not accept a new connection due to a system call failure. (vmd is the Media Manager volume daemon on UNIX and the NetBackup Volume Manager service on Windows.)

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Obtain the specific system call failure from the debug log, and investigate operating system functionality related to the failure.

Media Manager Status Code: 60

Message: cannot perform operation on this host

Explanation: A requested operation is not functional on a particular host.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Device discovery must be invoked only on specific platforms where it is supported. Robot inventory update, with optical media formatting specified, must be invoked only on the host where the robotic control and optical drives are configured.

Media Manager Status Code: 61

Message: robot number and robot host mismatch

Explanation: A request was made to add or change volumes in the volume configuration, or to issue a robot inventory update request. A robot host was specified that differed from the robot host for other volumes in the same robot (defined as those volumes having the same robot number). All volumes in the volume database that have a given robot number (for instance, 0) must have the same robot host name.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify the robot host in the device configuration to be the same case-sensitive host name on all hosts where the robot is configured. Re-issue the request. As an alternative, use move by volume group to logically move all volumes from a robotic volume group to standalone and then back into the robot. Specify the robot host as the host name used in the robot configuration. Then re-issue the request.

Media Manager Status Code: 62

Message: failed redirecting input to pipe

Explanation: A system pipe could not be created.

Recommended Action: Check the interface output for the specific system error and investigate operating system functionality related to the failure.

Media Manager Status Code: 63

Message: child process killed by signal

Explanation: A robot inventory update process was terminated by an unexpected signal.

Recommended Action:

1. Examine interface output and debug logs for a more detailed message error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs. Ensure that the process is allowed to complete.

Media Manager Status Code: 64

Message: no child process to wait for



Explanation: A media management interface attempted to wait for a child process to complete, but unexpectedly found that there was no such child process to wait for.

Recommended Action:

Examine interface output and debug logs for a more detailed message error.

1. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
2. Retry the operation (or try using a different media management interface) and examine the logs.

Media Manager Status Code: 65

Message: volume group does not exist

Explanation: While processing a request, a volume group could not be found within the existing volume entries in the volume database.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Check for data integrity or consistency problems in the volume database by using a media management interface or `vmdb_dump`. Delete or move volume entries so that the volume group issues are corrected.

Media Manager Status Code: 66

Message: no cleaning tape available

Explanation: The volume database was queried for cleaning tapes by robot number. No cleaning tape in the specified robot with available cleanings remaining was found in the volume database.

Recommended Action:



Either add cleaning tapes to the robot (physically, and logically in the volume database with a media management interface), or change the number of allowed cleanings if a cleaning tape is already configured and the cleaning tape is to be used beyond its allocated use cycles. Then reissue the cleaning request, or wait for the cleaning request to be automatically submitted when a drive in the robot once again needs cleaning.

Media Manager Status Code: 67

Message: unable to send exit status

Explanation: vmd could not send the status of a requested operation to the requestor. (vmd is the Media Manager volume daemon on UNIX and the NetBackup Volume Manager service on Windows.)

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Obtain the specific send or write system call failure from the debug log, and investigate operating system functionality related to the failure.
3. Check to see whether the command or application interface sending the request is aborting prematurely, as follows: enable reqlib debug logs, retry the operation, check the debug logs, and observe application interface output.

Media Manager Status Code: 68

Message: too many volumes in volume group

Explanation: A request was made to add or change volumes in the volume configuration, and the limit for the allowed number of volumes in a volume group was reached. The limit for the number of volumes in a volume group is based on the number of volumes allowed in a particular type of robot.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check to see if volumes are defined in the volume database associated with a slot number zero that may not exist in the robot. Run a robot inventory Show contents of robot report and observe the starting slot number. If the starting slot number is one (1) and there is a volume defined in the robot at slot zero (0), delete the volume entry or move it to standalone so that the remaining available media slots can be utilized.

Media Manager Status Code: 69

Message: failed sending request to vmd

Explanation: A request could not be sent to `vmd` or to `opr`, even though the initial connection to the server process was successful. (`vmd` is the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows, and `opr` is the operator request daemon/process.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check to see whether the `vmd` or `opr` process continued to run once it received the connection from the requestor. Run `netstat -a` or an equivalent socket diagnostic utility. Look at the daemon debug log on the server-side system and the process status of `vmd/opr` to see if the server process is hung up.

Media Manager Status Code: 70

Message: cannot connect to vmd [on host *host name*]



Explanation: A process timed out while connecting to `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) or to `opr`d (the operator request daemon/process). This problem can occur when a connection is attempted and the server process is not running. It can also occur if the network or server is heavily loaded and has slow response time.

Recommended Action:

1. On the host (Media Manager host, Device Host, or volume database host) where `vmd` is the recipient of the connection, verify that the daemon/service is running. If the daemon/service is not running, start it. On Windows, `vmd` is the NetBackup Volume Manager service.
2. If `vmd` is already running, examine command output, debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
3. Verify that the correct host names are defined in the configuration. Each robot definition contains a volume database host where volumes are configured for use in the robot. Each group of servers shares a common global device database host, which `vmd` manages.
4. Check the services file. On UNIX, verify that the `/etc/services` file (and NIS services if NIS is used) has entries for the `vmd` service. (Note that `opr`d is always started by the `vmd` service.) On Windows, verify that the `%systemroot%\system32\drivers\etc\services` file has the correct entry for `vmd`. Also verify that the `vmd` port number in the services file agrees with the port number configuration, which is noted in the man page for `vmd(1M)`.
5. Verify that all operating system patches or service packs are installed.
6. Ensure that the Media Manager configuration is not tuned so that the load on `vmd` exceeds its ability to service requests. Look for entries in the Media Manager configuration file, `vm.conf`, that increase the load. Consider placing the volume database on a higher performance server and file system if performance is an issue. Consider using inventory filtering for robot types that support it, to reduce the number of volumes in the volume configuration.



7. By checking utilities such as `ipcs -a`, ensure that shared memory is functioning properly. The `opr` process may not be responding, because it is having trouble attaching to shared memory.

Media Manager Status Code: 71

Message: failed sending to vmd

Explanation: An attempt to write data to a vmd socket failed. vmd is the Media Manager volume daemon (UNIX) or NetBackup Volume Manager service (Windows).

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the system where vmd is running. This is usually termed the Media Manager host or volume database host, and defaults to the local system in some user interfaces (such as `vmadm`). Possible causes for the error are high network load, missing operating system patches or service packs, or unexpected vmd process failure.

Media Manager Status Code: 72

Message: failed receiving from vmd

Explanation: An attempt to read data from a vmd socket failed. vmd is the Media Manager volume daemon (UNIX) or NetBackup Volume Manager service (Windows).

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Identify the system where vmd is running. This is usually termed the Media Manager host or volume database host, and defaults to the local system in some user interfaces (such as vmadm). Possible causes for the error are high network load, missing operating system patches or service packs, or unexpected vmd process failure. Also, the socket read may have failed because the requested operation did not complete within a specified time period. Some requests to vmd can be affected by robotic process and vmd interactions, so check the system log for errors on the robotic control host.

Media Manager Status Code: 73

Message: invalid query type

Explanation: An invalid volume query request was attempted.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that all Media Manager and user interface binaries are at a compatible version level.

Media Manager Status Code: 74

Message: invalid number of cleanings

Explanation: A request was made to change the number of cleanings remaining for one or more volumes in the volume configuration, and the value specified was not within the acceptable range. The number of cleanings value may also be invalid in the number of mounts/cleanings field of a barcode rule.



Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a number of cleanings value within the acceptable range of 0 to 2,147,483,647.

Media Manager Status Code: 75

Message: invalid change type

Explanation: An invalid volume change request was attempted.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that all Media Manager and user interface binaries are at a compatible version level.

Media Manager Status Code: 76

Message: cannot get host name

Explanation: The system call `gethostname(3C)` failed during an attempt to obtain the name of the local host.



Recommended Action:

1. Examine the command input, debug logs, and system logs for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon, or start `vmd` with the verbose option
 - a. Retry the operation and examine the logs.
2. Obtain the specific system call failure from the debug log, and investigate operating system functionality related to the failure. Execute the `hostname` system command to see if the command is operating correctly.

Media Manager Status Code: 77**Message:** failed during `tpformat`**Explanation:** A request was made to format an optical platter, and the request failed or was aborted by the administrator.

- ◆ The optical volume format may have failed because a WORM (write-once, read many) platter cannot be reformatted.
- ◆ If the overwrite label option was not specified and the format operation is not interactive, the format optical operation will fail if the platter has already been formatted.
- ◆ If the administrator chooses to abort the format operation after it has been found that the platter has already been formatted, the format request will return with this status code.
- ◆ The format operation may have failed due to a device or media problem.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the format error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. For any of the cases listed under Explanation, choose a format operation appropriate for the current state of the platter and retry the format as needed using the `tpformat` command.

Media Manager Status Code: 78

Message: barcode does not exist in database

Explanation: A query volume by barcode request did not return a volume entry having the specified barcode, or barcode and media type.

Recommended Action:

1. Examine the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Ensure that volumes are properly configured on the volume database host that matches the volume database host configured for the robot or set of standalone drives. Use `tpconfig -d` and `tpconfig -lsavdbhost` to list the configured volume database hosts. Select the current server (the one you are administering) to be the same as the host which is the correct volume database host for a targeted device. Update the volume or device configurations, target the correct volume database host, modify volume properties, or adjust search criteria as needed so that the volume query can find a matching volume. For media in their correct slot locations, execute the Rescan/update barcode request so that the barcode field in the volume configuration matches the actual barcode as interpreted by the robotic library barcode reader.

Media Manager Status Code: 79

Message: specified robot is unknown to vmd

Explanation: A request was made to query volumes by residence, and no volumes were found in the targeted volume configuration that matched the provided robot number, robot type, and robot host.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that volumes are properly configured on the volume database host that matches the volume database host configured for the robot or set of standalone drives. Use `tpconfig -d` and `tpconfig -lsavdbhost` to list the configured volume database hosts. Select the current server (the one you are administering) to be the same as the host which is the correct volume database host for a targeted device. Update the volume or device configurations, target the correct volume database host, modify volume properties, or adjust search criteria as needed so that the volume residence query can find a matching volume.

Media Manager Status Code: 81

Message: robot type and volume group mismatch

Explanation: A request was made to add volumes or change volume residences in the volume configuration, and the robot type and volume group associated with the volume configuration changes are in conflict with the requirements for volume groups. All volumes in a volume group are required to have the same residence, which includes having the same robot type. A requested operation may have tried to associate the special No Volume Group name "---" with a robotic residence.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the specified robot residence and volume group are compatible with other volumes in the volume configuration that are in the specified volume group. Do not try to move volumes in the special No Volume Group name "----" to a robotic



residence without moving them to a new or auto-generated volume group. Choose a different volume group on the request, or let the volume group be automatically selected. Volume group selection depends on the specific interface being used.

Media Manager Status Code: 82

Message: robot host and volume group mismatch

Explanation: A request was made to add volumes or change volume residences in the volume configuration, and the robot host and volume group associated with the volume configuration changes are in conflict with the requirements for volume groups. All volumes in a volume group are required to have the same residence, which includes having the same robot host, where robot host equivalence is defined as having the same case-sensitive robot host string.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the specified robot residence and volume group are compatible with other volumes in the volume configuration that are in the specified volume group. Do not try to add volumes for a robot host using a different form of the robot host name. For example, "acme" is not the same as "acme.veritas.com." Use the same host name as that used for other volumes in the volume group. If the robot host needs to be changed for volumes in a volume group, use a single move volume group request (available only in certain media management interfaces) to move the volume group to standalone residence. Then move the volume group back to the robotic residence, specifying the desired robot control host that will be associated with the new volume group.

Media Manager Status Code: 84

Message: this machine is not the volume database host

Explanation: A request was made to initiate vmd on a host other than the local host. vmd is the Media Manager volume daemon (UNIX) or NetBackup Volume Manager service (Windows).



vmd port numbers other than the default, or use of unsupported options, can affect which host and port is referenced in interfaces used to start vmd.

Recommended Action:

1. Initiate vmd on the local host only, by logging on to the host where vmd needs to be running and starting vmd on that host. On UNIX, execute `/usr/opensv/volmgr/bin/vmd [-v]`. On Windows NT, start the NetBackup Volume Manager service in Services of the system Control Panel. (On Windows 2000, Services is in Administrative Tools of the Control Panel.)
2. If more information is needed to explain the problem, examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
3. Make sure port numbers are consistent.

Media Manager Status Code: 85

Message: volume daemon fork failed

Explanation: A Media Manager daemon or service could not create a child process due to an error received from the system. This is probably an intermittent error based on the availability of resources on the system.

Recommended Action:

1. Restart the service at a later time and investigate system problems that limit the number of processes.
2. Examine debug and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



Media Manager Status Code: 86

Message: failed opening tmp output file

Explanation: The Media Manager configuration file (vm.conf) or temporary working file could not be opened.

Recommended Action: On UNIX: check for the existence and permissions of the /usr/opensv/volmgr/misc directory, /tmp directory, and /usr/opensv/volmgr/vm.conf file. On Windows: check for the existence and security properties of the *install_path*\Volmgr\vm.conf file.

Media Manager Status Code: 87

Message: failed redirecting tmp output file

Explanation: The system call dup2 (3C) failed during an attempt to direct interface output from a temporary file to the process's standard output.

Recommended Action: Investigate operating system functionality related to resource limits on the number of open files. Ensure that processes are not being interrupted by extraneous signals.

Media Manager Status Code: 88

Message: failed initiating child process

Explanation: A command could not be executed. This can occur because the permissions of the command do not allow it to be executed, or because system resources, such as memory and swap space, are insufficient.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the permissions on the vmcheckxxx, vmupdate, and oprd binaries, and (on Windows only) the rdevmi installed binary.



Media Manager Status Code: 89

Message: another daemon already exists

Explanation: vmd (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) was initializing and found that it was already running, according to the daemon/service lock file.

Recommended Action: Check to see if vmd is already running. Do not try to start another vmd daemon/service unless the running daemon/service is first shut down. Stop the running vmd with `vmctrldbm -t`, or on Windows by using the system Services interface. If the daemon/service was unexpectedly terminated, remove the lock file, which is `/usr/openv/volmgr/misc/vmd.lock` (UNIX) or `install_path\Volmgr\misc\vmd.lock` (Windows), and try restarting vmd.

Media Manager Status Code: 90

Message: invalid volume pool

Explanation: A request was made to add volumes, change the volume pool for a volume, add a barcode rule, or change a barcode rule. However, the volume pool name or number associated with the requested change is in conflict with the requirements for volume pools. These requirements are:

- ◆ Volumes in scratch pools cannot be assigned until they are first moved to another pool.
- ◆ Volume pool numbers cannot be negative.
- ◆ Volume pool names must consist of from 1 to 20 printable ASCII characters with no embedded whitespace.
- ◆ The None volume pool is the only valid pool for barcode rule entries that specify cleaning a media type.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Ensure that the volume pool specified does not violate the requirements noted. Use the `vmppool` command to display the pool information. Use the `vmrule` command to display the barcode rule information. Add or change volume pools and barcode rules as needed to rectify inconsistencies in cases where the databases are inconsistent or corrupted.

Media Manager Status Code: 91

Message: cannot change volume pool for assigned volume

Explanation: A request was made to change the volume pool for a volume, and the volume is currently assigned. For optical volumes, the volume pool cannot be changed unless both sides of the optical platter are unassigned.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. It is not possible to change the volume pool for assigned volumes. If no worthwhile data is on the volume, unassign the media using the appropriate application interface (which is `bpexptime` for NetBackup) and then retry the change pool request. For optical media, if no worthwhile data is on either side of the platter, unassign both of the volumes before the change pool request is retried.

Media Manager Status Code: 92

Message: cannot delete assigned volume

Explanation: A delete request was made to a volume, and the volume is currently assigned. Optical volumes cannot be deleted unless both sides of the optical platter are unassigned.

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. It is not possible to delete assigned volumes. If no worthwhile data is on the volume, unassign the media using the appropriate application interface (which is `bpexpdate` for NetBackup) and then retry the delete volume request. For optical media, if no worthwhile data is on either side of the platter, unassign both of the volumes before attempting to delete them.

Media Manager Status Code: 93

Message: volume is already assigned

Explanation: A request was made to assign a volume, and the volume was already assigned, or for optical media, the volume partner was already assigned.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Do not try to manually assign volumes that are already assigned, because it is not valid except for one condition: you can assign volumes for NetBackup catalog backups if the volume is already assigned for NetBackup catalog backups. Check the device configuration to determine if the volume database host for the device is consistent with the volume configuration in the volume database. Applications may attempt to query multiple volume databases for volume-related requests, so ensure that duplicate media IDs are not used in volume configurations across multiple hosts. If duplicate IDs are found, either completely separate the configurations by not sharing any devices, or remove volumes with duplicate media IDs and consolidate volumes into one volume configuration. Always use barcodes that are unique with



respect to the six (6) least significant characters across all media in all robots, or use media ID generation rules to ensure unique media IDs are generated when using robot inventory update.

Media Manager Status Code: 94

Message: volume is not in specified pool

Explanation: A request was made to assign a volume from a specified volume pool. The volume was either found to be in a different volume pool, or, for optical media, the volume partner was in a different volume pool.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. When assigning volumes manually, specify the volume pool associated with the volume. Check the device configuration to determine if the volume database host for the device is consistent with the volume configuration in the volume database. Applications may attempt to query multiple volume databases for volume-related requests, so ensure that duplicate media IDs are not used in volume configurations across multiple hosts. If duplicate IDs are found, either completely separate the configurations by not sharing any devices, or remove volumes with duplicate media IDs and consolidate volumes into one volume configuration. Always use barcodes that are unique with respect to the six (6) least significant characters across all media in all robots, or use media ID generation rules to ensure unique media IDs are generated when using robot inventory update.

Media Manager Status Code: 95

Message: media ID is not the specified media type

Explanation: A request was made to assign or add a volume of a specified media type, but the volume or other physically similar volumes have a different media type.

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. When using robot inventory update to make changes to the volume configuration, ensure that all volumes of the same physical cartridge type (for example, 3590J in TLH robots) are mapped to a single media type, such as HCART. This ensures that all media in the robotic library can be mounted on drives with a compatible drive type.
3. When assigning volumes manually, specify the media type associated with the volume. Check the device configuration to determine if the volume database host for the device is consistent with the volume configuration in the volume database. Applications may attempt to query multiple volume databases for volume-related requests, so ensure that duplicate media IDs are not used in volume configurations across multiple hosts. If duplicate IDs are found, either completely separate the configurations by not sharing any devices, or remove volumes with duplicate media IDs and consolidate volumes into one volume configuration. Always use barcodes that are unique with respect to the six (6) least significant characters across all media in all robots, or use media ID generation rules to ensure unique media IDs are generated when using robot inventory update.

Media Manager Status Code: 96

Message: oprd returned abnormal status

Explanation: A request serviced by `oprd` (the operator request daemon/process) or by `rdevmi` (the remote device management interface) returned an abnormal status.

Recommended Action:

1. On Windows, when auto-configuring devices or initiating the NetBackup Device Manager service from a graphical or command line interface, ensure that the service has not been disabled in the system services configuration.



2. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
3. Operator request daemon/process and remote device management errors are generally accompanied by device management-related errors that have occurred on a particular host. Check for errors in the debug and system/application logs on the host where `oprdr` or `rdevmi` was started or running, which is often a targeted device host or scan host. The kinds of requests serviced by `oprdr/rdevmi` that may have failed include: down/up/reset drives, change drive comments, deny/resubmit mount requests, assign drives, start/stop ltid, obtain ltid status, display drive status, manage pending actions, set NDMP attributes, configure devices, format optical platters, clean drives, obtain host version and device configuration information, and scan shared drives.

Media Manager Status Code: 97

Message: rule does not exist in rule database

Explanation: A request was made to change or delete a barcode rule, and no barcode rule having the specified barcode tag could be found.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. List the configured barcode rules on the targeted volume database host. Adjust the barcode tag specified on the change/delete request or the targeted host as appropriate so that the barcode rule is found when the request is retried.



Media Manager Status Code: 98

Message: rule database truncate operation failed

Explanation: The system call `ftruncate(3C)` failed during an attempt to rewrite the barcode rule database during a barcode rule change/delete operation.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Investigate the integrity of the file system and barcode rule database: on UNIX, `/usr/openv/volmgr/database/ruleDB`; on Windows, `install_path\Volmgr\database\ruleDB`.

Media Manager Status Code: 99

Message: user is not valid for this host

Explanation: A request was made to add or change a volume pool, and the specified UNIX user ID could not be found on the system that originated the request.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On the UNIX host where the request originated, check the system user configuration and ensure that add/change pool requests include only valid user IDs. No validation is attempted for user IDs in volume pools on Windows.



Media Manager Status Code: 100

Message: the requested slot is empty

Explanation: A request was made to validate/update the barcode for a volume, and information from the robot indicated that there was no volume in the robot that used the requested slot for its home location.

Recommended Action:

The volume configuration is not consistent with the physical contents of the robotic library that is associated with the volume. The volume configuration or media placement in the robotic library needs to be adjusted using one of the media management interfaces.

Update/validate barcode requests are made for each volume affected whenever a volume configuration is added or changed. Volume entries are still changed when the update/validate step fails, so administrative steps are required to ensure that volume entries are defined only for media slots in the library where the correct media resides. For media located in drives at the time the update/validate barcode is tried, the robotic information will relate the media with its known home slot location.

Media Manager Status Code: 101

Message: media type and volume group mismatch

Explanation: A request was made to add volumes or change volume residences in the volume configuration, and the media type and volume group associated with the volume configuration changes are in conflict with the requirements for volume groups. All volumes in a volume group are required to have the same residence, which includes having the same media type. Media types used for data and their associated cleaning media types are considered as being the same media types with regard to volume group restrictions.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Ensure that the specified media type and volume group are compatible with other volumes in the volume configuration that are in the specified volume group. Choose a different volume group on the request, or let the volume group be automatically selected. Volume group selection depends on the interface being used.

Media Manager Status Code: 102

Message: invalid pool database entry

Explanation: The volume pool database is corrupt, in that it contains records that are not compatible with the installed product binaries.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or by executing the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Use `vmppool` to investigate the integrity of the volume pool database. The daemon debug log file should indicate the number of fields expected and the number of fields found in the pool record. Restore a saved version of the pool database if the pool database cannot be manually corrected.

Media Manager Status Code: 103

Message: all available pool numbers are in use

Explanation: A request was made to add a volume pool in the volume pool configuration, but no unique pool numbers could be generated because the available pool numbers were used up.

Recommended Action: Consolidate volume pools so that a new pool number becomes available.

Media Manager Status Code: 104

Message: failed appending to pool database

Explanation: A request was made to add, change, or delete a volume pool in the volume pool configuration, but a pool record could not be appended to the volume pool database file.



Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and available file system space for writing to the database: on UNIX, /usr/openv/volmgr/database/poolDB; on Windows, install_path\Volmgr\database\poolDB.

Media Manager Status Code: 105

Message: poolname is not unique in pool database

Explanation: A request was made to add a volume pool in the volume pool configuration, but the pool name specified was a duplicate of the name for an existing volume pool.

Recommended Action: On the add volume pool request, specify a volume pool name that is not already in use on the targeted volume database host.

Media Manager Status Code: 106

Message: pool database lock operation failed

Explanation: vmd (the Media Manager volume daemon on UNIX) encountered a system call error while attempting to lock the volume pool database.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Use the vmops command to ensure that vmd and vmdb_dump are not both running at the same time.

3. Ensure that no other process has a lock on the volume pool database file, `/usr/opensv/volmgr/database/poolDB`.

Media Manager Status Code: 107

Message: pool database close operation failed

Explanation: An error occurred when vmd attempted to close the volume pool database.

Recommended Action:

Examine the daemon debug log for a more detailed message on the system error.

- a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
- b. Retry the operation and examine the logs.

Media Manager Status Code: 108

Message: pool database open operation failed

Explanation: A requested operation was unable to open the volume pool database file.

Recommended Action: Check for the existence and permissions of the `poolDB` file in the following: on UNIX, `/usr/opensv/volmgr/database` directory; on Windows, `install_path\volmgr\database` folder. Restore the `poolDB` file from the catalog backups or from another location, change the access permissions on the existing `poolDB`, or move/rename the current `poolDB` so that vmd can initialize a default pool configuration. If the move/rename method is used, modify the volume and other application configurations so that no references are made to volume pools that no longer exist.

Media Manager Status Code: 109

Message: pool does not exist in pool database

Explanation: A requested operation encountered a case where the specified volume pool was not found in the volume pool configuration on the targeted volume database host. The requests potentially returning this error code are: add/change/delete/query volume pool, add/change barcode rule, add/change volume, query scratch volumes, and robot inventory report or update.

Recommended Action:



1. Examine the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Ensure that volumes are properly configured on the volume database host that matches the volume database host configured for the robot or set of standalone drives. Use the `tpconfig -d` and `tpconfig -lsavdbhost` commands to list the configured volume database hosts. Select the current server (the one you are administering) to be the same as the host which is the correct volume database host for a targeted device.
3. Update the volume or device configurations, specify the correct volume database host, modify volume properties, or adjust search criteria as needed so that the requested operation can find the requested volume pool. Investigate inconsistencies between the volume database and the volume pool database, and restore or correct those databases from a previous state as needed.

Media Manager Status Code: 110

Message: pool database truncate operation failed

Explanation: The system call `ftruncate(3C)` failed during an attempt to rewrite the volume pool database during a volume pool add/change/delete operation.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Investigate the integrity of the file system and volume pool database, `/usr/opensv/volmgr/database/poolDB` (UNIX) or `install_path\Volmgr\database\poolDB` (Windows).

Media Manager Status Code: 111

Message: the specified pool is not empty

Explanation: On a request to delete a volume pool, it was found that the pool was not empty, or it could not be determined whether or not volumes were still associated with the specified volume pool.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Use a media management interface to query for volumes associated with the pool specified for deletion. Ensure that all volumes in a volume pool are reassociated with another pool before trying to delete the volume pool. Use change volume operations to change the volume pool for a volume. Check for possible volume database lock or seek errors (Media Manager code 29 or 30).

Media Manager Status Code: 112

Message: no pools in the pool list

Explanation: The volume pool list was unexpectedly found to be empty.

Recommended Action: The volume pool list should contain a minimum of three pools: None, NetBackup, and DataStore. Investigate the integrity of the volume pool database, `/usr/openv/volmgr/database/poolDB` (UNIX) or `install_path\Volmgr\database\poolDB` (Windows) on the host returning the error. Restore the volume database from catalog backups. As an alternative, reinitialize the volume database to include the None, NetBackup, and DataStore volume pools. To reinitialize it, remove the volume pool database and make any request to vmd, such as can be done by pointing a media management interface at the appropriate volume database host.

Media Manager Status Code: 113

Message: invalid expiration date

Explanation: A request was made to change the media expiration for one or more volumes in the volume configuration, but the date specified was not valid.



Recommended Action:

When changing the media expiration, provide the date in the format specified by the media management interface documentation.

Media Manager Status Code: 114

Message: invalid maximum mounts

Explanation: A request was made to change the limit for the number of times a volume can be mounted with write access for one or more volumes in the volume configuration, but the value specified was not within the acceptable range. The maximum number of mounts value may also be invalid in the number of mounts/cleanings field of a barcode rule.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a maximum mounts value within the range of 0 to 2,147,483,647.

Media Manager Status Code: 115

Message: volume has passed expiration date

Explanation: A request was made to assign a volume, and the volume expiration date has expired in relation to the current system date. For optical media, the volume partner expiration date has expired.

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Change the volume expiration date to a future date in relation to the current system date/time if you want to extend the active life of the physical media. Alternatively, replace the media with other media that still has useful life remaining. Check the system date/time and reset it correctly as needed.
3. If the media expiration is already set to a future date as compared to the current system date, check the device configuration to determine if the volume database host for the device is consistent with the volume configuration in the volume database. Applications may attempt to query multiple volume databases for volume-related requests, so ensure that duplicate media IDs are not used in volume configurations across multiple hosts. If duplicate IDs are found, either completely separate the configurations by not sharing any devices, or remove volumes with duplicate media IDs and consolidate volumes into one volume configuration. Always use barcodes that are unique with respect to the six (6) least significant characters across all media in all robots, or use media ID generation rules to ensure unique media IDs are generated when using robot inventory update.

Media Manager Status Code: 116

Message: volume has exceeded maximum mounts

Explanation: A request was made to assign a volume, and the volume's number of mounts has exceeded the maximum number of mounts allowed for the volume (or the maximum number allowed for the volume partner, in the case of optical media).

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Increase the volume's maximum number of mounts, or set the maximum number of mounts to infinite if you want to extend the active life of the physical media. Alternatively, replace the media with other media that still has useful life remaining.
3. If the number of mounts was less than the maximum mounts allowed for the volume, check the device configuration to determine if the volume database host for the device is consistent with the volume configuration in the volume database. Applications may attempt to query multiple volume databases for volume-related requests, so ensure that duplicate media IDs are not used in volume configurations across multiple hosts. If duplicate IDs are found, either completely separate the configurations by not sharing any devices, or remove volumes with duplicate media IDs and consolidate volumes into one volume configuration. Always use barcodes that are unique with respect to the six (6) least significant characters across all media in all robots, or use media ID generation rules to ensure unique media IDs are generated when using robot inventory update.

Media Manager Status Code: 117

Message: operation not allowed on cleaning cartridge

Explanation: A request was made to change a volume's expiration or maximum number of mounts, but the operation is not allowed because the volume is a cleaning cartridge.

Recommended Action:

1. If the volume is a cleaning cartridge, perform a valid operation such as changing the number of cleanings remaining for the cleaning cartridge.
2. If the volume's media type cannot be determined, examine command output (if available) and debug logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
3. If the targeted volume is incorrectly configured as a cleaning tape, delete the cleaning volume and update the volume configuration using options to define a new volume with the appropriate media type.

Media Manager Status Code: 118

Message: cannot delete one of the default volume pools



Explanation: An attempt was made to delete one of the special, pre-defined volume pools. The None, NetBackup, and DataStore volume pools are fixed volume pools in the volume pool configuration, and cannot be deleted.

Recommended Action: Do not attempt to delete the None, NetBackup, and DataStore volume pools.

Media Manager Status Code: 119

Message: invalid rule database entry

Explanation: The barcode rule database is corrupt: it contains records that are not compatible with the installed product binaries.

Recommended Action:

1. Examine command output and debug logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Use `vmrule` to investigate integrity of the barcode rule database. The daemon debug log file should indicate the number of fields expected and the number of fields found in the barcode rule record. Restore a saved version of the barcode rule database if the barcode rule database cannot be manually corrected.

Media Manager Status Code: 120

Message: all available rule numbers are in use

Explanation: A request was made to add a barcode rule in the barcode rule configuration. No unique rule numbers could be generated because the available rule numbers were used up.

Recommended Action: Consolidate barcode rules so that a new rule number becomes available.

Media Manager Status Code: 121

Message: failed appending to rule database

Explanation: A request was made to add, change, or delete a barcode rule, and a barcode rule record could not be appended to the barcode rule database file.



Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and available file system space for writing to the database, /usr/opensv/volmgr/database/ruleDB (UNIX) or install_path\Volmgr\database\ruleDB (Windows).

Media Manager Status Code: 122

Message: barcode tag is not unique in rule database

Explanation: A request was made to add a barcode rule, and the barcode tag specified was a duplicate of the tag for an existing barcode rule.

Recommended Action: On the add barcode rule request, specify a barcode tag that is not already in use on the specified volume database host.

Media Manager Status Code: 123

Message: rule database lock operation failed

Explanation: vmd (the Media Manager volume daemon on UNIX) encountered a system call error while attempting to lock the barcode rule database. This status code applies to UNIX servers only.

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Ensure that no other process has a lock on the barcode rule database file /usr/opensv/volmgr/database/ruleDB.



Media Manager Status Code: 124

Message: rule database close operation failed

Explanation: An error occurred when vmd attempted to close the barcode rule database.

Recommended Action: Examine the daemon debug log for a more detailed message on the system error.

1. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
2. Retry the operation and examine the logs.

Media Manager Status Code: 125

Message: rule database open operation failed

Explanation: A requested operation encountered a situation where the barcode rule database file could not be opened.

Recommended Action: Check for the existence and permissions of the ruleDB file in the /usr/opensv/volmgr/database directory on UNIX or *install_path*\Volmgr\database folder on Windows. Restore the ruleDB file from the catalog backups or from another location, change the access permissions on the existing ruleDB, or move/rename the current ruleDB so that vmd can initialize an empty barcode rule configuration. If the move/rename method is used, re-add barcode rule entries as needed so that new media moved into the robotic library are assigned to the correct media types.

Media Manager Status Code: 126

Message: not authorized to connect to vmd

Explanation: A caller requesting services from vmd is either not authenticated or not authorized, or a problem was encountered when two systems were attempting to authenticate one another.

Recommended Action:

1. See the Media Manager system administrator's guides for detailed information on vmd security. vmd security is based on NetBackup authentication/authorization, but has extensions for handling SERVER entries in the Media Manager configuration file.
2. Examine the debug log files for a more detailed message on the authentication/authorization problem.



- a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
- b. Retry the operation and examine the logs.
3. Correct the vmd security configuration by adjusting the authentication configuration, the AUTHORIZATION_REQUIRED entry, and SERVER entries.
4. If an authentication problem (rather than a configuration issue) is suspected, do the following:

- a. Ensure that the authentication libraries exist:

Windows:

```
install_path\NetBackup\lib\libvopie.dll
install_path\NetBackup\lib\libnoauth.dll
```

UNIX (except HP-UX):

```
/usr/opensv/lib/libvopie.so
/usr/opensv/lib/libnoauth.so
```

UNIX (HP-UX only):

```
/usr/opensv/lib/libvopie.sl
/usr/opensv/lib/libnoauth.sl
```

- b. Check the methods_allow.txt files on the systems that are having problems to ensure that authentication is enabled. The files are in the following locations:

Windows: *install_path*\NetBackup\var\auth

UNIX: /usr/opensv/var/auth

- c. On the systems that are having the authentication problem, remove the remote host that is not being authenticated from the methods_allow.txt file.

For example, if Host A and Host B are having the problem, remove Host A from the file on Host B, and vice versa.

Retry the operation.

- ◆ If the problem still exists, there are connection problems not related to authentication.
- ◆ If connections are now successful, proceed to the next step.

- d. Execute `bpauthsync -vopie` on the master server to resynchronize the key files on the systems.

On Windows:

```
install_path\NetBackup\bin\admincmd\bpauthsync -vopie -servers
```

On UNIX:

```
/usr/openv/netbackup/bin/admincmd/bpauthsync -vopie -servers
```

- e. Add back the names removed in step c and retry the operation.

Media Manager Status Code: 127

Message: unable to generate a unique media id

Explanation: A request was made to add volumes in the volume configuration using robot inventory update or using a media ID seed. A unique media ID was not generated because the “use seed” option was not specified, or because the available media ID combinations were used up.

Recommended Action: If using robot inventory update, ensure that all media in the robotic library have readable barcode labels, or request updates using a seed to automatically generated media IDs for non-barcode media. If volumes are being added by specifying a seed, use a seed that allows media ID character combinations beyond those already in use. To identify the slot associated with media that may not have a readable barcode, examine the command output.

Media Manager Status Code: 128

Message: group is not valid for this host

Explanation: A request was made to add or change a volume pool, and the specified UNIX group ID could not be found on the system that originated the request.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. On the UNIX host where the request originated, check the system group configuration and ensure that add/change pool requests include only valid group IDs. No validation is attempted for group IDs in volume pools on Windows.

Media Manager Status Code: 129

Message: invalid drive name

Explanation: A request was made to register, reserve, or release a shared drive with vmd/DA (the device allocator for the Shared Storage Option), and the drive name was not correctly formatted.

Recommended Action:

1. Examine the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon/NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Ensure that the drive name is from 1 to 48 ASCII characters in length. The following special characters are allowed: period (.), plus (+), minus (-), underscore (_).
3. Verify that the correct version of software is running on all servers.

Media Manager Status Code: 130

Message: requested drive is already reserved

Explanation: A request was made to reserve a shared drive with vmd/DA (the device allocator for the Shared Storage Option), and the drive was already reserved for another host.

This is a normal occurrence when drive resources are being oversubscribed for either of these reasons: independent schedulers/applications accessing the same pool of drives, or hardware or media errors causing some drives allocated to jobs to become unavailable.

Recommended Action:



1. Check the system log and application (bptm) debug log to determine if hardware or media errors have caused drives to become unavailable.
2. If more information is needed on the drive reservation problem, examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.

Media Manager Status Code: 131

Message: requested drive is not registered for host

Explanation: A request was made to reserve a shared drive with vmd/DA (the device allocator for Shared Storage Option). The drive was not registered by the requesting host, although other drives had been registered by that host.

This is an abnormal condition that could occur if two different hosts with the same host name (local host name, overridden by any SSO_HOST_NAME entries in the Media Manager configuration file `vm.conf`) have registered different drive lists with vmd/DA, and one of those hosts has requested a drive reservation.

Recommended Action: Use unique (non-duplicate) strings for host names and SSO_HOST_NAME configuration file entries.

Media Manager Status Code: 132

Message: requested drive is not currently registered

Explanation: A request was made to reserve or release a shared drive with vmd/DA (the device allocator for the Shared Storage Option). The drive was not registered by the requesting host or any other hosts.

Recommended Action: This is an abnormal condition that could occur in the following situations:

- ◆ vmd/DA was stopped and restarted. This situation will be automatically handled, because the requesting host re-registers its drives with vmd/DA when this error is encountered.

Media Manager Status Code: 133

Message: requested drive is not reserved by host



Explanation: A request was made to release a shared drive with vmd/DA (the device allocator for the Shared Storage Option). The drive was not reserved by the requesting host, although it had been reserved for another host.

This is an abnormal condition that could occur if there was a network problem or a suspended process. The following is a possible scenario:

1. Host A reserves a shared drive.
2. Host A becomes unavailable for some time, unable to communicate with other hosts.
3. Host B determines that the host having the reservation (Host A) is no longer available, and makes a request to vmd/DA denoting Host A as unavailable.
4. Some other host (such as Host A or Host C) reserves the drive.
5. The host originally owning the drive reservation tries to release the drive.

Recommended Action: Correct the network or process problem that led to the communications problem. Ensure that unique non-duplicate strings are being used for host names and for SSO_HOST_NAME configuration file entries.

Media Manager Status Code: 134

Message: requested drive is not currently reserved

Explanation: A request was made to release a shared drive with vmd/DA (the device allocator for the Shared Storage Option SSO), but the drive was not reserved by any hosts.

This is an abnormal condition that could occur if there was a network problem or a suspended process. The following is a possible scenario:

1. Host A reserves a shared drive.
2. Host A becomes unavailable for some time, unable to communicate with other hosts.
3. Host B determines that the host having the reservation (Host A) is no longer available, and makes a request to vmd/DA denoting Host A as unavailable.
4. The host originally owning the drive reservation tries to release the drive.

Recommended Action: Correct the network or process problem that led to the communications problem. Ensure that unique non-duplicate strings are being used for host names and for SSO_HOST_NAME configuration file entries.

Media Manager Status Code: 135

Message: requested host is not currently registered

Explanation: A request was made to reserve or release a shared drive or designate a host as unavailable with vmd/DA (the device allocator for the Shared Storage Option). The host reserving or releasing the drive, or being designated as unavailable, was not registered with vmd/DA.

This is an abnormal condition that could occur in the following situations.

1. vmd/DA was stopped and restarted. This situation will be automatically handled, because the requesting host re-registers its drives with vmd/DA when this error is encountered.
2. A host has been unregistered with vmd/DA, and another host was in the process of declaring the host to be unavailable.

Recommended Action: In case 2, above, determine whether the host ought to be available. Correct the underlying network problems or restart `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).

Media Manager Status Code: 136

Message: invalid host name

Explanation: A device host was being added to the Media Manager configuration, or a request was made to vmd/DA, the device allocator for the Shared Storage Option (SSO), and the host name exceeded the allowable length.

Recommended Action: Limit host names to 256 ASCII characters or less.

Media Manager Status Code: 137

Message: oprd request is not supported on the remote host

Explanation: An invalid request was sent to the operator request process.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. Identify the targeted host and verify that all Media Manager binaries on that host are at a compatible version level with other hosts that are part of the configuration. Update the software version as needed.

Media Manager Status Code: 138

Message: media generation rule already exists

Explanation: You, or a NetBackup media management interface have attempted to add a MEDIA_ID_BARCODE_CHARS rule that already exists. The same rule cannot be added twice.

Recommended Action: Re-examine the listing of the MEDIA_ID_BARCODE_CHARS rules. For a description of MEDIA_ID_BARCODE_CHARS rules, refer to “Media Manager Reference Topics” in the *NetBackup Media Manager System Administrator’s Guide*.

Media Manager Status Code: 139

Message: media generation rule does not exist

Explanation: You, or a NetBackup media management interface have attempted to delete a MEDIA_ID_BARCODE_CHARS rule that does not exist.

Recommended Action: Re-examine a listing of the MEDIA_ID_BARCODE_CHARS rules. For a description of MEDIA_ID_BARCODE_CHARS rules, refer to “Media Manager Reference Topics” in the *NetBackup Media Manager System Administrator’s Guide*.

Media Manager Status Code: 140

Message: invalid media generation rule

Explanation: You, or a NetBackup media management interface have attempted to add an incorrect MEDIA_ID_BARCODE_CHARS rule.

Recommended Action: Ensure that the MEDIA_ID_BARCODE_CHARS rule is composed correctly. For a description of MEDIA_ID_BARCODE_CHARS rules, refer to “Media Manager Reference Topics” in the *NetBackup Media Manager System Administrator’s Guide*.

Media Manager Status Code: 141

Message: invalid number of mounts

Explanation: A request was made to change the number of times that a volume has been mounted, and the value specified was not within the acceptable range.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a number of mounts value within the acceptable range of 0 to 2,147,483,647.

Media Manager Status Code: 142

Message: invalid offsite location

Explanation: The offsite location for a volume exceeds 25 ASCII characters in length, or contains unprintable characters.

Recommended Action: When adding or changing a volume record, ensure that the offsite location field contains only printable characters and does not exceed 25 ASCII characters in length.

Media Manager Status Code: 143

Message: invalid offsite sent date

Explanation: A request was made to change the offsite sent date for one or more volumes in the volume configuration, and the date specified was not valid.

Recommended Action: When changing the offsite sent date, provide the date in the format specified by the Media Management interface documentation.

Media Manager Status Code: 144

Message: invalid offsite return date

Explanation: A request was made to change the offsite return date for one or more volumes in the volume configuration, and the date specified was not valid.

Recommended Action: When changing the offsite return date, provide the date in the format specified by the Media Management interface documentation.

Media Manager Status Code: 145

Message: requested drive is already reserved by host



Explanation: A request was made to reserve a shared drive with vmd/DA (the device allocator for the Shared Storage Option). The drive was already reserved for the requesting host.

This is an abnormal condition that could occur if two different hosts with the same host name (local host name, overridden by any SSO_HOST_NAME entries in the Media Manager configuration file, vm.conf) have registered the same drive name with vmd/DA. In this case, one of those hosts has a drive reservation, and the other host is trying to reserve the same drive.

Recommended Action: Use unique non-duplicate strings for host names and for SSO_HOST_NAME configuration file entries.

Media Manager Status Code: 146

Message: incompatible database version

Explanation: An invalid or unknown database or communications protocol was encountered by a requesting process or by vmd. (vmd is the volume daemon on UNIX or NetBackup Volume Manager service on Windows.) Possible data stores affected by such an error are volume, volume pool, barcode rule, global device database, and shared drive information.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the target components (for example, vmd and daemons/services, or user interfaces on local or remote hosts). Verify that all Media Manager binaries are at a compatible version level. Depending on which requests encountered the invalid version, determine whether or not the database is corrupt. Use an appropriate interface to query for the type of information involved in the error condition.

Media Manager Status Code: 147

Message: invalid offsite slot

Explanation: A request was made to change the offsite slot location for a volume, and the value specified was not within the acceptable range.



Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify an offsite slot value within the range of 0 to 2,147,483,647.

Media Manager Status Code: 148

Message: invalid offsite session id

Explanation: A request was made to change the offsite session ID for a volume, and the value specified was not within the acceptable range.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify an offsite session ID within the range of 0 to 2,147,483,647.

Media Manager Status Code: 149

Message: current version does not support this configuration

Explanation: A request cannot be performed because it attempted to reference functionality that is not licensed. An example of this is attempting to add a volume with a media type that is not valid for the licensed product.

Recommended Action:

1. Examine command output (if available) and debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. List the license keys installed and verify that the functionality being referenced is supported with the currently installed license keys. Check to see that the databases defining externalized object types are in place and not corrupted. These database files are the following, in the /usr/opensv/share directory (UNIX) or *install_path*\NetBackup\share folder (Windows):
 - ◆ external_attributes.txt
 - ◆ external_densities.txt
 - ◆ external_drivetypes.txt
 - ◆ external_mediatypes.txt
 - ◆ external_robotics.txt

Media Manager Status Code: 151

Message: invalid global device database entry

Explanation: vmd encountered a read error while reading a global device database record, or a memory allocation error while allocating table space for global device information. vmd is the Media Manager volume daemon (UNIX) or NetBackup Volume Manager service (Windows).

Recommended Action:

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. The global device database may be corrupted. Restore an older volume database from a saved version or from catalog backups.



3. Free up memory by terminating unneeded processes that consume a lot of memory. Add more swap space or physical memory.

Media Manager Status Code: 152

Message: global device database record not found

Explanation: A request was made to update a global device database record, and the record specified was not found in the global device database. This condition could occur when a device configuration change is made after the global device database host has changed.

Recommended Action: If the request to update a global device database record fails because the record does not exist, a request is made to add the missing record to the global device database. No action is required.

Media Manager Status Code: 153

Message: device entry is not unique in global device database

Explanation: A request was made to add a global device database record, and the record specified was a duplicate of an existing record. This condition could occur if two processes are simultaneously updating the device configuration on the same host.

Recommended Action:

1. Coordinate changes to the device configuration so that changes come from a single source.
2. To investigate the details surrounding the global device database changes on the server (database) side, examine the daemon debug log file.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the request to change the device configuration and examine the debug log file.

Media Manager Status Code: 154

Message: global device database truncate operation failed

Explanation: When the user was trying to change the device configuration, the system call `ftruncate(3C)` failed during an attempt to rewrite the global device database

Recommended Action:



1. Examine command output (if available) and debug logs for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Investigate the integrity of the file system and global device database, `/usr/opensv/volmgr/database/globDB (UNIX)` or `install_path\Volmgr\database\globDB (Windows)`.

Media Manager Status Code: 155

Message: global device database append operation failed

Explanation: A request was made to change the device configuration, and a global device database record could not be written to the global device database file.

1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and available file system space for writing to the database, `/usr/opensv/volmgr/database/globDB (UNIX)` or `install_path\Volmgr\database\globDB (Windows)`.

Media Manager Status Code: 156

Message: global device database lock operation failed

Explanation: vmd, the Media Manager volume daemon (UNIX), encountered a system call error while attempting to lock the global device database.

Recommended Action:



1. Examine the daemon debug log for a more detailed message on the system error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Ensure that no other process has a lock on the global device database file
/usr/opensv/volmgr/database/globDB.

Media Manager Status Code: 157

Message: global device database open operation failed

Explanation: A requested operation encountered a situation where the global device database file could not be opened.

Recommended Action:

1. Check for the existence and permissions of the globDB file in the
/usr/opensv/volmgr/database directory or *install_path*\Volmgr\database folder.
2. Restore the globDB file from the catalog backups or from another location, change the access permissions on the existing globDB, or (as a last resort) move/rename the current globDB to start over with an empty global device configuration.
3. If the move/rename method is used, recreate all device configurations on all hosts.

Media Manager Status Code: 158

Message: global device database close operation failed

Explanation: An error occurred when vmd attempted to close the global device database.

Recommended Action: Examine the daemon debug log for a more detailed message on the system error.

1. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
2. Retry the operation and examine the logs.



Media Manager Status Code: 159

Message: the volume guid is not unique in the database

Explanation: A volume entry being added to or changed in the volume database had an RSM GUID specified which was a duplicate of the RSM GUID for another volume already in the volume database. All volumes in a volume database must have an RSM GUID that is either unique or null. (RSM is the Microsoft Removable Storage Manager, and GUID is a Global Unique Identifier.)

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Try the following procedure:
 - a. From the daemon debug log file, determine the offset of the volume that has an RSM GUID conflict with the volume entry being added or changed. The offset is the index of the volume in the volume database.
 - b. Dump out all volume records in the volume configuration for the targeted volume database host using the `vmdb_dump` command. Look up the volume offset indicated in the debug log file, noting the associated RSM GUID, which is the field `volume_guid`.

The condition may have occurred because the media name for a volume may have been changed in the RSM media configuration, followed by a change to the volume configuration in Media Manager that caused a new volume to be added. Since RSM media names are equivalent to media IDs, if the existing media ID is not deleted from the volume configuration, the conflict appears when the new volume is added. Do not change media names in RSM if volume entries have already been established for the media in the volume configuration.

Media Manager Status Code: 160

Message: the global device database device type is invalid

Explanation: An invalid device type appeared in a request to modify the device configuration.



Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the targeted host and verify that all Media Manager binaries on that host are at a compatible version level with other hosts that are part of the configuration. Update the software version as needed.

Media Manager Status Code: 161

Message: the global device database device serial number is invalid

Explanation: An invalid or missing device serial number was encountered in a request to modify the device configuration.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the targeted host and verify that all Media Manager binaries on that host are at a compatible version level with other hosts that are part of the configuration. Update the software version as needed.

Media Manager Status Code: 162

Message: the global device database device name is invalid

Explanation: An invalid or missing device name was encountered in a request to modify the device configuration.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Identify the targeted host and verify that all Media Manager binaries on that host are at a compatible version level with other hosts that are part of the configuration. Update the software version as needed.

Media Manager Status Code: 164

Message: the robotic daemon returned an invalid volume GUID

Explanation: An invalid RSM GUID was returned from the RSM robotic control process, which probably obtained it from the RSM API. (RSM is the Microsoft Removable Storage Manager, and GUID is a Global Unique Identifier.)

Recommended Action:

1. Examine the system's application log, the Removable Storage system interface, and the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If it is not already enabled, enable debug logging by creating the necessary folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the NetBackup Device Manager service.
 - b. Retry the operation and examine the logs. From the daemon debug log file, determine the media ID that has the invalid RSM GUID.
2. Make sure that the software components are compatible.

Media Manager Status Code: 165

Message: Evaluation period expired. Go to www.veritas.com to order this product.

Explanation: The NetBackup evaluation software has expired. See www.veritas.com for ordering information.

Recommended Action: Obtain a licensed copy of NetBackup, which includes Media Manager.



Media Manager Status Code: 166

Message: media access port not available

Explanation: A request was made to physically move a volume into or out of a robotic library, but the media access port was found to be unavailable.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If it is not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the physical move volume request for the robot type was not sent to a robotic control daemon/process on a system running an older, incompatible version of the software.
3. Ensure that the targeted robotic control daemon/process is operating normally.

Media Manager Status Code: 167

Message: ADAMM GUID is not unique in the database

Explanation: A volume entry being added to or changed in the volume database had an ADAMM GUID specified which was a duplicate of the ADAMM GUID for another volume already in the volume database. All volumes in a volume database must have an ADAMM GUID that is either unique or null. (ADAMM is Advanced Device and Media Management, and a GUID is a Global Unique Identifier.)

The GUID conflict may occur if the following are both true:

- ◆ The `bephyinv.exe` or `beconv.exe` command is running on a Windows host, in `install_path\NetBackup\bin\admincmd`.

AND

- ◆ The GUID field of a record in the volume database is modified, by either adding, changing, or deleting records.

Another possible cause may be one of the following:

- ◆ The physical inventory utility (`bephyinv.exe`) has already been run on this media.



- ◆ This media had on-disk Backup Exec catalogs, and the catalog converter utility (`beconv.exe`) has already been run on this media.

Recommended Action:

1. Examine command output (if available) and the daemon and reqlib debug logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. From the daemon debug log file, determine the offset of the volume that has an ADAMM GUID conflict with the volume entry that is being added or changed. (The offset is the index of the volume in the volume database.) Using the `vmdb_dump` command, dump out all volume records in the volume configuration for the targeted volume database host and look up the volume offset indicated in the debug log file. Note the associated ADAMM GUID, which is the field `adamm_guid`.

Note Although a GUID can be changed or added by means of the `vmchange` and `vmadd` commands, the GUID field is for internal use only. Do not add or change a GUID.

Media Manager Status Code: 168

Message: ADAMM GUID does not exist in database

Explanation: The volume database was queried for a specified ADAMM (Advanced Device and Media Management) GUID, and no volumes were found matching the specified criteria. (The GUID is a Global Unique Identifier.)

This error could result if both of the following occur:

- ◆ The `bephyinv.exe` command or `beconv.exe` command is running on a Windows host (in `install_path\NetBackup\bin\admincmd`).

AND

- ◆ The GUID field of a record in the volume database is modified by either adding, changing, or deleting records.

Recommended Action:

None. This is a normal occurrence indicating that there is no volume with a particular ADAMM GUID in the targeted volume configuration. The requesting software may query the volume configuration on other hosts for a volume with the specified ADAMM GUID, or it may perform other media management related actions based on this status code.

Note Although a GUID can be changed or added by means of the `vmchange` and `vmadd` commands, the GUID field is for internal use only. Do not add or change a GUID.

Media Manager Status Code: 171

Message: a scratch pool is already defined

Explanation: A new scratch pool cannot be defined because another scratch pool already exists.

Recommended Action:

Use the scratch pool already defined, or delete the current scratch pool and create a new scratch pool.

Media Manager Status Code: 172

Message: pool not defined as a scratch pool

Explanation: You, or a NetBackup media management interface have tried to delete (unset) a scratch pool that is not defined as a scratch pool.

Recommended Action: To delete the scratch pool by using the `vmppool` command, make sure that the name of the pool specified with the `unset_scratch` option is the correct name of the scratch pool.

Media Manager Status Code: 173

Message: invalid scratch pool name

Explanation: You, or a NetBackup media management interface have tried to specify the NetBackup, DataStore, or None pool as a scratch pool. The NetBackup, DataStore, and None pools cannot be specified as scratch pools.

Recommended Action: Create a scratch pool with a different name.

Media Manager Status Code: 174

Message: unable to link to dynamic library



Explanation: An attempt to open and link to a dynamic library failed. This may be caused by a missing or unusable dynamic library for the EMC Symmetrix API. The error may be generated at both the server and the client; the dynamic libraries are used by the `ltid`, `tlld`, and `bptm` processes.

Recommended Action: Make sure that the EMC-supplied files `/usr/symapi/shlib/libsymapi.so` and `/usr/symapi/shlib/libsymlvm.so` exist on the system that reported the error. For new copies of these files, contact EMC.

Device Configuration Status Codes

These status codes appear in exit status and command output for the `tpconfig` and `tpautoconf` commands, and in system or debug logs. These codes are also presented by programs that call `tpconfig` and `tpautoconf`, such as media and device management user interfaces and the `vmopr cmd` command.

Device Configuration Status Code: 0

Message: Success

Explanation: A requested operation was successfully completed.

Recommended Action: None.

Device Configuration Status Code: 1

Message: Cannot execute command, permission denied

Explanation: The process was started by a user or process that did not have root privileges (on UNIX) or administrator privileges (on Windows), or the global device database host name could not be set.

Recommended Action:

1. If desired, give the user or process administrator privileges (on Windows) or root privileges (on UNIX) and reissue the device configuration request.
2. If the volume daemon (UNIX) or NetBackup Volume Manager service (Windows) is not running, start it and retry the operation that tried to set the global device database host name, such as during an install.
3. Establish a common global device database host name as follows:
 - ◆ Run `tpautoconf -get_gdbhost` on other hosts.
 - ◆ Set the global device database host name with


```
tpautoconf -set_gdbhost host_name
```

 where *host_name* is the host name returned by `tpautoconf -get_gdbhost`.

Device Configuration Status Code: 2

Message: The `external_robot_mappings` file has invalid license info

Explanation: The problem concerns one of the following files:

- ◆ `/usr/opensv/share/external_robot_mappings.txt` (UNIX)



- ◆ *install_path*\VERITAS\NetBackup\share\external_robot_mappings.txt (Windows)

1. The file does not exist.
2. The file is for a different version of NetBackup. You can find what version it is for by reading the header in the file.
3. The file has a corrupted licensing digest.

Recommended Action: Download the latest external mappings files from the VERITAS support website at www.veritas.com.

Device Configuration Status Code: 3

Message: The external_drive_mappings file has invalid license info

Explanation: The problem concerns one of the following files:

- ◆ /usr/opensv/share/external_drive_mappings.txt (UNIX)
- ◆ *install_path*\VERITAS\NetBackup\share\external_drive_mappings.txt (Windows)

1. The file does not exist.
2. The file is for a different version of NetBackup. You can find what version it is for by reading the header in the file.
3. The file has a corrupted licensing digest.

Recommended Action: Download the latest external mappings files from the VERITAS support website at www.veritas.com.

Device Configuration Status Code: 4

Message: The global device database version is incompatible.

Explanation: The Device Configuration wizard is trying to store the global device information on a server that is at the wrong NetBackup server level.

Recommended Action: Choose a NetBackup server on which to store the global device information that is running at the same Netbackup version as that used on the host where the device discovery process was executed.

Device Configuration Status Code: 5

Message: Cannot synchronize global device database



Explanation: There was a failed request to synchronize the global device database with the local drive (`ltidevs`) or robot (`robotic_def`) databases. This could be caused by the Media Manager volume daemon / NetBackup Volume Manager Service not running on the global device database host. This could also be caused by conflicting information between the global device database and the local databases mentioned above.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders (including the `tpcommand` log). Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that `vmc` is running on the global device database host.
3. Examine the device configurations of other hosts sharing the same global device database, looking for conflicts such as duplicate robot numbers with conflicting robot types.

Device Configuration Status Code: 6

Message: Robot type is not supported on this platform

Explanation: A request was made to add a robot, but the robot type is not supported on the device host.

Recommended Action: Check www.veritas.com and product release documentation for supported device configurations.

Device Configuration Status Code: 7

Message: Invalid SCSI port number for the robot

Explanation: A request was made to add or change the SCSI port number for a robot, but the SCSI port number provided was not valid.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify the correct SCSI port number for the robot. Perform device discovery using the Device Configuration wizard, or check the Windows registry as needed to obtain the SCSI port number.

Device Configuration Status Code: 8

Message: Invalid SCSI bus number for the robot

Explanation: A request was made to add or change the SCSI bus number for a robot, but the SCSI bus number provided was not valid.

Recommended Action: Specify the correct SCSI bus number for the robot. Perform device discovery using the Device Configuration wizard, or check the Windows registry as needed to obtain the SCSI bus number.

Device Configuration Status Code: 9

Message: Invalid SCSI target for the robot

Explanation: A request was made to add or change the SCSI target for a robot, but the SCSI target provided was not valid.

Recommended Action: Specify the correct SCSI target for the robot. Perform device discovery using the Device Configuration wizard, or check the Windows registry as needed to obtain the SCSI target.

Device Configuration Status Code: 10

Message: Invalid SCSI logical unit number for the robot

Explanation: A request was made to add or change the SCSI logical unit number for a robot, but the SCSI logical unit number provided was not valid.

Recommended Action: Specify the correct SCSI logical unit number for the robot. Perform device discovery using the Device Configuration wizard, or check the Windows registry as needed to obtain the SCSI logical unit number.

Device Configuration Status Code: 11

Message: Invalid Usage

Explanation: One of the Media Manager device configuration commands (`tpconfig` or `tpautoconf`) was executed with improper options, or there is an incompatibility between components or versions of the product.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the `tpconfig` or `tpautoconf` usage statement for expected usage and compare with the parameters being sent to start the new process.
3. Verify that all Media Manager binaries are at a compatible version level.

Device Configuration Status Code: 12

Message: Failed writing drive or robot config file

Explanation: A request was made to change the device configuration, but an error was encountered while writing to the device database.

Recommended Action:

1. Examine the daemon debug log and command or interface output for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon / NetBackup Volume Manager service, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and available file system space for writing to the device configuration database files (`ltidevs` and `robotic_def`), located in the directory `/usr/opensv/volmgr/database` (UNIX) or in the folder



install_path\Volmgr\database (Windows). Display the device configuration to determine whether or not the database is corrupt, and restore a saved copy of the databases from catalog backups, or delete them and recreate the device configuration as needed.

Device Configuration Status Code: 13

Message: Failed reading drive or robot config file

Explanation: A request was made to change or list the device configuration, but an error was encountered while reading from the device database.

Recommended Action:

1. Examine the daemon debug log and command or interface output for a more detailed message on the error.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and check for the existence of the device configuration database files (*ltidevs* and *robotic_def*), located in the directory */usr/opensv/volmgr/database* (UNIX) or the folder *install_path\Volmgr\database* (Windows). Display the device configuration to determine whether or not the database is corrupt. Restore a saved copy of the databases from catalog backups, or delete them and recreate the device configuration as needed.

Device Configuration Status Code: 14

Message: Invalid drive index

Explanation: A request was made to add, update, or list a drive configuration entry, and the specified drive index was not associated with a configured drive.

Recommended Action:

1. Display the device configuration to obtain the list of valid drives. Avoid making device configuration changes from multiple sources simultaneously.
2. If more information is needed, examine the daemon debug log and command or interface output for a more detailed message on the error.



- a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
- b. Retry the operation and examine the log files.

Device Configuration Status Code: 15

Message: Invalid robot number

Explanation: On a request to modify the device configuration, the specified robot number was not within the allowable range, or the robot number did not correspond to a currently configured robot, or the robotic database is corrupted.

Recommended Action:

1. Specify a robot number in the range of 0 to 32767.
2. Ensure that all device configuration changes or deletions are performed on devices that are currently part of the device configuration.
3. Check the integrity of the robotic database file `robotic_def` located in the directory `/usr/opensv/volmgr/database` (UNIX) or the folder `install_path\Volmgr\database` (Windows), by displaying the contents of the device configuration. Restore a saved copy of the robotic database from catalog backups, or delete it and recreate any needed robotic configuration information.

Device Configuration Status Code: 16

Message: A SCSI inquiry sent to the device has failed

Explanation: On a request to add or update a SCSI robotic library or drive, Media Manager failed to obtain the serial number and inquiry string for the device. This information is obtained by Media Manager by sending a SCSI Inquiry command to the device. Failure indicates that NetBackup was not able to communicate with the device by means of SCSI.

Recommended Action:

1. Ensure that the device is physically connected.
2. Ensure that the operating system is configured to recognize the device and that the operating system can see the device.
3. Ensure that no other process is using the device and that the device is not offline.



Device Configuration Status Code: 17

Message: This robot type does not support multiple media types

Explanation: An attempt to add or update a robotic drive has failed because there are drives configured in this robotic library with a different drive type. (Some NetBackup robotic library types do not support multiple media types.) Refer to the *NetBackup Release Notes* or to the *NetBackup Media Manager System Administrator's Guide* for more information on which NetBackup robotic library types support multimedia.

Recommended Action:

1. Configure all drives for this robotic library with the same drive type.
2. If you are using NetBackup BusinessServer and want a robotic library with multiple media types, contact VERITAS to purchase NetBackup DataCenter.

Device Configuration Status Code: 18

Message: Invalid robot type

Explanation: On a request to modify the device configuration, the specified robot type was invalid, or it did not match the robot type for the robot associated with the specified robot number.

Recommended Action:

1. Check the device configuration for configured robots, and specify the correct robot type applicable for the device configuration information being updated.
2. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
3. Verify that all Media Manager binaries are at a compatible version level.

Device Configuration Status Code: 19

Message: Invalid device path name

Explanation: On a request to change the device configuration, the specified device path or device name was not valid.



Recommended Action:

1. To avoid configuring invalid device paths and device names, use the Device Configuration wizard (on supported device discovery platforms) so that device paths and device names are automatically configured.
2. On Windows hosts, check the operating system configuration or registry for device names and refer to the `tpconfig` command in NetBackup online help. On UNIX hosts, refer to the appropriate chapter in the *NetBackup Device Configuration Guide*. Always use no-rewind device files for drives attached to UNIX hosts, and check to ensure that the specified device paths exist as character-special files. Check for detailed errors from the command or user interface output.

Device Configuration Status Code: 20

Message: Duplicate device path names

Explanation: The same device path name was used for the optical drive character and volume header names.

Recommended Action: Refer to the appropriate chapter in the *NetBackup Device Configuration Guide* to determine which optical drive names should be specified.

Device Configuration Status Code: 21

Message: Robot number is already in use

Explanation: On a request to add a robot to the device configuration, the robot number was found to be already in use for a different robot.

Recommended Action: Check the device configuration on all device hosts for configured robots, and specify a robot number that is not already in use. Use `tpautoconf -get_gdbhost` to obtain the global device database host, and use the following

```
vmglob -h global_device_database_host -listall
```

to display all devices sharing a common global device database.

Device Configuration Status Code: 22

Message: Device path is already in use

Explanation: On a request to add or change robot information in the device configuration, the specified robotic device path is already in use for another configured robot.

Recommended Action:



1. To avoid configuring device paths that are already in use, use the Device Configuration wizard (on supported device discovery platforms) so that device paths and device names are automatically configured.
2. Display the device configuration using `tpconfig -d` or a device configuration interface to see the robotic information that is already configured. On Windows hosts where there are multiple ways to configure robots (changer names or port/bus/target/LUN), check the operating system configuration or registry for changer names and their associated SCSI paths. Check for detailed errors from the command or user interface output.

Device Configuration Status Code: 24

Message: Incomplete robot information

Explanation: On a request to change the device configuration, some of the required robot information was not specified.

Recommended Action: Check the command usage and reissue the request with all required robot information specified.

Device Configuration Status Code: 25

Message: Robot drive number in use for this robot

Explanation: On a request to change the device configuration, the specified drive address in the robot was found to be already in use by another drive in the device configuration.

Recommended Action: The drive address in the robot is the robot drive number for most robot types, the ACS/LSM/PANEL/DRIVE coordinates for ACS robots, or a vendor drive name for TLH and TLM robots. Two drives cannot have the same drive address in a robot in a given device configuration. If the drive addresses need to be adjusted, either delete one of the drives or make use of an unused drive address as a temporary state. For example, if a robot has two drives with robot drive numbers 1 and 2 that need to be swapped, change one drive to use robot drive number 3 temporarily, change the other drive to use robot drive number 1 or 2 as appropriate, and finally change the first drive to the open robot drive address 1 or 2.

Device Configuration Status Code: 27

Message: Invalid drive type for the robot

Explanation: On a request to configure a drive to be in a robot, it was found that the drive type was not valid for the selected robot type.

Recommended Action: In the *NetBackup Media Manager System Administrator's Guide* appendices, check the Robot Attributes tables to determine valid media types for a given robot type. Drive types directly correspond to the listed media types. Configure supported devices so that invalid combinations of drive types and robot types are not required.

Device Configuration Status Code: 28

Message: Invalid robot drive number for the robot type

Explanation: On a request to configure a drive to be in a robot, it was found that the robot drive number was not valid for the selected robot type.

Recommended Action: The robot drive number, or for ACS robots the set of ACS drive identifiers, is limited to certain ranges based on the robot type. These limits are based on a supported device list. An invalid robot drive number means that the drive number was not within the acceptable range. Make sure that the robot hardware is supported and that the required patches are installed to support the robotic library. If the robot type is TLH or TLM, do not specify a robot drive number, because the drives are addressed using a vendor drive name.

Device Configuration Status Code: 29

Message: Drive index is in use by another drive

Explanation: On a request to add a drive to the device configuration, the requested drive index was found to be in use on the targeted device host.

Recommended Action:

1. To avoid configuring a drive index that is already in use, use the Device Configuration wizard (on supported device discovery platforms) so that the drive index is automatically configured.
2. If using a device configuration interface that allows the drive index to be specified, use `tpconfig -d` to determine the drive indexes that are already in use on the targeted device host, and specify a drive index that is not already in use.

Device Configuration Status Code: 30

Message: Robot number is in use by another robot

Explanation: On a request to add or update a robotic drive in the device configuration, it was found that the robot number and robot type specified were associated with an existing robot of a different robot type.



Recommended Action: Check the device configuration on the targeted device host and identify the configured robots. On the drive configuration request, specify both the robot number and robot type that relate to the robot containing the drive.

Device Configuration Status Code: 31

Message: Robot number does not exist

Explanation: On a request to add or update a drive or robot in the device configuration, it was found that the robot number and robot type specified were not associated with any configured robots on the targeted device host.

Recommended Action: Check the device configuration on the targeted device host and identify the configured robots. Every drive that is configured as a robotic drive must already have its robot configured on that device host. For shared robotic libraries having robotic control on a remote host, there must be a logical robotic entry that refers to the remote host having robotic control. Add the robot to the device configuration first, then add the drive, defining it to be in the robot. If the robot was already configured, specify the correct robot number and robot type on the drive or robot configuration request.

Device Configuration Status Code: 34

Message: Drive name is already in use by another drive

Explanation: On a request to add or update a drive in the device configuration, the requested drive path was found to be in use on the targeted device host.

Recommended Action:

1. To avoid configuring paths that are already in use, use the Device Configuration wizard (on supported device discovery platforms) so that the drive paths are automatically configured.
2. Before making configuration changes, check the existing drive configuration through a device configuration interface or run `tpconfig -d` to determine the drive paths that are already in use on the targeted device host, and specify a drive path that is not already in use.

Device Configuration Status Code: 35

Message: Drive name does not exist

Explanation: On a request to update or delete a drive in the device configuration, no drives having the specified drive name were found on the targeted device host.

Recommended Action: Check the device configuration on the targeted device host and identify the configured drives. When making drive configuration changes or deletions, specify the drive name as it is configured, taking care to use the proper case.



Device Configuration Status Code: 36

Message: <NONE>

Explanation: On a request to make a device configuration change, an error occurred for which a detailed message has been displayed in the command or utility interface output.

Recommended Action: Examine the daemon debug log and command or interface output for a more detailed message on the error.

1. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the volume daemon / NetBackup Volume Manager service, or start vmd with the verbose option.
2. Retry the device configuration request and examine the logs.

Device Configuration Status Code: 37

Message: Residence is not licensed for shared drive support

Explanation: On a request to add or update a drive in the device configuration, the drive was specified as shared, but there is no support for shared drives for that drive type or for the type of robot associated with the drive.

Recommended Action: Check www.veritas.com and product release documentation for supported device configurations.

Device Configuration Status Code: 38

Message: Current version does not support remote device host

Explanation: On a request to change the global device database host or the volume database host for a residence, the specified host is not the local host, and the current software is not licensed to allow remote hosts.

Recommended Action: Check product documentation for supported device configurations. Obtain an additional software license that allows remote hosts to be configured, or specify only local host names on the configuration request.

Device Configuration Status Code: 39

Message: Adding this drive would exceed the maximum allowed

Explanation: On a request to add a drive to the device configuration, the licensed limit for the maximum number of drives was reached on the targeted host.



Recommended Action: Check product documentation for supported device configurations. Obtain an additional software license that allows more drives to be configured, or limit the configuration to the number of drives allowed by the current licensing.

Device Configuration Status Code: 40

Message: Adding this device would exceed the maximum allowed

Explanation: On a request to add a robot to the device configuration, the licensed limit for the maximum number of robots was reached on the targeted host.

Recommended Action: Check product documentation for supported device configurations. Obtain an additional software license that allows more robots to be configured, or limit the configuration to the number of robots allowed by the current licensing.

Device Configuration Status Code: 41

Message: Cannot change terminal mode

Explanation: A system call failed when an attempt was made to change the mode for terminal input between cooked and raw.

Recommended Action: Examine the user interface output for the system error associated with the failed system call, and troubleshoot according to operating system vendor recommendations.

Device Configuration Status Code: 42

Message: Cannot create miscellaneous working repository

Explanation: On a device configuration request, the miscellaneous working directory/folder was missing and could not be created.

Recommended Action: Find out why `/usr/opensv/volmgr/misc` (UNIX) or `install_path\volmgr\misc` (Windows) cannot be created. On Windows, determine which accounts the NetBackup Volume Manager service and device configuration interfaces are running under, and compare them with the security properties of the database folder. On UNIX, determine whether users or device configuration interface callers are running under a user and group with permissions to create the miscellaneous directory.

Device Configuration Status Code: 43

Message: Cannot backup/restore local device database files



Explanation: There was a failed request to create a backup copy, remove a backup copy, or replace the current copy of the local device databases. These databases are `ltidevs` and `robotic_def`, located in `/usr/opensv/volmgr/database` (UNIX) or `install_path\volmgr\database` (Windows).

Recommended Action:

1. Examine the daemon debug log and command or interface output for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon / NetBackup Volume Manager service, or start `vm` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and check for the existence of the local device database files. Display the device configuration to determine whether or not the database is corrupt, and restore a saved copy of the databases from catalog backups, or delete them and recreate the device configuration as needed.

Device Configuration Status Code: 44

Message: Cannot discover devices. See the Troubleshooting Guide for details.

Explanation: Any of the following: device discovery was attempted on a platform where it is not supported according to the currently installed software, there was an internal consistency problem with the global device database, or device discovery could not obtain or verify its lock file.

Recommended Action:

1. Check `www.veritas.com` and product release documentation for supported platforms for device discovery. Upgrade the installed software to the latest available patch level if documentation indicates that device discovery is supported on the targeted host platform.
2. Examine the daemon debug log and command or interface output for a more detailed message on the system error, as follows.



- a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the volume daemon / NetBackup Volume Manager service, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs. One of the following may have occurred, as described in the following steps.
3. Lock file problems: The device discovery process sets a lockfile in the `/usr/opensv/volmgr/misc` (UNIX) or `Install_path\Volmgr\misc` (Windows) directory named `tpac.lock` to ensure that only one instance of discovery is running on a particular host. It then checks the lockfile before updating the configuration.
 - ◆ Cannot obtain lockfile.
 The lockfile may be held by another discovery process. In this case the following error is displayed:

```
"another tpautoconf is already running"
```

 Use standard OS process tools (`ps` on UNIX or Task Manager on Windows) to determine if another `tpautoconf` process is running. If not, delete the lockfile and re-run device discovery. If another `tpautoconf` process is running, wait for it to complete before retrying.
 - ◆ Failed checking lockfile.
 In the case of long device-discovery cycles, the interface may timeout or the user may cancel the process. Part of the timeout or cancelling is to remove the lockfile. This tells the device discovery process that it should not continue making modifications to the device configuration. If this happens, re-run the discovery process.
4. Global device database inconsistency: Prior to beginning the process of discovering new devices on a host, the global device database is checked for internal consistency. The following are example log messages in the `tpcommand` log directory, along with steps to determine the problem and correct it.
 - ◆ Fatal Global Database consistency error: Couldn't contact robot 1 on host mud
 The global device database has found a robot entry for robot 1 on mud, but could not communicate with it. Delete that robot on host mud and re-run device discovery there.
 - ◆ Fatal Global Database consistency error: TLM/ACS control host mismatch 1 on hosts bison and mud.

The global device database has found TLM or ACS robot entries for robot 1, on hosts bison and mud, but their ACSLS Host or DAS Server did not agree. Determine which host is running the ACS library software or the DAS software. Using `tpconfig` or the administration console, update the robot entry to indicate the correct ACSLS Server name or DAS host name.

- ◆ Fatal Global Database consistency error: remote control host mismatch 1 on hosts bison and mud.

The global device database has found remote robot entries for robot 1 on hosts bison and mud, but their robot control hosts did not agree. Determine which host should be the controlling host. Then determine which host is incorrect. Delete the remote robot entry on the host that is incorrect, and re-run device discovery.

- ◆ Fatal Global Database consistency error: missing robot control host 1.

The global device database has found a remote robot entry for robot 1, but the corresponding controlling entry could not be found. Check each of the media servers in the configuration for a remote robot definition for robot 1. Delete that robot and re-run device discovery there.

- ◆ Fatal Global Database consistency error: serial number 1234567 on robot 1 on host bison, and on robot 2 on host mud.

The global device database has found duplicate robot serial numbers on robot 1 on bison, and robot 2 on mud. This is probably an invalid configuration. First determine if these are unique robots, or if they are actually the same robot connected to each host. If they are unique robots, run `tpconfig -tables` on bison and mud and look for serial number 1234567 on robot 1 on bison and robot 2 on mud. If these serial numbers are the same, check with the robot vendor to see if it is possible to modify the serial number. If the serial numbers are different, delete the robot on one of the hosts and re-run device discovery there.

- ◆ Fatal Global Database consistency error: drive SSO mismatch MyDrive0 on hosts bison and mud

The global device database has at least two entries for MyDrive0, one on bison, and one on mud. One of these two entries states that the drive is shared. Determine if MyDrive0 should be shared and look for entries that are conflicting. Run `tpconfig -d` to determine which of these hosts is incorrect. Delete the drive on the host that has the incorrect data and re-run device discovery on that host. If neither of these hosts is incorrect according to the `tpconfig -d` output, delete the drive on both hosts and re-run device discovery on both hosts.

- ◆ Fatal Global Database consistency error: serial number on drive MyDrive0 on host bison, and on drive MyDrive1 on host mud.

The global device database has found duplicate drive serial numbers on MyDrive0 on bison, and on MyDrive1 on mud. This is probably an invalid configuration. First determine if these are unique drives, or if they are actually the



same drive connected to each host. If they are unique drives, run `tpconfig -tables` on bison and mud and look for the serial number for MyDrive0 and MyDrive1. If the serial numbers are the same, check with the drive vendor to see if it is possible to modify the serial number. If the serial numbers are different, delete the drive on one of the hosts and re-run device discovery there.

Device Configuration Status Code: 45

Message: No device found in RSM at the specified location

Explanation: On a request to add or change robot information in the device configuration, the specified robotic device path could not be found in the system registry. This status code applies to Windows 2000 systems only.

Recommended Action: Use the Media and Device Management interface New Robot or Change Robot display to browse for robots in the system registry, eliminating the need to manually specify device paths or device control parameters. Check the operating system registry for changer names and their associated SCSI paths when manually specifying robotic control information. Check for detailed errors from the command or user interface output.

Device Configuration Status Code: 46

Message: Unable to retrieve GUID from RSM api

Explanation: On a request to add or change robot information in the device configuration, an error was encountered while attempting to obtain the RSM GUID for the specified device path or device control parameters. (RSM is the Microsoft Removable Storage Manager and GUID is a Global Unique Identifier.) This error code applies to Windows 2000 systems only.

Recommended Action:

1. Use the Media and Device Management interface New Robot or Change Robot display to browse for robots in the system registry, eliminating the need to manually specify device paths or device control parameters.
2. Check the operating system registry for changer names and their associated SCSI paths when manually specifying robotic control information. Check for detailed errors from the command or user interface output. Ensure that the Removable Storage service is running. Ensure that the device is present and working properly according to the Removable Storage administration interface.

Device Configuration Status Code: 47

Message: Cannot backup/restore global device database files



Explanation: There was a failed request to create a backup copy, remove a backup copy, or replace the current copy of the local device databases. This database is `globDB`, located in `/usr/opensv/volmgr/database` (UNIX) or `install_path\Volmgr\database` (Windows) on your global device database host.

Recommended Action:

1. Examine the daemon debug log and command or interface output for a more detailed message on the system error, as follows.
 - a. If not already enabled, enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the volume daemon / NetBackup Volume Manager service, or start `vmd` with the verbose option.
 - b. Retry the operation and examine the logs.
2. Examine the permissions and check for the existence of the global device database file. Display the device configuration to determine whether or not the database is corrupt, and restore a saved copy of the databases from catalog backups, or delete them and recreate the device configuration as needed.

Device Configuration Status Code: 48

Message: RSM is supported only on Microsoft Windows 2000 and later OS versions.

Explanation: On a request to make a device configuration change, the RSM (Microsoft Removable Storage Manager) robot type was specified, but the operating system version on the targeted device host does not support RSM devices.

Recommended Action: Specify RSM devices only on Windows 2000 or later Windows-based operating systems.

Device Configuration Status Code: 49

Message: The global device database host name is invalid.

Explanation: On a device configuration request, the global device database host name could not be obtained.

The global device database host name is obtained through an internal request that is sent to `vmd` (the volume daemon on UNIX or the NetBackup Volume Manager service on Windows). This request is likely to fail if `vmd` is not running on the targeted device host.

Recommended Action:



1. See the recommended actions for the following Media Manager status codes:
 - ◆ 69, failed sending request to vmd
 - ◆ 70, cannot connect to vmd
 - ◆ 71, failed sending to vmd
 - ◆ 72, failed receiving from vmd
2. Use `tpautoconf -get_gdbhost` on a device host to obtain its global device database host name. Use `tpautoconf -set_gdbhost` to set the global device database host name, as needed.

Device Configuration Status Code: 50

Message: Device Configuration was not upgraded.

Explanation: An attempt was made to make an automated device configuration change, but the device configuration from a previous release has not been upgraded.

Recommended Action: Run the device configuration upgrade as part of the upgrade installation procedure. If a device configuration from a previous release has been restored, run `tpautoconf -upgrade`. If the Media Manager database directory/folder (or its contents) has been recently lost and the directory/folder has been partially recreated with device databases from the current release, run `tpautoconf -ready_devices` and retry the automated device configuration change request.

Device Configuration Status Code: 51

Message: No device is registered at these SCSI coordinates.

Explanation: On a request to add or change robot or drive information in the device configuration, the specified SCSI coordinates did not correspond to a device in the system registry. This status code applies to Windows systems only.

Recommended Action: To avoid manually specifying SCSI coordinates (port, bus, target, and LUN), use the Device Configuration wizard so that device configuration requests are fully automated (on supported device discovery platforms), or use the Media and Device Management interface to browse for devices in the system registry. Check the operating system registry to ensure that devices are present at the specified coordinates when SCSI coordinates are manually configured.

Device Configuration Status Code: 52

Message: The device name is not valid, no device responded.



Explanation: On a request to add or change robot or drive information in the device configuration, there was no device found in the system registry with the specified device name. This error code applies to Windows systems only.

Recommended Action: To avoid manually specifying the device name, use the Device Configuration wizard so that device configuration requests are fully automated (on supported device discovery platforms), or use the Media and Device Management interface to browse for devices in the system registry. Check the operating system registry to ensure that devices are present at the specified coordinates when devices are manually configured.

Device Configuration Code: 53

Message: Not licensed for Fastrax support

Explanation: An attempt was made to add or update a Fastrax device without a valid Fastrax license. The request cannot be performed without a valid NetBackup for EMC Fastrax license key.

Recommended Action: Install a Fastrax license key, then re-issue the configuration request.



Format Optical Status Codes

These status codes appear in exit status and command output for the `tpformat` command, and in system or debug logs. These codes are also presented by programs that call `tpformat`, such as media and device management user interfaces and the `vmopr cmd` command.

Format Optical Status Code: 0

Message: Success

Explanation: An optical volume format operation was successfully completed.

Recommended Action: None.

Format Optical Status Code: 1

Message: `tpformat`: Invalid usage

Explanation: The format optical disk command `tpformat` was executed with improper options or there is an incompatibility between components or versions of the product.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the `tpformat` usage statement and compare with the parameters being sent to start the new process.
3. Verify that all Media Manager binaries are at a compatible version level.

Format Optical Status Code: 2

Message: `tpformat`: Cannot set volume header

Explanation: The format optical disk command `tpformat` encountered a system, device, or media error while trying to write the optical volume header.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify integrity of the device and the media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*. Examples of problems that may have been encountered are:
 - a. Operating system error where exclusive access to the disk could not be set.
 - b. Operating system error while attempting to format the disk.
 - c. Cannot determine the name of the disk.
 - d. Operating system was unable to set the geometry.
 - e. Could not write the volume table of contents.
 - f. Cannot determine SCSI passthrough path to the device.
 - g. Cannot read capacity of the optical platter.
 - h. Cannot seek to write the volume header.
 - i. Optical volume format is not supported on the targeted platform.

Format Optical Status Code: 3

Message: tpformat: Cannot open

Explanation: The format optical disk command `tpformat` encountered a system, device, or media error while trying to open the optical disk device.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify integrity of the device and the media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*. Use the `tpformat -f` option if the media has not already been sector formatted.

Format Optical Status Code: 4

Message: `tpformat: Cannot read`

Explanation: The format optical disk command `tpformat` encountered a system, device, or media error while trying to read the optical disk.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify the integrity of the device and media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*. Use the `tpformat -f` option if the media has not already been sector formatted.

Format Optical Status Code: 5

Message: `tpformat: Cannot seek`

Explanation: The format optical disk command `tpformat` encountered a system, device, or media error while trying to seek on or determine characteristics of the optical disk.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify the integrity of the device and media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*.

Format Optical Status Code: 6

Message: `tpformat: Cannot write`

Explanation: The format optical disk command `tpformat` encountered a system, device, or media error while trying to write the optical disk.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify the integrity of the device and media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*. Use the `tpformat -f` option if the media has not already been sector formatted.

Format Optical Status Code: 7

Message: `tpformat: Existing media ID`

Explanation: The format optical disk command `tpformat` could not format the optical disk because it has already been formatted.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Ensure that the device files and optical drive library address are correct, since this error may occur if the device paths or drive address was incorrectly configured. Use the `tpformat -o` (overwrite) option if you want to reformat the optical platter. If the platter is WORM (write-once, read-many), it cannot be reformatted.

Format Optical Status Code: 8

Message: tpformat: Must be root

Explanation: The format optical disk command `tpformat` was run by a non-root user.

Recommended Action: Execute `tpformat` only as the root user.

Format Optical Status Code: 9

Message: tpformat: Tape request failed

Explanation: The format optical disk command `tpformat` encountered a situation where the optical volume could not be mounted.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify the integrity of the device and media, and check the system device files for correctness according to the *NetBackup Device Configuration Guide*. Investigate robotic errors and determine whether mount requests are being canceled by the administrator.



Format Optical Status Code: 10

Message: tpformat: Invalid robot

Explanation: The format optical disk command `tpformat` could not find a valid, specified robot in the device configuration.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the device configuration to see if a robot of type TLM (Tape Library Multimedia) or ODL (Optical Disk Library) is configured, matching the robot number passed on the `tpformat -r` option.

Format Optical Status Code: 11

Message: tpformat: Command interrupted

Explanation: The format optical disk command `tpformat` was interrupted because the optical mount request was canceled or not accomplished within the required time interval.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Resubmit the request and observe the Device Monitor for standalone optical mount requests, servicing them as needed. Look for pending requests indicating reasons for the optical mount not being completed.



Format Optical Status Code: 12

Message: tpformat: Skip

Explanation: Because an optical disk format operation failed, remaining optical format operations were skipped.

Recommended Action: Look in the user interface output for the cause of the initial optical disk format failure. Resolve the situation based on the error provided, and use the `tpformat` command interface to format any remaining optical disks.

Format Optical Status Code: 13

Message: tpformat: No media present in drive or robot slot

Explanation: The format optical disk command `tpformat` was interrupted because no media was found in the drive or robotic slot.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Resubmit the request and observe the Device Monitor for standalone optical mount requests, servicing them as needed, and look for pending requests indicating reasons for the optical mount not being satisfied.



Device Management Status Codes

These status codes appear in exit status and command output for the `ltid`, `tpclean`, `tpreq`, and `tpunmount` commands, and in system or debug logs. These codes are also presented by programs that call those commands, such as media and device management user interfaces and the `vmopr cmd` command.

Device Management Status Code: 1

Message: Invalid Drive Type/Density

Explanation: An invalid density was specified for the `-d` parameter on `tpreq`.

Recommended Action: Check the `tpreq` man page (command description) for the list of valid densities. Resubmit the mount request using a valid density.

Device Management Status Code: 2

Message: Drive is currently assigned

Explanation: A request was made for a specified drive, but the drive was assigned.

Recommended Action: Display drive status (using `vmopr cmd -d` or other means) to see the list of drives and their assignment status. Run the request later, or first clear the drive assignment by stopping application activity on the drive, unmounting the media with `tpunmount`, or resetting the drive. If the wrong drive was specified, resubmit the request specifying the correct drive name or index as appropriate for the interface being used.

Device Management Status Code: 3

Message: Error in Sending Operator Message

Explanation: An attempt was made to send an operational message to `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows), on an already existing internal message queue used for inter-process communication. But an error was encountered in the message communications. The error probably indicates a lack of system resources for message queues.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 4

Message: Error in Receiving Operator Message

Explanation: An attempt was made to receive a message from `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows) on an already existing internal message queue used for inter-process communication. But an error was encountered in the message communications. The error probably indicates a lack of system resources for message queues.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use. Investigate whether `ltid` is tied up in communications with devices or other components.

Device Management Status Code: 5

Message: Error in Sending Daemon Message



Explanation: An attempt was made by `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows) to send an internal process communications message to a robotic daemon/process using an already existing internal message queue. An error was encountered in the message communications. The error probably indicates a lack of system resources for message queues.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use. Investigate whether the robotic daemon/process on the local device host is tied up in communications with devices or other components.

Device Management Status Code: 6

Message: Error in Receiving Daemon Message

Explanation: An attempt was made by `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows) to receive or process an internal process communications message to a robotic daemon/process using an already existing internal message queue, but an error was encountered in the message communications. The error probably indicates a lack of system resources for message queues, or mismatched software components.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use. Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 7

Message: Error in Sending User Message

Explanation: An attempt was made to send a user message to `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows) on an already existing internal message queue used for inter-process communication. But an error was encountered in the message communications. The error probably indicates a lack of system resources for message queues.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 8

Message: Error in Receiving User Message

Explanation: An attempt was made to receive a user message from `ltid` (the Media Manager device daemon on UNIX and the NetBackup Device Manager service on Windows) on an already existing internal message queue used for inter-process communication. But an error was encountered in the message communications. The error probably indicates a lack of system resources for message queues. On Windows, this error can also occur if an internal-system-registered event cannot be opened.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 9

Message: Drive is currently reserved

Explanation: An attempt was made to reserve a shared drive, but the drive is already reserved. This status code is related to the internal implementation of the SSO feature, not SCSI Reserve/Release.

Recommended Action: This is an unexpected condition that will be automatically retried. If problems persist, stop and restart `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows).

Device Management Status Code: 10

Message: IPC sequence error

Explanation: An internal process communications message sequencing error has occurred.

Recommended Action: Examine command output (if available), debug logs, and system logs for messages related to the error.

1. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
2. Retry the operation and examine the logs.

Device Management Status Code: 11

Message: One implicit reserve already exists

Explanation: A tape mount has been requested with an unsupported option.



Recommended Action: Verify that the installed software components are all at a compatible release version.

Device Management Status Code: 12

Message: Invalid Operator

Explanation: An internal list of operators could not be obtained.

Recommended Action: This is an unexpected internal error. Stop and restart `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows).

Device Management Status Code: 13

Message: Error in IPC SHMGET call

Explanation: A process was unable to get a shared memory identifier associated with a segment of shared memory that `ltid` maintains. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather output from the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 14

Message: Error in IPC SHMAT call

Explanation: A process was unable to attach a shared memory segment that `ltid` maintains. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 15

Message: The drive is DOWN

Explanation: An attempt was made to mount media on a drive or to reserve a shared drive which has since been logically configured to the DOWN state.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Check the application log files (such as the bptm log) to see why the drive may have been configured DOWN.
3. Check the integrity of the drive, drive path, and media.

Device Management Status Code: 16

Message: No mount pending for given mount index

Explanation: An attempt was made to retrieve information about a pending mount request, but no such pending mount request was found.

Recommended Action: Use a device monitor interface or consult application logs to see whether the request has been completed or canceled. Requests to retrieve information for pending mount requests are valid only when the mount request is actually pending.



Device Management Status Code: 17

Message: Drive does not support pending request density

Explanation: A drive was selected that has a drive type which is not compatible with the requested density.

Recommended Action:

1. Allow the drive selection to be determined automatically.
2. When selecting the drive manually, check the device configuration and the valid density table (available in the `tpreq` man page or command description), then specify a drive that is compatible with the requested density.

Device Management Status Code: 18

Message: Invalid volume count

Explanation: A tape mount has been requested with an unsupported option.

Recommended Action: Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 19

Message: Only the administrative user can perform the requested operation

Explanation: Either an attempt was made to stop `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows), or the `tpclean` command was called but the user was not root (UNIX) or the administrator (Windows).

Recommended Action: If desired, give the user or process administrator privileges on Windows or root privileges on UNIX and retry the operation.

Device Management Status Code: 20

Message: Cannot stop device daemon with tapes assigned

Explanation: An attempt was made to stop `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows), but media is currently mounted and assigned.

Recommended Action: Halt all jobs referencing media, unmount all media, and stop all applications from using Media Manager before trying to stop `ltid`. If unable to unmount media through the application interface, check for the existence and permissions of the `.ltisymlinks` file in the `/usr/openv/volmgr/misc` directory or in the

install_path\Volmgr\misc folder. Invoke `tpunmount filename` for each line in the `.ltisymlinks` file, where *filename* specifies the contents of a line in that file. For example, on UNIX, the command may look like the following:

```
tpunmount /usr/opensv/netbackup/db/media/tpreq/A00001
```

Device Management Status Code: 21

Message: The drive is not ready or inoperable

Explanation: A drive was selected for a mount request, but the drive is not ready with loaded media.

Recommended Action: Wait until the drive is ready before manually assigning a drive to a pending mount request.

Device Management Status Code: 22

Message: IPC Error: Daemon may not be running

Explanation: A request to `ltid` could not be serviced. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.) `ltid` is probably not running. If `ltid` is still running, its process lock file may have been removed. Also, message queues may not be functioning correctly on the system.

Recommended Action:

1. If `ltid` is not running, start `ltid` and try the operation again. On UNIX, run `/usr/opensv/volmgr/bin/ltid`, and on Windows, start the NetBackup Device Manager service.
2. If `ltid` was already running, check for the existence and permissions of the lock file itself and the lock file directory, which are `/usr/opensv/volmgr/misc/.ltipid` (UNIX) or `install_path\Volmgr\misc\ltipid` (Windows). Terminate the `ltid` process if it is running. Create the lock directory/folder and adjust the permissions as needed so that `ltid` can obtain the above lock.
3. On UNIX, check the `msgget` man page and look for suggestions on troubleshooting the system message queues.

Device Management Status Code: 23

Message: Invalid Drive Number

Explanation: A request was made for drive, but no such drive could be found in the active configuration.



Recommended Action: Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration. Display the device configuration (using `tpconfig -d` or other means) to see the list of valid drives. Specify the drive name or index as appropriate for the interface being used.

Device Management Status Code: 24

Message: Requested drive could not be reserved

Explanation: An attempt was made to reserve a shared drive, but the drive reservation request failed. This status code is related to the internal implementation of the SSO feature, not SCSI Reserve/Release.

Recommended Action: This is an expected condition for shared drives which will be automatically retried. If problems persist, verify that `vmd/DA` is servicing requests and is not listing drives as reserved to hosts that are not currently using the drives. (`vmd/DA` is the Media Manager device daemon device allocator on UNIX and the NetBackup Device Manager service device allocator on Windows.) Clear out extraneous reservations by (re)starting `ltid` on the host that has the drive reservation. As an alternative, use `vmdareq -release` (plus other arguments) and then retry the request.

Device Management Status Code: 25

Message: File name does not exist

Explanation: A logical tape file or help file could not be found. The `tpunmount` command was probably issued with a logical tape file specified that does not exist for this user.

Recommended Action: Check for existence of the logical tape file at the file path specified. The specified file path must match the exact, case-sensitive path used when the tape mount was requested. Resubmit the request using the correct file path. If the condition is occurring during operator display of a pending request error message, check to see if the help files are properly installed at */usr/opensv/volmgr/help/robots/robot type/help file name* (UNIX) or at *install_path\Volmgr\Help\Robots\robot type\help file name* (Windows).

Device Management Status Code: 26

Message: Request terminated because host not validated for volume pool

Explanation: The host where the mount request was initiated has been denied access to the media due to permissions defined for the volume pool in which the media ID is contained.

Recommended Action:

1. Query the volume pool information for the requested volume pool on the host where the mount request was issued by running `vmppool -listall -b`. Obtain the name of the host from which the mount request originated by checking the system log. This host name is the one returned by the system `hostname(1)` command.
2. Change the volume pool host name security with `vmppool` or another user interface that supports volume pool host attributes, change the volume pool associated with the volume (if it is not assigned), or log in to the host that is allowed to use media in the targeted volume pool. Then, resubmit the mount request.

Device Management Status Code: 27

Message: Request terminated because media ID is expired

Explanation: A mount request has been canceled because the media was requested with write access, and the media has expired.

Recommended Action: Request read-only access to the media on the mount request if a read-only operation is needed. Replace the media or change the expiration date to a future date, based on site policy. A media management interface can be used to view and change the expiration date for the media. Check and correct the system date/time, as needed.

Device Management Status Code: 28

Message: Error in MsgGet

Explanation: An attempt was made by `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) to obtain a message queue identifier used for internal message communications, and the request failed due to a system error. The error probably indicates a lack of system resources for message queues, or mismatched software components.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use. Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 29

Message: Magic Number MisMatch



Explanation: An attempt was made to read the drive database, but it was found to be of an unknown format or version. The database is corrupt or there has been a mismatch of software components.

Recommended Action: Check integrity of the drive database file `ltidevs`, located in the directory `/usr/opensv/volmgr/database` (UNIX) or in the folder `install_path\Volmgr\database` (Windows). Display the device configuration to determine whether or not the database is corrupt, and restore a saved copy of the database file from catalog backups, or delete it and recreate the device configuration as needed.

Device Management Status Code: 30

Message: Request terminated because media id will exceed maximum mount count

Explanation: A mount request has been canceled because the media being requested has reached the maximum mount count associated with the media.

Recommended Action: Replace the media or change the maximum mount count to a higher value, based on site policy. A media management interface can be used to view and change the maximum mounts allowed for the media. Check that the number of mounts for the media is set to a reasonable value given the media's usage history, and correct it as needed using `vmchange`.

Device Management Status Code: 31

Message: Requested number of drives are not configured

Explanation: A tape mount request was submitted, and there are not enough drives in the configuration that match the requested density.

Recommended Action: Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration. Display the device configuration (using `tpconfig -d` or other means) to see the list of configured drives. Check the man page (command description) for `tpreq` to find the list of valid densities. Resubmit the mount request using a valid density that corresponds to a drive in the device configuration.

Device Management Status Code: 32

Message: Error in getting semaphore

Explanation: An attempt was made by `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) to obtain a semaphore used for arbitrating access to shared memory, and the request failed due to a system error. The error probably indicates a lack of system resources for semaphores, or mismatched software components.



Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting ltid (the device daemon on UNIX or NetBackup Device Manager service on Windows).
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use. Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 33

Message: Error in SEMAPHORE operation

Explanation: A process was unable to perform a semaphore operation (such as lock or unlock) associated with resources maintained by `ltid`. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 34

Message: Error in getting semaphore for operator

Explanation: A process was unable to perform a semaphore operation (such as lock or unlock) associated with resources maintained by `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows).

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Device Management Status Code: 35

Message: Request terminated because media is unavailable (in DOWN drive, misplaced, write protected or unmountable)

Explanation: A mount request has been canceled because the media being requested is not available. It may be in a DOWN drive, misplaced, write protected, or unmountable.

Recommended Action: Use robotic inventory or manual means to compare the contents of media in the robotic library with the volume configuration, and update the configuration as needed. Determine the physical location of the media. Check integrity of the drive, drive path, and media if the media is found in a logically DOWN drive. Verify that the media is not a misconfigured cleaning tape. Move the media into the robotic library and update the volume configuration if the media was not present in the library. Set the cartridge tab to allow write access, or request the media with read-only access if the write protection was the cause of the error.

Device Management Status Code: 36

Message: Request terminated by tpunmount call from another process

Explanation: A request was made to change the limit for the number of times that a volume can be mounted with write access for one or more volumes in the volume configuration, and the value specified was not within the acceptable range. The maximum number of mounts value may also be invalid in the number of mounts/cleanings field of a barcode rule.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Specify a maximum-mounts value within the range of 0 to 2,147,483,647.

Device Management Status Code: 37

Message: Drive being assigned is either not NDMP or on the wrong NDMP client

Explanation: A mount request has been canceled because of the following: the request was targeted to a drive configured as attached to an NDMP client, but the request was manually assigned to a drive other than the requested drive, and the assigned drive is either not NDMP or it is an NDMP drive configured to a different client.

Recommended Action: Display the device configuration to determine which drives are configured as being attached to specific NDMP clients. Ensure that `ltid` was stopped and restarted after the last configuration changes were made. Reissue the request and assign it to a drive attached to the requested NDMP client.

Device Management Status Code: 38

Message: Character device name for drive is not a character device

Explanation: On a tape mount request, the configured tape drive's no-rewind-on-close device file was neither a character-special device nor of a known type such as NDMP (which does not need to be a character special file). On an optical mount request, the optical disk drive character-device file was not a character-special device.

Recommended Action:

1. To avoid configuring invalid device paths and device names, use the Device Configuration wizard (on supported device discovery platforms) so that device paths and device names can be automatically configured for tape drives.
2. Refer to the appropriate chapter in the *NetBackup Device Configuration Guide*. Always use no-rewind tape device files, recommended character device files for optical devices, or recognized drive name syntax (such as for NDMP) for tape drives. Make sure that the specified device paths exist as character-special files. Check for detailed errors from the command or user interface output.



Device Management Status Code: 39

Message: Parameter is invalid

Explanation: The `tpclean` command was called with invalid arguments, or an internal function encountered a missing reference to data it requires.

Recommended Action:

1. If a cleaning operation was requested, check the `tpclean` usage statement and compare with the parameters that were specified.
2. Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 40

Message: File name already exists

Explanation: On a tape mount request, the file name associated with the request already existed or was already associated with another mount request.

Recommended Action: Resubmit the request using a different file name. Specify a file name that does not correspond to an existing file, or a file name that is not in use for another mount request that may be in progress.

Device Management Status Code: 41

Message: Unknown drive name

Explanation: A request was made for a specified drive, but no such drive could be found in the active configuration. This status may occur if the device files are corrupt or missing, if they cannot be opened or read, or if there are no devices configured.

Recommended Action:

1. Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration. Display the device configuration (using `tpconfig -d` or other means) to see the list of valid drives. Specify the drive name or index as appropriate for the interface being used.
2. Check integrity of the drive database file `ltidevs`, located in the directory `/usr/opensv/volmgr/database` (UNIX) or in the folder `install_path\Volmgr\database` (Windows). Display the device configuration to determine whether or not the database is corrupt, and restore a saved copy of the database file from catalog backups, or delete it and recreate the device configuration as needed.



Device Management Status Code: 42

Message: Incorrect tpreq access mode

Explanation: On a tape mount request, the specified access mode was invalid. On Windows hosts, a user without Administrator privileges made a request for NetBackup Device Manager services.

Recommended Action: When using `tpreq`, specify an access mode argument of `r` for read, `w` for write, or use the default (read) access mode. When making requests that require NetBackup Device Manager services on Windows, do so under an account with Administrator privileges.

Device Management Status Code: 43

Message: Drive is not a shared drive

Explanation: A shared drive (or SSO-related) request was made for a drive, but the drive was not a shared drive.

Recommended Action: Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration. Display the device configuration (using `tpconfig -d` or other means) to see the drive attributes. Ensure that a license key for the Shared Storage Option is installed and has not expired.

Device Management Status Code: 44

Message: You do not have permission to create the file

Explanation: On a tape mount request, the file name associated with the request could not be created due to directory or folder permissions.

Recommended Action: Check for existence of a file at the file path specified. If a file is found, delete the file if it is not needed or resubmit the request using a different file path. If there is no file at that location, check the directory/folder permissions for read/write access for the user or application process that issued the mount request.

Device Management Status Code: 45

Message: Drive is not currently reserved for this host

Explanation: On a request to release a shared drive, the drive was found to be not reserved to the local host. This status code is related to the internal implementation of the SSO feature, not SCSI Reserve/Release.



Recommended Action: If problems are encountered as a result of the reported error, verify that there are no unexpected robotic daemons/processes running by executing `vmops`. Stop and restart `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) so that its internal tables are re-initialized.

Device Management Status Code: 46

Message: Tape needs to be write enabled

Explanation: On a tape mount request, the specified access mode was for write access, but the physical media was write-protected.

Recommended Action: Change the physical media write-protect setting to allow write access (unlocked), or resubmit the request with read-only access. To request read-only access using `tpreq`, specify an access mode argument of `r` for read or use the default (read) access mode.

Device Management Status Code: 47

Message: Unable to establish scan host for shared drive

Explanation: On a request to change a shared drive's status, an attempt to establish a connection to the drive's scan host failed.

Recommended Action:

1. Determine which host is serving as the drive's scan host. Do this by sending a `vmddareq` command to the volume database host for the drive's residence (robot or set of standalone drives on a host).
2. Ensure that `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) is running on the scan host. On the scan host, examine debug logs and system logs for messages related to the error.
3. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows). The detailed reason for the canceled request should be available in the daemon debug logs on the scan host. Correct the problem and resubmit the request if needed.

Device Management Status Code: 48

Message: Host is not the scan host for this shared drive



Explanation: On a request to assign, reserve, or scan a drive, the targeted device host determined that it was not the scan host for the drive, so the request was refused (to be retried by the caller).

Recommended Action:

1. If problems are encountered as a result of the reported error, check for communication, configuration, and system problems among the associated hosts. Display the device configurations on the affected hosts to determine the role that each host is handling for drive sharing. Identify the DA (drive allocation) host as the volume database for the residence in which the drives are configured. Identify the current scan host for the drive by sending a `vmdatareq` call to the DA host.
2. Examine command output (if available), debug logs, and system logs for messages related to the error. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows). Configure scan ability priorities for assigning scan hosts by changing the Media Manager configuration, so that less network connections need to be maintained, and greater system load is placed on hosts more capable of servicing the load.

Device Management Status Code: 49

Message: Tape file path exceeds 255 character maximum

Explanation: On a tape mount request, the file name associated with the request exceeded 255 characters.

Recommended Action: When requesting a tape mount, ensure that the file name does not exceed 255 ASCII characters in length. If the mount requests are coming from an application, request an application change to use a shorter file name, or if needed, install the product in a directory/folder that will not cause the file name limit to be exceeded.

Device Management Status Code: 50

Message: No action pending for given mount index

Explanation: On a request to obtain the pending action for a mount request, there was no known pending action associated with the request.

Recommended Action: Use a device monitor interface to display requests that have pending actions. Perform requests (like assign, deny, display, or resubmit) only on requests that have pending actions.



Device Management Status Code: 51

Message: Frequency-based cleaning is not supported for this drive

Explanation: A request was made to set the cleaning frequency for a drive, and the configuration of the drive does not support frequency-based cleaning.

Recommended Action: See the Drive Cleaning section under the Media Manager Reference Topics appendix, in the *NetBackup Media Manager System Administrator's Guide*. Shared drives cannot be cleaned based on a frequency-based schedule. Cleaning for drives in ACS, LMF, RSM, and TLH robots is managed by vendor or operating system administrative interfaces for these types of robotic libraries. Drives in optical disk libraries cannot be cleaned using cleaning media.

Device Management Status Code: 52

Message: No robot is defined of this type

Explanation: On internal communications between a robotic daemon/process and `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows), no robots of the expected type were found actively configured.

Recommended Action: Display the running robotic processes to see if processes from a previous configuration are still running. If any are found, terminate them. Check the installed software components and verify that they are all at a compatible release version.

Device Management Status Code: 53

Message: Request has been queued (Cancel to clear message)

Explanation: A mount request or drive-related operation was queued because drive resources were in use.

Recommended Action: Wait until the drive resources become available, or cancel pending mount requests as needed.

Device Management Status Code: 54

Message: Block device name for optical disk is not a block device

Explanation: On an optical mount request, the configured optical disk drive block device file was not a block-special device.

Recommended Action: Refer to the appropriate chapter in the *NetBackup Device Configuration Guide*, use only the recommended device files for optical devices, and check to ensure that the specified device names exist as the type of special file required.



Device Management Status Code: 55

Message: Operator denied mount request

Explanation: The operator denied a mount request.

Recommended Action: This happens when a user or application mount request has been canceled by an administrator or operator. The request may have been canceled for a number of reasons, such as missing or faulty media or the need to allow other, higher priority requests to obtain drive resources. Check with the administrator or operator for more information.

Device Management Status Code: 56

Message: Mount canceled, device daemon is terminating

Explanation: Pending mount requests were canceled because the administrator terminated `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows).

Recommended Action: Wait for `ltid` to be restarted before resubmitting the request. Check with the administrator as needed to determine daemon/service availability.

Device Management Status Code: 57

Message: Cannot assign due to media ID mismatch

Explanation: An attempt was made to assign an optical disk request to a volume that contained a different recorded media ID than was requested.

Recommended Action: Refer to the `tpformat` man page to change recorded media IDs on optical platters.

Device Management Status Code: 58

Message: The device is not robotic, cannot perform cleaning

Explanation: An attempt was made to automatically clean a drive, but the drive is not in a robotic library.

Recommended Action: Clean standalone drives by inserting a cleaning tape when needed. For non-shared drives, update the cleaning statistics with `tpclean` or another user interface that supports cleaning-related operations.

Device Management Status Code: 59

Message: No cleaning tape is defined in the device's robot or 0 cleanings remaining

Explanation: An attempt was made to automatically clean a drive, but no usable cleaning media is available, or the number of cleanings remaining for the cleaning tape is zero.



Recommended Action:

1. Ensure that cleaning media has been added to the robotic library for each drive type capable of being cleaned with a separate cleaning cartridge.
2. Ensure there is a positive number of cleanings available for the cleaning media in the appropriate volume database for the robotic library. Replace the cleaning tape or increase the number of cleanings for the cleaning media before the count reaches zero.
3. Check the availability of `vmd` (the Media Manager volume daemon on UNIX or NetBackup Volume Manager service on Windows) on the volume database host where the cleaning media is defined, by sending a request to it or using a media management interface.
4. Examine command output (if available), debug logs, and system logs for messages related to the error. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the device daemon (`ltid`) on UNIX, or the NetBackup Device Manager service on Windows.

Device Management Status Code: 60

Message: No robot daemon or robotics are unavailable

Explanation: A robot was not configured or was operationally unavailable. Specifically, an attempt may have been made to automatically clean a robotic drive, but the robot is not defined or is unavailable. Alternatively, on an attempt to initialize the shared drive lists, a drive was found to be configured as robotic, without the required robot configured.

Recommended Action: Display the device configuration and ensure that the drive and robotic configuration information are consistent. Check the operational status of the robot and robotic software by checking the system log files. If more detail on robot operational status is needed, increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon / NetBackup Device Manager service).

Device Management Status Code: 61

Message: No media found in device or robot slot, please verify

Explanation: On a request to mount media, no media was found in the targeted location before a designated time period had elapsed.

Recommended Action: Resubmit the request, and mount the media in the targeted drive before the designated time period has elapsed. Check the device configuration to ensure that the correct drive name has been configured and that `ltid`, the device daemon, was restarted after the last device configuration change was made.



Device Management Status Code: 62

Message: Drive not available in library for mount request

Explanation: A mount request has been canceled because no drive is available. All compatible drives may be DOWN, or oversubscribed due to other active mount requests.

Recommended Action: Investigate device availability and scheduling/drive utilization of applications requesting drive resources. Under some conditions, mount requests will be canceled so that they can be reissued at a later time when compatible drive resources are available.

Device Management Status Code: 63

Message: Request terminated because mount requests are disabled

Explanation: A mount request was canceled because it cannot be satisfied.

Recommended Action: Examine command output (if available), debug logs, and system logs for messages related to the error. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).

The detailed reason for the canceled request should be available in the system log, command output, or from a device monitor interface. Correct the problem and resubmit the request if needed.

Device Management Status Code: 64

Message: Cannot assign a robotically controlled device

Explanation: An attempt was made to manually assign a specific device to satisfy a mount request, and the chosen device was configured in a robotic library.

Recommended Action: Assign the request to a standalone drive, or allow requests for mounts in robotic drives to be automatically assigned.

Device Management Status Code: 65

Message: Invalid volume pool specified

Explanation: On a mount request, the media pool specified was not valid.

Recommended Action: Resubmit the request, specifying a volume pool name that is no more than 20 ASCII characters in length.

Device Management Status Code: 66

Message: Request terminated because of volume pool mismatch



Explanation: The volume pool specified on the `tpreq` command did not match the volume pool specified in the Media Manager configuration for the media ID.

Recommended Action: Use a media management interface to obtain the volume pool name of the media that is to be mounted, and resubmit the mount request, specifying the correct pool name.

Device Management Status Code: 67

Message: Request terminated because user not validated for volume pool

Explanation: The user is not validated to use the media ID, because of permissions defined for the volume pool in which the media ID is contained.

Recommended Action: Query the volume pool information for the requested volume pool on the host where the mount request was issued by running `vmppool -listall -b`. Check the user ID (on UNIX) by executing the `id(1M)` system command. Change the volume pool user ID security with `vmppool` or another user interface that supports volume pool user and group attributes. Change the volume pool associated with the volume (if it is not assigned), or log in as the user ID with permissions to use media in the targeted volume pool. Then, resubmit the mount request.

Device Management Status Code: 68

Message: Request terminated because user/group not validated for volume pool

Explanation: The user or group is not validated to use the media ID because of permissions defined for the volume pool in which the media ID is contained.

Recommended Action: Query the volume pool information for the requested volume pool on the host where the mount request was issued by running the command `vmppool -listall -b`. Check the user ID and group ID (on UNIX) by executing the `id(1M)` system command. Change the volume pool user and/or group ID security with `vmppool` or another user interface that supports volume pool user and group attributes. Change the volume pool associated with the volume (if it is not assigned), or log in with user/group ID permissions to use media in the targeted volume pool. Then, resubmit the mount request.

Device Management Status Code: 69

Message: Request terminated because media is unmountable

Explanation: A mount request has been canceled because the media being requested is not mountable. The same media has been found to be unmountable in at least two different drives.

Recommended Action:



1. Check integrity of the drive, drive path, and media.
2. Verify that the media is not a misconfigured cleaning tape.

Device Management Status Code: 70

Message: Request terminated because media is write protected

Explanation: A mount request has been canceled because the media being requested for write access is not write-enabled.

Recommended Action: Check the physical media cartridge to see whether write-protection has been enabled. If write access to the media is desired, disable write protection for the media. If read-only access is desired, leave the write-protection enabled and make the necessary administrative requests in the requesting application (such as suspending the media) to ensure that the media is requested only for read access.

If the media was requested through the command line interface, see the `tpreq` man page or command description for specifying the access mode of the media. The `tpreq` command is described in the *NetBackup Media Manager System Administrator's Guide*.



Robotic Status Codes

These status codes are logged by robotic daemons/processes. They are also issued by programs that call the robotic operations, such as the `vmchange` command and the media and device management user interfaces.

Robotic Status Code: 200

Message: STATUS_SUCCESS

Explanation: A robotic operation was successfully completed.

Recommended Action: None.

Robotic Status Code: 201

Message: Unable to open robotic path

Explanation: The robotic library device could not be opened. The specific case could be one of the following.

- ◆ The robot device, path, or library name in the device configuration may not be valid.
- ◆ The configured robotic device may not exist.
- ◆ The robotic device may be incorrect, such as a UNIX device file that is not of a character special file format.
- ◆ The robotic daemon/process lock file could not be opened or a lock obtained.
- ◆ The open operation on the device or through the API interface (such as NDMP) failed.

Recommended Action:

1. Stop any robot test utilities that may be running, since they have the lock on the robotic device when they are active.
2. Check the configuration of the robot against the recommended configuration as indicated in the documentation for robot configuration.
3. Check the health of the robotic device by using a robot test utility, then close the test utility when finished.
4. Check for the existence and permissions of the lock file itself and the lock file directory, which is `/usr/opensv/volmgr/misc/vmd.lock` (UNIX) or `install_path\Volmgr\misc\vmd.lock` (Windows). Create the directory/folder and adjust the permissions as needed so that the robotic daemon/process can use the lock file. Stop and restart `ltid` (the device daemon on UNIX or the NetBackup Device Manager service on Windows).

Robotic Status Code: 202

Message: Unable to sense robotic device

Explanation: An element of the robotic library device could not be sensed. The cause could be any of the following.

- ◆ The SCSI commands mode sense, mode select, or read element status (of slot, drive, transport, i/e element) may have failed.
- ◆ A network API-controlled library inventory request may have failed.
- ◆ The robotic daemon/process could not initialize a robotic database file.

Recommended Action:

1. Check the configuration of the robot against the recommended configuration as indicated in the documentation for robot configuration.
2. Check the health of the robotic device by using a robot test utility, then close the test utility when finished.
3. Check for the existence and permissions of the temporary robotic database and the temporary database directory/folder, which is
/usr/opensv/volmgr/misc/robotic_db (UNIX) or
install_path\Volmgr\misc\robotic_db (Windows). Create the directory/folder and adjust the permissions as needed so that the robotic daemon/process can create it or use it. Stop and restart *ltid* (the device daemon on UNIX or the NetBackup Device Manager service on Windows).

Robotic Status Code: 203

Message: Timeout waiting for robotic command

Explanation: A robotic operation timed out: it did not return with a status before a designated time period had elapsed.

Recommended Action:

1. Stop any robot test utilities that may be running, since they have the lock on the robotic device when they are active, and can block other requests.
2. Check whether excessive hardware retries have delayed the completion of a robotic command.



3. Check to see whether the robotic device is still functioning. Use a robot test utility to send commands to the device to see whether it is responsive. Verify that there are no unexpected Media Manager processes running by executing `vmops`. Some processes are expected to remain running, but some processes that do not go away could indicate a more serious problem, such as a hung system call.

Robotic Status Code: 204

Message: Unable to initialize robot

Explanation: The robot could not be initialized. This is a generic status used for many conditions.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the robot initialization failure.

Robotic Status Code: 205

Message: Robotic mount failure

Explanation: The robot could not mount media.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.

2. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the media mount failure.

Robotic Status Code: 206

Message: Robotic dismount failure

Explanation: The robot could not dismount media.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the media dismount failure.

Robotic Status Code: 207

Message: Invalid command code

Explanation: A robotic operation was requested with improper options, when it was not supported, or a robotic operation encountered an incompatible device interface. There may be an incompatibility between components or versions of the product.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that all Media Manager binaries and user interfaces are at a compatible version level.



Robotic Status Code: 208

Message: Requested slot is empty

Explanation: No media was found in a specified slot. The volume configuration may not be consistent with the physical contents of the robotic library that is associated with the volume.

Recommended Action: Install or realign the container/holder for the media if it was missing or misaligned. Place media right-side-up in the slot if the media is upside-down. Check to see if the requested slot is reserved to the robotic library for internal use. Physically correct issues within the robotic library, or use a media management interface to correct the volume configuration.

Robotic Status Code: 209

Message: Unable to open drive

Explanation: The drive could not be opened. The drive configuration may be incorrect and the drive may be logically DOWN. Also, the drive may never have become ready after media was placed in the drive.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Check for improperly configured cleaning media or interference with the drive cleaning operation. Check for bad media which may have led to the drive not becoming ready after media was placed within it.
3. To avoid configuring incorrect device paths and device names, which is a common root cause of drive open problems, use the Device Configuration wizard (on supported device discovery platforms) so that device paths and device names can be automatically configured. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the open failure.



Robotic Status Code: 210

Message: Unable to SCSI unload drive

Explanation: The drive could not be unloaded. The drive configuration may be incorrect and the drive may be logically DOWN. Also, the drive may never have become ready after media was placed in the drive.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Check for improperly configured cleaning media or interference with the drive cleaning operation. Check for bad media which may have led to the drive not being able to be unloaded. To avoid configuring incorrect device paths and device names, which is a common root cause of drive unload problems, use the Device Configuration wizard (on supported device discovery platforms) so that device paths and device names can be automatically configured. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the unload failure.

Robotic Status Code: 211

Message: Process killed by signal

Explanation: A robotic operation was canceled by an unexpected signal or event.

Recommended Action:

1. Examine system and debug logs for a more detailed message error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services.
 - b. Retry the operation and examine the logs. Ensure that the robotic process is allowed to fully complete.



2. Check vendor or operating system administrative interfaces and logs to see if robotic commands are being canceled.

Robotic Status Code: 212

Message: Process killed by parent

Explanation: A robotic operation was canceled because it either did not return with a status before a designated time period had elapsed, or communications/hardware errors led to the need to reinitialize the device.

Recommended Action:

1. Stop any robot test utilities that may be running, since they have the lock on the robotic device when they are active, and can block other requests.
2. Check to see whether the robotic device is still functioning.
3. Check whether excessive hardware or communication problems have delayed the completion of a robotic command.
4. Use a robot test utility to send commands to the device to see whether it is responsive. Verify that there are no unexpected Media Manager processes running by executing `vmmps`. Some processes are expected to remain running, but some processes that do not go away could indicate a more serious problem, such as a hung system call.

Robotic Status Code: 213

Message: Drive does not exist in robot

Explanation: A targeted drive was not found in the robotic library. The drive configuration may be incorrect.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.



2. Attempt to obtain the list of drives using a method that involves a robotic library query, such as that available from the robot test utility. Compare the list of drives returned against the device configuration. Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration.

Robotic Status Code: 214

Message: Robot number does not exist

Explanation: A targeted robotic library was not found in the active device configuration.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Ensure that `ltid` (the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows) was stopped and restarted after changes were last made to the device configuration. When issuing commands to robotic libraries, specify only robotic libraries that are actively part of the device configuration.

Robotic Status Code: 215

Message: Requested tape in other or non-configured drive

Explanation: The targeted media was found in a drive differing from the targeted drive.

It is normal for requested media to be temporarily unavailable. Also, media can remain unavailable until administrator or operator action is taken.

Recommended Action:

1. If the media is needed immediately, examine command output (if available), debug logs, and system logs for messages relating to the targeted media.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Check for conflicts between multiple applications using media in the robotic library. Check integrity of the drive and drive paths, so that media is not routinely left in other drives.

Robotic Status Code: 216

Message: Door is open on cabinet

Explanation: The robotic library door was open.

Recommended Action: Close the door of the robotic library and reissue the robotic request. Check to see if the door latch mechanism is working by comparing what happens with robot test utility commands when the door is opened versus when it is closed.

Robotic Status Code: 217

Message: Requested slot already has cartridge

Explanation: The requested slot was already held or was associated with a cartridge.

Recommended Action: Ensure that the inject/eject request does not target a slot that already contains media. Check for media in drives to ensure that the media's home slot location is not being targeted for use with media to be injected.

Robotic Status Code: 218

Message: Cannot move from media access port to slot

Explanation: A robotic inject media operation returned a status indicating that an inject failure occurred.

Recommended Action:

1. Check to see whether the robotic library has a media access port. Use the robot test utility to validate this. Investigate whether the administrator or operator has canceled the inject operation. Ensure that inject for LMF robot types is done only on the LMF server.
2. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.

Robotic Status Code: 219

Message: Cannot move from slot to media access port

Explanation: A robotic eject media operation returned a status indicating that an eject failure occurred.

Recommended Action:

1. Check to see whether the robotic library has a media access port. Use the robot test utility to validate this. Investigate whether the administrator or operator has canceled the eject operation. Ensure that eject for LMF robot types is done only on the LMF server. When ejecting RSM media, ensure that the device is available, and that media is available in the NetBackup media pool.
2. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.

Robotic Status Code: 220

Message: Media access port does not contain media



Explanation: A robotic inject media operation returned a status indicating that the media access port does not contain any cartridges/media. The operator or administrator may not have placed media into the media access port for inject.

Recommended Action:

1. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows). Retry the operation and examine the logs.
2. Coordinate inject/eject operations between all operators and administrators.

Robotic Status Code: 221

Message: Media access port already contains media

Explanation: A robotic eject media operation returned a status indicating that the media access port contains one or more cartridges. The operator or administrator may not have removed media from the media access port as part of the latest (or a previous) eject operation.

Recommended Action:

1. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows). Retry the operation and examine the logs.
2. Coordinate inject/eject operations between all operators and administrators. Ensure the media access port is empty of media before starting an eject operation.

Robotic Status Code: 222

Message: Robotic arm has no addressable holder

Explanation: An element of the robot is missing a holder and cannot be used.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Investigate the state of the physical hardware and correct the holder status for storage, drive, and transport elements as needed. Then, resubmit the request.

Robotic Status Code: 223

Message: Robot busy, cannot perform operation

Explanation: The robot is busy performing another operation, using resources needed for the requested operation.

Recommended Action: Wait until the robot is done performing current external-based requests (including robot inventory and inject/eject media) before starting new requests. Check vendor or operating system administrative interfaces and logs to see if robotic resources are busy.

Robotic Status Code: 224

Message: Control daemon connect or protocol error

Explanation: A protocol error occurred between robotic and other components.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the media mount failure. Verify that all Media Manager binaries are at a compatible version level.



3. Verify that robotic interfaces to vendor and operating system software have compatible versions.

Robotic Status Code: 225

Message: Robot hardware or communication error

Explanation: A hardware or communications error occurred between robotic and other components.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Resolve the situation by referring to troubleshooting methods or investigating the system log messages related to the specific error leading to the media mount failure.
3. Verify that all Media Manager binaries are at a compatible version level. Verify that robotic interfaces to vendor and operating system hardware and software have compatible versions.

Robotic Status Code: 226

Message: Requested slot contains the wrong tape

Explanation: The media in the requested slot is different from the media expected in that slot. The volume configuration is not consistent with the physical contents of the robotic library that is associated with the slot associated with the requested volume.

Recommended Action: The volume configuration or media placement in the robotic library needs to be adjusted using one of the media management interfaces. Determine whether the barcode has changed or whether the media has been changed since the last time the volume database was reconciled for the affected slot. If only the barcode has changed but not the media, issue an update barcode request for each affected volume. If the media has been changed, use a media management interface to run robot inventory update, which will update the volume database to reflect the physical location of the media.



Robotic Status Code: 227

Message: FASTRAX unable to process clean request

Explanation: After a cleaning tape is mounted on a Fastrax-attached drive, control is passed to the Fastrax system which determines when the cleaning has completed. This error is reported when the Fastrax system detects an error while processing the clean request.

Recommended Action: Examine the Symmetrix logs located in the `/usr/emc/API/symapi/log` directory. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX). Verify that a cleaning tape was mounted to the specified Fastrax drive.

Robotic Status Code: 228

Message: Requested slot does not exist in robot

Explanation: The slot associated with a request is not valid for the robot.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Issue a robot inventory Contents report to determine the valid slot range for the robot. Check the volume configuration to ensure that only valid slots are referenced in volume records, paying particular attention to the starting and ending slot numbers. Update the volume configuration as needed, or request only valid slot ranges for robotic operations.

Robotic Status Code: 229

Message: Requested operation is not supported by the robot

Explanation: A robotic operation was sent to a robotic component that did not support that operation, or options requested for the operation were not supported. There may be an incompatibility between components or versions of the product.

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for a more detailed message on the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the VERBOSE option in the vm.conf file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. Verify that all Media Manager binaries and user interfaces are at a compatible version level.

Robotic Status Code: 230

Message: System error occurred during robot operation

Explanation: A robotic operation encountered a system error. This status code is used for generic system call failures within robotic daemons/processes.

Recommended Action:

1. Check for other error messages in the command or interface output to indicate which system call failed. Enable debug logging, retry the operation, and check the debug log files for more specific error messages.
2. Check the system application log for error and warning messages.
3. Verify that the system is not running out of virtual memory. If virtual memory is the problem, shut down unused applications or increase the amount of virtual memory. To increase virtual memory on Windows: display the Control Panel, double-click System, and on the Performance tab, set Virtual Memory to a higher value.
4. Verify that all product binaries are properly installed.
5. Verify that there are no unexpected Media Manager processes running by executing `vmmps`. Some processes are expected to remain running, but some processes that do not go away could indicate a more serious problem, such as a hung system call.

Robotic Status Code: 232

Message: Volume not found in library

Explanation: The requested media was not found in the robotic library. The media has been ejected or become inaccessible for some other reason.

Recommended Action:



1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows).
 - b. Retry the operation and examine the logs.
2. Issue a robot inventory Contents report to obtain the list of media in the robotic library. Check to see whether inventory filters have been enabled in the Media Manager configuration file, since they affect the contents of the media list returned from the robotic daemon/process. Use a robot test utility or an operating system/vendor administrative interface to verify the status of media, as needed. Update the volume configuration and search for the media if it was not in the robotic library, as needed, and resubmit the request.

Robotic Status Code: 233

Message: Volume is in library, but not in drive domain

Explanation: The media was found in the robotic library, in a domain of the library that is inaccessible to the drives that are configured in the robot.

Recommended Action: Issue a robot inventory Contents report to obtain the list of media in the robotic library. Check the device configuration and ensure that the drive addresses correspond to the correct domain for the media. Correct the device configuration as needed and restart `ltid` (the device daemon on UNIX or NetBackup Device Manager service on Windows). Use a robot test utility or a vendor administrative interface to verify the status of media, as needed. Update the volume configuration and physically move the media into the robotic library, as needed, and resubmit the request.

Robotic Status Code: 234

Message: Robot denied access to the resource

Explanation: The media was found in the robotic library, but is being denied access according to an established security policy.

Recommended Action: Issue a robot inventory Contents report to obtain the list of media in the robotic library. Use a vendor administrative interface to verify the status of media, as needed. Delete the media in the volume configuration, or make the volume accessible through a vendor administrative interface, as appropriate. Update the volume configuration, as needed, and resubmit the request.



Robotic Status Code: 235

Message: barcode label is unreadable

Explanation: The media was found in the robotic library, but it has an unreadable barcode label.

Recommended Action: Use the robot test utility or a vendor administrative interface to verify the status of media. Correct the label or replace the media as appropriate. Update the volume configuration, as needed, and resubmit the request.

Robotic Status Code: 236

Message: Robot has misplaced the media

Explanation: The requested media was known according to the vendor software managing the robotic library, but the media has been misplaced.

Recommended Action: Use a robot test utility or a vendor administrative interface to verify the status of media. Search for the media inside the robotic library. Update the volume configuration and search for the media if it was not in the robotic library, as needed, and resubmit the request.

Robotic Status Code: 237

Message: Volume is in use

Explanation: The media was in use.

Recommended Action: Use the robot test utility or a vendor administrative interface to verify the status of media. Determine what applications may be using the media. Dismount the media if it is not being used by an application. Wait for the media to become available, as needed.

Robotic Status Code: 238

Message: Requested drive is in an offline domain

Explanation: The drive targeted for a mount request was in a robotic library domain that is offline.

Recommended Action: Bring the robotic library domain (ACS Library Storage Module) back online, or postpone use of drives in that domain until the domain can be brought back online.

Robotic Status Code: 239

Message: Requested volume is in an offline domain



Explanation: The volume targeted for a mount request was in a robotic library domain that is in the offline or offline pending state.

Recommended Action: Bring the robotic library domain (ACS Library Storage Module) back online, or postpone use of media in that domain until the domain can be brought back online.

Robotic Status Code: 240

Message: A memory allocation attempt failed in the robotic daemon

Explanation: An attempt by the robotic control daemon to allocate memory has failed. This may indicate serious memory problems on your media server.

Recommended Action: Stop all NetBackup Media Manager daemons. Consult the documentation for your operating system memory management tools to determine what remaining process is leaking memory, and stop that process. Restart the NetBackup Media Manager daemons. Free up memory by terminating unneeded processes that consume a lot of memory. Add more swap space or physical memory if necessary.

Robotic Status Code: 241

Message: An error occurred accessing the RSM api

Explanation: A failure occurred in a call to the Removable Storage Manager application programming interface.

Recommended Action: Use the robot test utility or the operating system administrative interface to check the status of robotic libraries and media. Resolve the problem according to troubleshooting techniques recommended by Removable Storage Manager documentation.

Robotic Status Code: 242

Message: Robot media access port does not exist

Explanation: the requested media access port was not valid for use with the targeted media.

Recommended Action: Use the robot test utility or a vendor administrative interface to verify the media access port address based on the location of the media. Choose a media access port that is valid, or let one be automatically selected, and retry the robotic operation.

Robotic Status Code: 243

Message: Cannot open/create the media access port status file



Explanation: A robotic daemon/process could not create or open a status file in the database directory/folder.

Recommended Action: Investigate why the robot status file in the directory `/usr/opensv/volmgr/database` (UNIX) or folder `install_path\Volmgr\database` (Windows) cannot be created or opened. On Windows, check which account the NetBackup Device Manager service (and thus the robotic process) is running under and compare it against the security properties of the database folder.

Robotic Status Code: 244

Message: The eject command was aborted by the user

Explanation: An administrator or operator canceled an eject media request.

Recommended Action: This happens when an eject request has been canceled by an administrator or operator. The request may have been canceled for a number of reasons, such as missing or faulty media, the need to allow the media access port to be used for other requests, or the desire to perform the operation at a later time. Check with the administrator or operator for more information.

Robotic Status Code: 245

Message: Physical drive is not available

Explanation: A robotic mount operation could not be completed because physical drive resources are not available for the request. This is probably the result of operating in an environment based on virtualized resources, such as one involving the Storagenet 6000 Storage Domain Manager (SN6000).

The SN6000 virtualizes tape drives. Some configurations of the SN6000 may involve a different number of logical drives as compared to the number of physical drives (or equivalent resources) available for satisfying the requests for drive resources. Also, the relationship between the number of logical drives and physical drives may change as hardware failures occur. NetBackup scheduling, drive allocation, and drive assignment algorithms can only determine logical drive availability; NetBackup attempts to fully utilize all configured and available logical drives. If the number of logical drives being utilized exceeds the number of physical drives available, a NetBackup job may be started when insufficient drive resources are available for the job. Instead of queueing the job in the scheduler, the job runs and does not encounter the resource issue until the time it makes an ACS tape mount request.

Recommended Action:

1. Install the Shared Storage Option (SSO) license for mount requests to requeue when physical drive resources are not available.
2. Since there is a fixed limit for the number of drives that can be in use at any one time, optionally configure backup windows so the different storage units tied to the same physical drives are active only at non-overlapping times. Also, raise (or set to infinite) the media mount timeout to avoid job failures when the job cannot get a physical drive due to the drives all being busy.

Robotic Status Code: 246

Message: Failed to find an available slot to inject to

Explanation: An attempt to inject a volume into a full library failed. This should only occur when the library is full, meaning that all storage elements either contain media or have been assigned media that is currently mounted in a drive. Note that some libraries that support multiple media types restrict which type of media can be assigned to each storage element. In this case, this error might occur even if some of the storage elements in a library were not full. Since the empty storage elements may not match the media type for the media you are trying to inject, the library is full for this media type.

Recommended Action: Clear the media access port, then re-inventory the robot by doing a volume configuration update.

Robotic Status Code: 248

Message: Cannot recover aborted eject with this type of media access port

Explanation: An eject failed from a robot with a media access port that does not allow automatic recovery of media.

Recommended Action: Manually remove any media remaining in the robot's media access port, then re-inventory the robot to ensure that NetBackup's volume database matches what is in the library. You can also use the robot's utilities or the NetBackup `robtest` utility to move the media from the robot's media access port back to robotic storage elements. In any case, re-inventory the robot to ensure that the NetBackup volume database matches what is in the robot.

Robotic Status Code: 249

Message: Volume is in home slot

Explanation: Volume is currently in its home slot and ready for eject.

Recommended Action: None.

Robotic Status Code: 250

Message: Media access port is available

Explanation: Media access port is available for inject or eject.

Recommended Action: Begin inject or eject operation.

Robotic Status Code: 251

Message: Media access port is unavailable

Explanation: Media access port is not ready for inject or eject.

Recommended Action: Manually remove any media remaining in the robot's media access port. If this status persists, check robotic console for errors.

Robotic Status Code: 252

Message: Media access port is in inject mode

Explanation: Media access port is ready to inject and is not available for eject.

Recommended Action: Complete inject operation.

Robotic Status Code: 253

Message: Media access port is in eject mode

Explanation: Media access port is ready to eject and is not available for inject.

Recommended Action: Complete eject operation.

Robotic Error Codes

These status codes are returned if a robotic daemon/process was started from the command line and an error occurs. For example, if the administrator executes the following:

```
/usr/openv/volmgr/bin/tl8d
```

and no robots are configured, the following may be returned:

```
TL8: No robots are configured
```

These status codes are also logged to the system log.

Usually, robotic daemons/processes are not started from the command line, but are started automatically, as needed, when `ltid` starts.

Robot Error Status Code: 1

Message: You must be ROOT to start daemon

Explanation: A robotic daemon was started by a user other than root. This applies to UNIX systems only.

Recommended Action: Log on as the root user before starting robotic daemons. Allow robotic daemons to be started automatically as needed by `ltid` (the device daemon).

Robot Error Status Code: 2

Message: LTI Daemon may not be running

Explanation: On an attempt to start a robotic daemon/process, an attempt to connect to the `ltid` message queue failed, indicating that `ltid` (the device daemon / NetBackup Device Manager service), may not be running.

Recommended Action:

1. Start `ltid` so that shared memory can be initialized, allowing the robotic daemon/process to function.
2. If problems persist, examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.



3. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Robot Error Status Code: 3

Message: Error in getting shared memory

Explanation: A robotic daemon/process was unable to get a shared memory identifier associated with a segment of shared memory that `ltid` maintains. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Robot Error Status Code: 4

Message: Error in attaching the shared memory

Explanation: A robotic daemon/process was unable to attach a shared memory segment that `ltid` maintains. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting `ltid`.
 - b. Retry the operation and examine the logs.



2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Robot Error Status Code: 5

Message: Error in getting process Id

Explanation: A robotic daemon/process was unable to obtain its own process identifier due to a system call failure.

Recommended Action: Investigate operating system functionality regarding a process obtaining its own process identifier.

Robot Error Status Code: 6

Message: No devices are configured on the robot

Explanation: A robotic daemon/process was started, but no drives are configured for the robot.

Recommended Action: Some robotic daemons/processes will not run if there are no drives configured for them to manage. Add or reconfigure one or more drives to be in the associated robot. Then, stop and restart `ltid` (the Media Manager device daemon on UNIX or NetBackup Device Manager service on Windows).

Robot Error Status Code: 7

Message: No robots are configured

Explanation: A robotic daemon/process was started, but no robots of the associated robot type are configured.

Recommended Action: Robotic daemons/processes will not run if there are no robots configured for the associated robot type. Add or reconfigure one or more robots, then stop and restart `ltid` (the Media Manager device daemon on UNIX or NetBackup Device Manager service on Windows).

Robot Error Status Code: 8

Message: No memory available

Explanation: A robotic daemon/process was unable to allocate memory. This error occurs when there is insufficient system memory available. This could be caused by the system being overloaded with too many processes and there is not enough physical and virtual memory.

Recommended Action: Free up memory by terminating unneeded processes. Add more swap space or physical memory.



Robot Error Status Code: 9

Message: Error in SEMAPHORE operation

Explanation: A process was unable to perform a semaphore operation (such as lock or unlock) associated with resources maintained by `ltid`. (`ltid` is the Media Manager device daemon on UNIX or the NetBackup Device Manager service on Windows.)

Recommended Action:

1. Examine command output (if available), debug logs, and system logs for messages related to the error.
 - a. Enable debug logging by creating the necessary directories/folders. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file and restarting the daemons/services, or execute the command's verbose option, if available.
 - b. Retry the operation and examine the logs.
2. On UNIX servers, gather the output of the `ipcs -a` command to see what resources are currently in use.

Robot Error Status Code: 10

Message: Fork failure occurred

Explanation: A robotic daemon/process could not create a child process due to a system error. This is probably an intermittent error based on the availability of resources on the system. (This applies to UNIX servers only.)

Recommended Action:

1. Restart the device daemon at a later time and investigate system problems that limit the number of processes.
2. Examine the system logs for a more detailed message on the error. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file. Restart the device daemon, then retry the operation and examine the system log file.

Robot Error Status Code: 11

Message: System error occurred

Explanation: A robotic daemon/process encountered a system error.



Recommended Action: Examine the system log for a more detailed message on the error. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file. Restart the device daemon `ltid` (UNIX) or NetBackup Device Manager service (Windows), then retry the operation and examine the system log file.

Robot Error Status Code: 12

Message: Usage error in creating child process

Explanation: A robotic daemon/process could not create a child process due to an incompatibility between robotic software components.

Recommended Action:

1. Examine system logs for a more detailed message on the error.
 - a. Increase the level of verbosity by adding the `VERBOSE` option in the `vm.conf` file. Restart the `ltid` device daemon (UNIX) or NetBackup Device Manager service.
 - b. Retry the operation and examine the system log file.
2. Verify that all Media Manager binaries are at a compatible version level.

Robot Error Status Code: 14

Message: You must be administrator to execute

Explanation: A robotic process was started under a user account that was lacking Administrator privileges. This applies to Windows systems only.

Recommended Action: Allow robotic daemons to be started automatically as needed by the NetBackup Device Manager service. Ensure that this service is being started from a user account with administrator privilege.

Robot Error Status Code: 16

Message: Devices located in multiple domains

Explanation: A robotic daemon/process encountered an invalid device configuration, in which drives from different domains were configured to be controlled by a single logical robot.

Recommended Action: Display the device configuration using `tpconfig -d` or a device configuration interface to see the robotic and drive information that is already configured. Ensure that the drive addresses do not span physical domains. Drives can only be



Messages

configured in the same robot if they can be used with media from a single domain, where the domain includes a single physical library or multiple libraries connected by a cartridge exchange or pass-through mechanism.

Robot Error Status Code: 17

Message: Robotic daemon not licensed

Explanation: A robotic daemon/process was started without the required, current product license, or a required database file was missing or corrupt.

Recommended Action:

1. Check product documentation for supported device configurations.
2. Obtain an additional software license that allows robots of the associated robot type to be configured, or limit the configuration to robot types allowed by the current licensing. Check for the existence and permissions of the `external_robotics.txt` file in the `/usr/opensv/share` directory (UNIX) or in the `install_path\NetBackup\share` folder (Windows).

Messages

This section lists Media Manager messages alphabetically. The status code type and number are included in parentheses after the message. Refer to the appropriate section in this chapter (such as “Media Manager Status Codes,” “Device Configuration Status Codes,” and so forth) for the status code with explanation and recommended action.

<NONE>

(Device Configuration Status Code 36)

A memory allocation attempt failed in the robotic daemon

(Robotic Status Code 240)

a scratch pool is already defined

(Media Manager Status Code 171)

A SCSI inquiry sent to the device has failed

(Device Configuration Status Code 16)



ADAMM GUID does not exist in database

(Media Manager Status Code 168)

ADAMM GUID is not unique in the database

(Media Manager Status Code 167)

Adding this device would exceed the maximum allowed

(Device Configuration Status Code 40)

Adding this drive would exceed the maximum allowed

(Device Configuration Status Code 39)

all available pool numbers are in use

(Media Manager Status Code 103)

all available rule numbers are in use

(Media Manager Status Code 120)

An error occurred accessing the RSM api

(Robotic Status Code 241)

another daemon already exists

(Media Manager Status Code 89)

barcode does not exist in database

(Media Manager Status Code 78)

barcode label is unreadable

(Robotic Status Code 235)

barcode not unique in database

(Media Manager Status Code 36)



barcode tag is not unique in rule database

(Media Manager Status Code 122)

Block device name for optical disk is not a block device

(Device Management Status Code 54)

cannot allocate requested memory

(Media Manager Status Code 18)

Cannot assign a robotically controlled device

(Device Management Status Code 64)

Cannot assign due to media ID mismatch

(Device Management Status Code 57)

cannot auto-eject this robot type

(Media Manager Status Code 51)

cannot auto-inject this robot type

(Media Manager Status Code 52)

Cannot backup/restore global device database files

(Device Configuration Status Code 47)

Cannot backup/restore local device database files

(Device Configuration Status Code 43)

Cannot change terminal mode

(Device Configuration Status Code 41)

cannot change volume pool for assigned volume

(Media Manager Status Code 91)

cannot connect to robotic software daemon

(Media Manager Status Code 42)

cannot connect to vmd [on host *host name*]

(Media Manager Status Code 70)

Cannot create miscellaneous working repository

(Device Configuration Status Code 42)

cannot delete assigned volume

(Media Manager Status Code 92)

cannot delete one of the default volume pools

(Media Manager Status Code 118)

Cannot discover devices. See the Troubleshooting Guide for details.

(Device Configuration Status Code 44)

Cannot execute command, permission denied

(Device Configuration Status Code 1)

cannot get host name

(Media Manager Status Code 76)

Cannot move from media access port to slot

(Robotic Status Code 218)

Cannot move from slot to media access port

(Robotic Status Code 219)

cannot obtain daemon lockfile

(Media Manager Status Code 21)



Cannot open/create the media access port status file

(Robotic Status Code 243)

cannot perform operation on this host

(Media Manager Status Code 60)

Cannot recover aborted eject with this type of media access port

(Robotic Status Code 248)

Cannot stop device daemon with tapes assigned

(Device Management Status Code 20)

Cannot synchronize global device database

(Device Configuration Status Code 5)

Character device name for optical disk is not a character device

(Device Management Status Code 38)

child process killed by signal

(Media Manager Status Code 63)

Control daemon connect or protocol error

(Robotic Status Code 224)

Current version does not support remote device host

(Device Configuration Status Code 38)

current version does not support this configuration

(Media Manager Status Code 149)

daemon cannot obtain socket

(Media Manager Status Code 58)

daemon failed accepting connection

(Media Manager Status Code 59)

daemon resources are busy

(Media Manager Status Code 5)

daemon terminated

(Media Manager Status Code 7)

database already open

(Media Manager Status Code 24)

database close operation failed

(Media Manager Status Code 23)

database initialization failed

(Media Manager Status Code 22)

database lock operation failed

(Media Manager Status Code 29)

database open operation failed

(Media Manager Status Code 26)

database read operation read too few bytes

(Media Manager Status Code 28)

database read record operation failed

(Media Manager Status Code 27)

database seek operation failed

(Media Manager Status Code 30)



database unlock operation failed

(Media Manager Status Code 31)

database write operation wrote too few bytes

(Media Manager Status Code 33)

database write record operation failed

(Media Manager Status Code 32)

Device Configuration was not upgraded

(Device Configuration Status Code 50)

device entry is not unique in global device database

(Media Manager Status Code 153)

Device path is already in use

(Device Configuration Status Code 22)

Devices located in multiple domains

(Robot Error Status Code 16)

Door is open on cabinet

(Robotic Status Code 216)

Drive being assigned is either not NDMP or on the wrong NDMP client

(Device Management Status Code 37)

Drive does not exist in robot

(Robotic Status Code 213)

Drive does not support pending request density

(Device Management Status Code 17)

Drive index is in use by another drive

(Device Configuration Status Code 29)

Drive is currently assigned

(Device Management Status Code 2)

Drive is currently reserved

(Device Management Status Code 9)

Drive is not a shared drive

(Device Management Status Code 43)

Drive is not currently reserved for this host

(Device Management Status Code 45)

Drive name does not exist

(Device Configuration Status Code 35)

Drive name is already in use by another drive

(Device Configuration Status Code 34)

Drive not available in library for mount request

(Device Management Status Code 62)

Duplicate device path names

(Device Configuration Status Code 20)

error auto-generating volume group

(Media Manager Status Code 57)

Error in attaching the shared memory

(Robot Error Status Code 4)



Error in getting process Id

(Robot Error Status Code 5)

Error in getting semaphore for operator

(Device Management Status Code 34)

Error in getting semaphore

(Device Management Status Code 32)

Error in getting shared memory

(Robot Error Status Code 3)

Error in IPC SHMAT call

(Device Management Status Code 14)

Error in IPC SHMGET call

(Device Management Status Code 13)

Error in MsgGet

(Device Management Status Code 28)

Error in Receiving Daemon Message

(Device Management Status Code 6)

Error in Receiving Operator Message

(Device Management Status Code 4)

Error in Receiving User Message

(Device Management Status Code 8)

Error in SEMAPHORE operation

(Device Management Status Code 33)

Error in SEMAPHORE operation

(Robotic Error Status Code 9)

Error in Sending Daemon Message

(Device Management Status Code 5)

Error in Sending Operator Message

(Device Management Status Code 3)

Error in Sending User Message

(Device Management Status Code 7)

Evaluation period expired. Go to www.veritas.com to order this product.

(Media Manager Status Code 165)

failed appending to pool database

(Media Manager Status Code 104)

failed appending to rule database

(Media Manager Status Code 121)

failed changing terminal characteristics

(Media Manager Status Code 45)

failed during tpformat

(Media Manager Status Code 77)

failed initiating child process

(Media Manager Status Code 88)

failed making the database directory

(Media Manager Status Code 25)



failed opening tmp output file

(Media Manager Status Code 86)

Failed reading drive or robot config file

(Device Configuration Status Code 13)

failed receiving from robotic software daemon

(Media Manager Status Code 44)

failed receiving from vmd

(Media Manager Status Code 72)

failed redirecting input to pipe

(Media Manager Status Code 62)

failed redirecting tmp output file

(Media Manager Status Code 87)

failed sending request to vmd

(Media Manager Status Code 69)

failed sending to robotic software daemon

(Media Manager Status Code 43)

failed sending to vmd

(Media Manager Status Code 71)

Failed to find an available slot to inject to

(Robotic Status Code 246)

Failed writing drive or robot config file

(Device Configuration Status Code 12)

FASTRAX unable to process clean request

(Robotic Status Code 227)

File name already exists

(Device Management Status Code 40)

File name does not exist

(Device Management Status Code 25)

Fork failure occurred

(Robot Error Status Code 10)

Frequency-based cleaning is not supported for this drive

(Device Management Status Code 51)

global device database append operation failed

(Media Manager Status Code 155)

global device database close operation failed

(Media Manager Status Code 158)

global device database lock operation failed

(Media Manager Status Code 156)

global device database open operation failed

(Media Manager Status Code 157)

global device database record not found

(Media Manager Status Code 152)

global device database truncate operation failed

(Media Manager Status Code 154)



group is not valid for this host

(Media Manager Status Code 128)

Host is not the scan host for this shared drive

(Device Management Status Code 48)

incompatible database version

(Media Manager Status Code 146)

Incomplete robot information

(Device Configuration Status Code 24)

Incorrect tpreq access mode

(Device Management Status Code 42)

invalid barcode

(Media Manager Status Code 10)

invalid change type

(Media Manager Status Code 75)

invalid change-entry request

(Media Manager Status Code 50)

Invalid command code

(Robotic Status Code 207)

invalid command usage

(Media Manager Status Code 4)

invalid database version header

(Media Manager Status Code 56)

invalid description

(Media Manager Status Code 11)

Invalid device path name

(Device Configuration Status Code 19)

Invalid drive index

(Device Configuration Status Code 14)

invalid drive name

(Media Manager Status Code 129)

Invalid Drive Number

(Device Management Status Code 23)

Invalid drive type for the robot

(Device Configuration Status Code 27)

Invalid Drive Type/Density

(Device Management Status Code 1)

invalid expiration date

(Media Manager Status Code 113)

invalid global device database entry

(Media Manager Status Code 151)

invalid host name

(Media Manager Status Code 136)

invalid maximum mounts

(Media Manager Status Code 114)



Messages

invalid media generation rule

(Media Manager Status Code 140)

invalid media ID for naming mode

(Media Manager Status Code 41)

invalid media ID

(Media Manager Status Code 8)

invalid media type

(Media Manager Status Code 9)

invalid number of cleanings

(Media Manager Status Code 74)

invalid number of mounts

(Media Manager Status Code 141)

invalid offsite location

(Media Manager Status Code 142)

invalid offsite return date

(Media Manager Status Code 144)

invalid offsite sent date

(Media Manager Status Code 143)

invalid offsite session id

(Media Manager Status Code 148)

invalid offsite slot

(Media Manager Status Code 147)



Invalid Operator

(Device Management Status Code 12)

invalid pool database entry

(Media Manager Status Code 102)

invalid protocol request

(Media Manager Status Code 6)

invalid query type

(Media Manager Status Code 73)

invalid robot coord1

(Media Manager Status Code 16)

invalid robot coord2

(Media Manager Status Code 17)

Invalid robot drive number for the robot type

(Device Configuration Status Code 28)

invalid robot host

(Media Manager Status Code 14)

Invalid robot number

(Device Configuration Status Code 15)

invalid robot number

(Media Manager Status Code 13)

Invalid robot type

(Device Configuration Status Code 18)



invalid robot type

(Media Manager Status Code 12)

invalid rule database entry

(Media Manager Status Code 119)

invalid scratch pool name

(Media Manager Status Code 173)

Invalid SCSI bus number for the robot

(Device Configuration Status Code 8)

Invalid SCSI logical unit number for the robot

(Device Configuration Status Code 10)

Invalid SCSI port number for the robot

(Device Configuration Status Code 7)

Invalid SCSI target for the robot

(Device Configuration Status Code 9)

Invalid Usage

(Device Configuration Status Code 11)

invalid volgroup

(Media Manager Status Code 15)

Invalid volume count

(Device Management Status Code 18)

invalid volume database host

(Media Manager Status Code 19)

invalid volume move mode

(Media Manager Status Code 53)

Invalid volume pool specified

(Device Management Status Code 65)

invalid volume pool

(Media Manager Status Code 90)

IPC Error: Daemon may not be running

(Device Management Status Code 22)

IPC sequence error

(Device Management Status Code 10)

LTI Daemon may not be running

(Robot Error Status Code 2)

Magic Number MisMatch

(Device Management Status Code 29)

Media access port already contains media

(Robotic Status Code 221)

Media access port does not contain media

(Robotic Status Code 220)

Media access port is available

(Robotic Status Code 250)

Media access port is in eject mode

(Robotic Status Code 253)



Media access port is in inject mode

(Robotic Status Code 252)

Media access port is unavailable

(Robotic Status Code 251)

media access port not available

(Media Manager Status Code 166)

media generation rule already exists

(Media Manager Status Code 138)

media generation rule does not exist

(Media Manager Status Code 139)

media ID is not the specified media type

(Media Manager Status Code 95)

media ID not unique in database

(Media Manager Status Code 34)

media type and volume group mismatch

(Media Manager Status Code 101)

Mount canceled, device daemon is terminating

(Device Management Status Code 56)

must be root user to execute command

(Media Manager Status Code 3)

network protocol error

(Media Manager Status Code 39)

No action pending for given mount index

(Device Management Status Code 50)

no child process to wait for

(Media Manager Status Code 64)

no cleaning tape available

(Media Manager Status Code 66)

No cleaning tape is defined in the device's robot or 0 cleanings remaining

(Device Management Status Code 59)

No device found in RSM at the specified location

(Device Configuration Status Code 45)

No device is registered at these SCSI coordinates

(Device Configuration Status Code 51)

No devices are configured on the robot

(Robot Error Status Code 6)

no entries changed

(Media Manager Status Code 47)

no entries deleted

(Media Manager Status Code 48)

no entries inserted

(Media Manager Status Code 49)

No media found in device or robot slot, please verify

(Device Management Status Code 61)



No memory available

(Robot Error Status Code 8)

No mount pending for given mount index

(Device Management Status Code 16)

no pools in the pool list

(Media Manager Status Code 112)

No robot daemon or robotics are unavailable

(Device Management Status Code 60)

No robot is defined of this type

(Device Management Status Code 52)

No robots are configured

(Robot Error Status Code 7)

<NONE>

(Device Configuration Status Code 36)

not authorized to connect to vmd

(Media Manager Status Code 126)

Not licensed for Fastrax support

(Device Configuration Code 53)

One implicit reserve already exists

(Device Management Status Code 11)

Only the administrative user can perform the requested operation

(Device Management Status Code 19)

operation not allowed on cleaning cartridge

(Media Manager Status Code 117)

Operator denied mount request

(Device Management Status Code 55)

oprd request is not supported on the remote host

(Media Manager Status Code 137)

oprd returned abnormal status

(Media Manager Status Code 96)

Parameter is invalid

(Device Management Status Code 39)

Physical drive is not available

(Robotic Status Code 245)

pool database close operation failed

(Media Manager Status Code 107)

pool database lock operation failed

(Media Manager Status Code 106)

pool database open operation failed

(Media Manager Status Code 108)

pool database truncate operation failed

(Media Manager Status Code 110)

pool does not exist in pool database

(Media Manager Status Code 109)



pool not defined as a scratch pool

(Media Manager Status Code 172)

poolname is not unique in pool database

(Media Manager Status Code 105)

Process killed by parent

(Robotic Status Code 212)

Process killed by signal

(Robotic Status Code 211)

protocol error

(Media Manager Status Code 20)

request completed

(Media Manager Status Code 1)

Request has been queued (Cancel to clear message

(Device Management Status Code 53)

Request terminated because host not validated for volume pool

(Device Management Status Code 26)

Request terminated because media id is expired

(Device Management Status Code 27)

Request terminated because *media id* will exceed maximum mount count

(Device Management Status Code 30)

Request terminated because media is unavailable (in DOWN drive, misplaced, write protected or unmountable

(Device Management Status Code 35)

Request terminated because media is unmountable

(Device Management Status Code 69)

Request terminated because media is write protected

(Device Management Status Code 70)

Request terminated because mount requests are disabled

(Device Management Status Code 63)

Request terminated because of volume pool mismatch

(Device Management Status Code 66)

Request terminated because user not validated for volume pool

(Device Management Status Code 67)

Request terminated because user/group not validated for volume pool

(Device Management Status Code 68)

Request terminated by tpunmount call from another process

(Device Management Status Code 36)

Requested drive could not be reserved

(Device Management Status Code 24)

requested drive is already reserved by host

(Media Manager Status Code 145)

requested drive is already reserved

(Media Manager Status Code 130)

Requested drive is in an offline domain

(Robotic Status Code 238)



requested drive is not currently registered

(Media Manager Status Code 132)

requested drive is not currently reserved

(Media Manager Status Code 134)

requested drive is not registered for host

(Media Manager Status Code 131)

requested drive is not reserved by host

(Media Manager Status Code 133)

requested host is not currently registered

(Media Manager Status Code 135)

Requested number of drives are not configured

(Device Management Status Code 31)

Requested operation is not supported by the robot

(Robotic Status Code 229)

Requested slot already has cartridge

(Robotic Status Code 217)

Requested slot contains the wrong tape

(Robotic Status Code 226)

Requested slot does not exist in robot

(Robotic Status Code 228)

Requested slot is empty

(Robotic Status Code 208)

Requested tape in other or non-configured drive

(Robotic Status Code 215)

Requested volume is in an offline domain

(Robotic Status Code 239)

Residence is not licensed for multihosted drive support

(Device Configuration Status Code 37)

Robot busy, cannot perform operation

(Robotic Status Code 223)

Robot denied access to the resource

(Robotic Status Code 234)

Robot drive number in use for this robot

(Device Configuration Status Code 25)

Robot hardware or communication error

(Robotic Status Code 225)

Robot has misplaced the media

(Robotic Status Code 236)

robot host and volume group mismatch

(Media Manager Status Code 82)

Robot media access port does not exist

(Robotic Status Code 242)

robot number and robot host mismatch

(Media Manager Status Code 61)



robot number and robot type mismatch

(Media Manager Status Code 54)

robot number and volume group mismatch

(Media Manager Status Code 55)

Robot number does not exist

(Device Configuration Status Code 31)

Robot number does not exist

(Robotic Status Code 214)

Robot number is already in use

(Device Configuration Status Code 21)

Robot number is in use by another robot

(Device Configuration Status Code 30)

robot type and volume group mismatch

(Media Manager Status Code 81)

Robot type is not supported on this platform

(Device Configuration Status Code 6)

Robotic arm has no addressable holder

(Robotic Status Code 222)

Robotic daemon not licensed

(Robot Error Status Code 17)

Robotic dismount failure

(Robotic Status Code 206)

Robotic mount failure

(Robotic Status Code 205)

robotic volume position is already in use

(Media Manager Status Code 37)

RSM is supported only on Microsoft Windows 2000 and later OS versions

(Device Configuration Status Code 48)

rule database close operation failed

(Media Manager Status Code 124)

rule database lock operation failed

(Media Manager Status Code 123)

rule database open operation failed

(Media Manager Status Code 125)

rule database truncate operation failed

(Media Manager Status Code 98)

rule does not exist in rule database

(Media Manager Status Code 97)

specified robot is unknown to vmd

(Media Manager Status Code 79)

STATUS_SUCCESS

(Robotic Status Code 200)

Success

(Device Configuration Status Code 0)



Success

(Format Optical Status Code 0)

System error occurred during robot operation

(Robotic Status Code 230)

System error occurred

(Robot Error Status Code 11)

system error

(Media Manager Status Code 2)

Tape file path exceeds 255 character maximum

(Device Management Status Code 49)

Tape needs to be write enabled

(Device Management Status Code 46)

The device is not robotic, cannot perform cleaning

(Device Management Status Code 58)

The device name is not valid, no device responded

(Device Configuration Status Code 52)

The drive is DOWN

(Device Management Status Code 15)

The drive is not ready or inoperable

(Device Management Status Code 21)

The eject command was aborted by the user

(Robotic Status Code 244)

The external_drive_mappings file has invalid license info

(Device Configuration Status Code 3)

The external_robot_mappings file has invalid license info

(Device Configuration Status Code 2)

the global device database device name is invalid

(Media Manager Status Code 162)

the global device database device serial number is invalid

(Media Manager Status Code 161)

the global device database device type is invalid

(Media Manager Status Code 160)

The global device database hostname is invalid

(Device Configuration Status Code 49)

The global device database version is incompatible

(Device Configuration Status Code 4)

the requested slot is empty

(Media Manager Status Code 100)

the robotic daemon returned an invalid volume GUID

(Media Manager Status Code 164)

the specified pool is not empty

(Media Manager Status Code 111)

the volume guid is not unique in the database

(Media Manager Status Code 159)



this machine is not the volume database host

(Media Manager Status Code 84)

This robot type does not support multiple media types

(Device Configuration Status Code 17)

Timeout waiting for robotic command

(Robotic Status Code 203)

too many volumes in volume group

(Media Manager Status Code 68)

tpformat: Cannot open

(Format Optical Status Code 3)

tpformat: Cannot read

(Format Optical Status Code 4)

tpformat: Cannot seek

(Format Optical Status Code 5)

tpformat: Cannot set volume header

(Format Optical Status Code 2)

tpformat: Cannot write

(Format Optical Status Code 6)

tpformat: Command interrupted

(Format Optical Status Code 11)

tpformat: Existing media ID

(Format Optical Status Code 7)

tpformat: Invalid robot

(Format Optical Status Code 10)

tpformat: Invalid usage

(Format Optical Status Code 1)

tpformat: Must be root

(Format Optical Status Code 8)

tpformat: No media present in drive or robot slot

(Format Optical Status Code 13)

tpformat: Skip

(Format Optical Status Code 12)

tpformat: Tape request failed

(Format Optical Status Code 9)

unable to generate a unique media id

(Media Manager Status Code 127)

Unable to initialize robot

(Robotic Status Code 204)

unable to link to dynamic library

(Media Manager Status Code 174)

Unable to open drive

(Robotic Status Code 209)

Unable to open robotic path

(Robotic Status Code 201)



Unable to retrieve GUID from RSM api

(Device Configuration Status Code 46)

Unable to SCSI unload drive

(Robotic Status Code 210)

unable to send exit status

(Media Manager Status Code 67)

Unable to sense robotic device

(Robotic Status Code 202)

unexpected data from robotic software daemon

(Media Manager Status Code 46)

unexpected data from robotic software daemon

(Media Manager Status Code 46)

unexpected data received

(Media Manager Status Code 40)

Unknown drive name

(Device Management Status Code 41)

Usage error in creating child process

(Robot Error Status Code 12)

user is not valid for this host

(Media Manager Status Code 99)

volume daemon fork failed

(Media Manager Status Code 85)

volume does not exist in database

(Media Manager Status Code 35)

volume group does not exist

(Media Manager Status Code 65)

volume has exceeded maximum mounts

(Media Manager Status Code 116)

volume has passed expiration date

(Media Manager Status Code 115)

volume is already assigned

(Media Manager Status Code 93)

Volume is in home slot

(Robotic Status Code 249)

Volume is in library, but not in drive domain

(Robotic Status Code 233)

Volume is in use

(Robotic Status Code 237)

volume is not in specified pool

(Media Manager Status Code 94)

Volume not found in library

(Robotic Status Code 232)

You do not have permission to create the file

(Device Management Status Code 44)



Messages

You must be administrator to execute

(Robot Error Status Code 14)

You must be ROOT to start daemon

(Robot Error Status Code 1)



Disaster Recovery

6

This chapter has procedures for recovering your data in case of a server or client disk failure. The recovery procedures are as follows:

- ◆ Master Server Disk Recovery
- ◆ Media Server Disk Recovery
- ◆ Client System Disk Recovery - Windows
- ◆ Recovering the NetBackup Catalogs

Master Server Disk Recovery

The procedures in this section explain how to recover your data if one or more disk partitions are lost on a NetBackup master server. Two general cases are considered:

- ◆ Windows is intact. The system still boots Windows, but all or some of the other partitions are lost. NetBackup is also assumed to be lost.
- ◆ All disk partitions are lost. This is a total recovery.


In both cases, you restore the server to the state it was in at the time of the most recent backup of the NetBackup catalogs. If the recovery is successful, reconfiguration is unnecessary.

Recovery When Windows is Intact

This procedure assumes that Windows will boot and is not corrupt. The general steps are to restore NetBackup and then restore all other files. Figure 1 illustrates the procedure.



Figure 1. Recover Master Server - Windows Intact (overview)



Before Starting

Verify that you have:

- ◆ NetBackup server software for Windows
- ◆ The latest NetBackup catalog backup on tape or disk

To Recover the Master Server (Windows intact)

1. Partition the disks as they were before the failure.
2. Install NetBackup server software. However, do not configure any NetBackup policies or devices.

3. Install any NetBackup patches that had previously been installed.
4. Update the external mapping files.
5. Enable debug logging by creating the following directories:
`install_path\NetBackup\logs\tar`
`install_path\NetBackup\logs\bpineta`
6. Start the NetBackup Client service and stop all other NetBackup services.
 Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel.
7. Use the `bprecover` command to recover the NetBackup catalogs:
 Choose one of the procedures under “Recovering the NetBackup Catalogs” on page 409.
8. When catalog recovery is complete, start the NetBackup services that are not already running.
 Use the Activity Monitor, or the Services application in the Windows Control Panel.

Caution In step 9, do not restore files to the `install_path\NetBackup\db`, `install_path\NetBackup\var`, or `install_path\Volmgr\database` directories. These directories were recovered in step 7 and overwriting them with regular backups will leave the catalogs in an inconsistent state.

9. Restore all other files:
 - a. Start the NetBackup Administration interface on the master server.
 - b. Start the Backup, Archive, and Restore utility.
 - c. Browse for restores and select the partitions that were lost.
 - d. Deselect the `install_path\NetBackup\db`, `install_path\NetBackup\var`, and `install_path\Volmgr\database` directories (see the caution above).
 - e. Start the restore.
10. When all partitions are restored, check the debug logs in the directories created in step 5. If there are any ERR or WRN messages, resolve the problems before proceeding.




11. Reboot the system.

This replaces any files that were busy during the restore. When the boot process is complete, the system is restored to the state it was in at the time of the last backup.

Total Recovery

The following procedure explains how to perform a total recovery of a NetBackup master server and assumes that Windows must be reinstalled. Figure 2 illustrates the procedure.

Figure 2. Master Server Total Recovery (overview)



Assumptions

- ◆ The NetBackup master server was running Windows NT or Workstation 4.0 or above, or Windows 2000.
- ◆ The latest NetBackup catalog backup is available on tape or disk.
- ◆ The regular backups included the system directory (typically, C:\Winnt). This is the directory where the Windows operating system and therefore the registry reside.

If the regular backups excluded any files that resided in the system directory, it is possible that you will not be able to restore the system so it completely matches its previous configuration.

- ◆ Defective hardware has been replaced.

Before Starting

Verify that you have:

- ◆ Windows software to reinstall on the NetBackup server that is being restored.
Reinstall the same type and version of software that was previously used. For example, do not install Windows NT Server 4.0 software if, before the failure, the system was a Windows NT 4.0 workstation.
- ◆ NetBackup server software for Windows.
- ◆ Special Drivers or other software required to get the hardware operational (for example, a special driver for the disk drive).
- ◆ IP address and host name of the NetBackup master server.
- ◆ Partitioning and formatting scheme that was used on the system you are restoring. You must duplicate that scheme during Windows installation.
- ◆ Latest NetBackup catalog backup on tape or disk.

To Recover the Master Server (total recovery)

1. Install a minimal Windows operating System (perform the Express install).

Be certain to:

- ◆ Partition the disk as it was before the failure (if partitioning is necessary). Then, reformat each partition as it was before the failure.
- ◆ Install Windows in the same partition that was used before the failure.
- ◆ Specify the default workgroup. Do not restore to the domain.
- ◆ Follow any hardware manufacturers instructions that apply, such as loading SSD on a Compaq system.



- ◆ Reboot the system when the install is complete.
- 2. Install SCSI or other drivers needed to communicate with the tape drives on the system.
- 3. Install NetBackup server software. However, do not configure any NetBackup policies or devices.
- 4. Install any NetBackup patches that had previously been installed.
- 5. Update the external mapping files.
- 6. Enable debug logging by creating the following directories:
install_path\NetBackup\logs\tar
install_path\NetBackup\logs\bpinetd
- 7. Start the NetBackup Client service and stop all other NetBackup services.
Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel.
- 8. Use the `bprecover` command to recover the NetBackup catalogs.
Choose one of the procedures under “Recovering the NetBackup Catalogs” on page 409.
- 9. When catalog recovery is complete, start the NetBackup services that are not already running.
Use the Activity Monitor, or the Services application in the Windows Control Panel.

Caution In step 10, do not restore files to the *install_path\NetBackup\db*, *install_path\NetBackup\var*, or *install_path\Volmgr\database* directories. These directories were recovered in step 8 and overwriting them with regular backups will leave the catalogs in an inconsistent state.

- 10. Restore all other files:
 - a. Start the NetBackup Administration interface on the master server.
 - b. Start the Backup, Archive, and Restore utility.
 - c. Browse for restores and select all partitions.

It is especially important to select the system directory (typically C:\Winnt). This ensures that all registry files are restored.

- d. Deselect the *install_path*\NetBackup\db, *install_path*\NetBackup\var, or *install_path*\Volmgr\database directories (see the caution above).
- e. Select the Overwrite existing files option.
This ensures that existing files are replaced with the backups.
- f. Start the restore.

11. Check the debug logs in the directories created in step 6. If there are any ERR or WRN messages, resolve the problems before proceeding.

12. Reboot the system.

This replaces any files that were busy during the restore. When the boot process is complete, the system is restored to the state it was in at the time of the last backup.

Media Server Disk Recovery

Note The term *media server*, as distinct from *master server* or *server*, does not apply to the NetBackup BusinessServer product. When troubleshooting a BusinessServer installation, please ignore any references to media server.

The procedure for recovering a media server where the system disk has failed is the same as for a master server, except that you use the following paths when running `bprecover`:

media_server_name:*install_path*\NetBackup\db\media

media_server_name:*install_path*\NetBackup\var

media_server_name:*install_path*\Volmgr\database

In the above paths, substitute the host name of the media server for *media_server_name* (for example, elk). For *install_path*, substitute the directory where NetBackup is installed.

You can execute `bprecover` from either the master or media server by specifying the correct destination host with the `bprecover -dhost` option.



Client System Disk Recovery - Windows

The following procedure explains how to perform a total recovery of a Windows NetBackup client in the event of a system disk failure.

Note For Windows NT/2000 systems: if you have installed and configured NetBackup Intelligent Disaster Recovery, refer to the *NetBackup System Administration Guide* instead of the instructions below.

This procedure assumes that the Windows operating system and NetBackup must be reinstalled in order to boot the system and perform a restore.

Assumptions

- ◆ The NetBackup client was running one of the following:
 - ◆ Windows NT Server or Workstation 4.0 or above, or Windows 2000.
 - ◆ Windows 98 or 95 software
- ◆ The NetBackup client was backed up with version 3.0 or later NetBackup client and server software.
- ◆ The NetBackup master server to which the client sent its backups is operational. This is the server from which you will be requesting the restore.
- ◆ The backups included the directory where the operating system and therefore the registry resided (typically C:\winnt40 on Windows NT and C:\Windows on Windows 98 or 95).

If the backups excluded any files that resided in the above directory, it is possible that you will not be able to restore the system so it completely matches its previous configuration.

- ◆ Defective hardware has been replaced.

Before Starting

Verify that you have the following:

- ◆ Windows system software to reinstall on the NetBackup client that is being restored:
 - ◆ Reinstall the same type and version of software that was previously used. For example, do not install Windows NT Server 4.0 software if, before the failure, the system was a Windows NT 4.0 workstation.
 - ◆ For a Windows NT/2000 client, this software must be Windows NT Server or Workstation 4.0 or above, or Windows 2000.
- ◆ NetBackup 3.0 or later client software to install on the client that is being restored.



- ◆ Special drivers or other software required to get the hardware operational (for example, a special driver for the disk drive).
- ◆ IP address and host name of the NetBackup client.
- ◆ IP address and host name of the NetBackup master server.
- ◆ Partitioning and formatting scheme that was used on the system that you are restoring. You must duplicate that scheme during Windows installation.

To Recover a Windows Client Disk

1. Install a minimal Windows operating system (perform the Express install).

During the install, be certain to:

- ◆ Partition the disk as it was before the failure (if partitioning is necessary). Then, reformat each partition as it was before the failure.
- ◆ Install the operating system in the same partition that was used before the failure.
- ◆ Specify the default workgroup. Do not restore to the domain.
- ◆ Follow any hardware manufacturers instructions that apply, such as loading SSD on a Compaq system.

2. Reboot the system when the install is complete.
3. Configure the NetBackup client system to re-establish network connectivity to the NetBackup master server.

For example, if your network uses DNS, the configuration on the client must use the same IP address as before the failure and must specify the same name server (or another name server that recognizes both the NetBackup client and master server). On the client, configure DNS in the Network dialog box that you access from the Control Panel.

4. Install NetBackup client software.

Refer to the *NetBackup Installation Guide for PC Clients* for instructions. Ensure that you specify the correct names for the client and master server. To specify the client name, start the user interface on the client and click Configure on the Actions menu. Enter the client name on the General tab of the NetBackup Configuration dialog. To specify the server name, click Specify NetBackup Machines on the Actions menu and make the entry on the Servers tab.

5. Install any NetBackup patches that had previously been installed.
6. Enable debug logging by creating the following debug log directories on the client:



On a Windows NT/2000 client:

install_path\NetBackup\Logs\tar

install_path\NetBackup\Logs\bpnetd

On a Windows 98 or 95 client:

install_path\NetBackup\Logs\bpcd

NetBackup creates logs in these directories.

7. For a Windows NT/2000 client, stop and restart the NetBackup Client Manager service.

This enables NetBackup to start logging to the bpnetd debug log.

8. For a Windows 98 or 95 client, stop and restart the NetBackup Client Daemon.

This enables NetBackup to start logging to the bpcd debug log.

9. Use the NetBackup client user interface to restore the system and user files to the client system.

For example, if all files are on the C: drive, restoring that drive restores the entire system.

To restore files, you do not have to be the administrator, but you must have restore privileges. For example, on Windows NT/2000, you must be a member of the Restore group, which is one of the built-in Windows NT/2000 groups. Refer to the online help or *NetBackup User's Guide for Microsoft Windows* for instructions on how to restore files.

Note NetBackup restores the registry when it restores the Windows system files. For example on a Windows NT/2000 client, if the system files are in the C:\Winnt40 directory, NetBackup restores the registry when it restores that directory and all its subordinate subdirectories and files.

10. Check for ERR or WRN messages in the log files that are in the directories you created in step 6.

- ◆ For a Windows NT/2000 client, these are the tar and inetd log files.
- ◆ For a Windows 98 or 95 client, this is the bpcd log file.

If the logs indicate problems with the restore of Windows system files, resolve those problems before proceeding.

11. Reboot the NetBackup client system.

When the boot process is complete, the system is restored to the state it was in at the time of the last backup.

Recommended Backup Practices

In addition to backing up files on a regular basis it is important to select the correct files to back up. The first concern is to include all files with records that are critical to users and the organization. It is equally important to back up system and application files, so you can quickly and accurately restore a system to normal operation if a disaster occurs.

Include all Windows system files in your backups. For example, if Windows NT/2000 is installed in the C:\Winnt40 directory, include this directory in the list of those that you are backing up (it may be best to back up the entire drive). In addition to the other system software, the Windows system directories include the registry, without which it is impossible to restore the client to its original configuration. If you are using a NetBackup exclude list for a client, do not specify any Windows system files in that list.

It is not a good idea to omit executable and other files for applications such as NetBackup. It is tempting to save tape by excluding these easy to reinstall files. However, backing up the entire application, ensures that you can restore it to its exact configuration. For example, if you have applied software updates or patches, restoring from a backup eliminates the need to reapply them, thus reducing recovery time.

For information on how to configure scheduled backups, see the *NetBackup System Administrator's Guide*. For instructions on performing user backups and archives, see the *NetBackup User's Guide for Microsoft Windows*.

Recovering the NetBackup Catalogs

The NetBackup catalogs contain critical information and must be recovered before any other backups.

Master servers have the following NetBackup catalog files:

```
install_path\NetBackup\db  
install_path\NetBackup\var  
install_path\Volmgr\database
```

Media servers have the following NetBackup catalog files:

```
install_path\netbackup\db\media  
install_path\netbackup\var  
install_path\volmgr\database
```

For *install_path*, substitute the directory where NetBackup and Media Manager are installed (C:\Program Files\VERITAS by default).

Because of their importance, the catalogs are backed up separately from other files as described in the *NetBackup System Administrator's Guide for Windows*. To recover the catalogs, use the `bprecover` command:



`install_path\NetBackup\bin\admincmd\bprecover`

The topics in this section explain how to use `bprecover` to recover NetBackup catalog backups. Also, see the description in the Commands appendix in the *NetBackup System Administrator's Guide for Windows*.

Note The following discussions assume that NetBackup has been reinstalled, if required (see “Master Server Disk Recovery” on page 399).

Identifying the Most Recent Database Backup

Caution Before you can recover the NetBackup catalogs, you must know which media ID has their latest backups. Without this media ID, you cannot accurately recover your catalogs and your only option is to use the NetBackup import feature to import all lost backup records into your NetBackup catalogs (see the *NetBackup System Administrator's Guide for Windows*).

As mentioned in the *NetBackup System Administrator's Guide for Windows*, the best way to track media IDs for catalog backups is to configure E-mail notifications with the E-mail Address global attribute. This attribute causes NetBackup to specify the status and media ID in an E-mail to the administrator each time a catalog backup occurs. You can then check the E-mail to determine the last media ID used.

If you know the media IDs that were used but are not sure which of them has the most recent backup, use the `-l` option of `bprecover` to list the backups on each media ID. This information includes the date and time that the media was written.

Example 1: List by Using a Raw Device

Assume the catalog backup was to tape but the Media Manager part of the catalogs was lost so Media Manager cannot control the drive.

In this case, insert the media in an appropriate drive (assume the raw-device path is `\\.\Tape1`). Then, execute the following `bprecover` command on the NetBackup server that has the drive.

```
bprecover -l -tpath \\.\Tape1
Database Backup Information from \\.\Tape1
```

```
Created:      03/31/97 11:31:34
Server:      bphost
Block Size:   32768
```

```
Path
```

```
----
```

```
IMAGE1 D:\apps\VERITAS\NetBackup\db
```



```
IMAGE2 D:\apps\VERITAS\Volmgr\database
```

Example 2: List by Using a Media Manager Controlled Drive

Assume the Media Manager part of the catalogs is intact and the backup was to a dlt tape with media ID 000001. Insert the tape into an appropriate drive. Then, execute the following `bprecover` command on the NetBackup server that has the drive (the NetBackup Device Manager Service must be active).

```
bprecover -l -ev 000001 -d dlt  
Database Backup Information from 000001
```

```
Created:      03/31/97 05:50:51  
Server:      bphost  
Block size:  32768
```

```
Path
```

```
----
```

```
IMAGE1 D:\apps\VERITAS\Netbackup\db  
IMAGE2 D:\apps\VERITAS\Volmgr\database  
IMAGE3 D:\apps\VERITAS\var
```

Example 3: List Disk Path

Assume the catalog backup was done to disk path `D:\apps\dbbackup` and this disk has not failed. Execute the following `bprecover` command to list the backup information.

```
bprecover -l -dpath D:\apps\dbbackup  
Database Backup Information from D:\apps\dbbackup
```

```
Created:      03/31/97 11:31:34  
Server:      bphost  
Block size:  32768
```

```
Path
```

```
----
```

```
IMAGE1 D:\apps\VERITAS\NetBackup\db  
IMAGE2 D:\apps\VERITAS\NetBackup\var  
IMAGE3 D:\apps\VERITAS\Volmgr\database
```

Procedures for Recovering NetBackup Catalogs

This section explains how to recover the NetBackup catalogs when all or part of them are lost. You perform this recovery with the `bprecover` command.

The method required to recover the catalogs depends on:



Recovering the NetBackup Catalogs

- ◆ The type of media that contains the backup of the NetBackup catalogs (tape or magnetic disk).
- and
- ◆ Whether the Media Manager part of those catalogs is still intact. The Media Manager catalog files are normally in the *install_path*\Volmgr\database directory.

Note The Media Manager device catalogs are binary files and you cannot restore them to a different type of platform.

Before Starting

- ◆ Reinstall the NetBackup software (if necessary) as explained in “Master Server Disk Recovery” on page 399 or “Media Server Disk Recovery” on page 405.
- ◆ Find the tape that has the latest catalog backups.
- ◆ Ensure that the disk where you are restoring the catalogs contains the directory where the catalogs resided.

This is required because the `bprecover` command always restores the NetBackup catalogs to the path from which they were backed up (alternate-path restores are not allowed).

Recover Catalogs From Tape - Media Manager Catalogs Lost


If the NetBackup catalog backup is on tape and the Media Manager catalogs are lost, specify a raw-device path on the `bprecover` command. This method involves mounting the backup tape in a drive and using the `-tpath` parameter.

Note If the configuration was lost for the device that you plan to use for the recovery, reinstall the device as explained in the Windows system documentation.

1. Insert the catalog backup tape into an appropriate drive.

The example on Figure 3 shows a nonrobotic tape drive connected to a NetBackup master server.

Figure 3. Recover Catalogs From Tape



2. Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to stop the following services, if they are running.
 - ◆ NetBackup Request Manager service
 - ◆ NetBackup Database Manager service
 - ◆ NetBackup Device Manager service
 - ◆ NetBackup Volume Manager service
3. Use the Activity Monitor, or the Services application in the Windows Control Panel, to verify that the NetBackup Client Manager service is running. Start it if necessary.
4. On the NetBackup server where the drive attaches, execute the `bprecover` command. Specify the raw-device path for the drive where you inserted the tape in step 1.

Example 1

This example interactively restores images to disk 1 on Figure 3 by using raw-device path `\\\\.\\Tape1`:

```
bprecover -r -tpath \\.\\Tape1
Recover shark:D:\\VERITAS\\NetBackup\\db y/n (n)? y
Recover shark:D:\\VERITAS\\Volmgr\\database y/n (n)? y
Recovering shark:D:\\VERITAS\\NetBackup\\db
Recovering shark:D:\\VERITAS\\Volmgr\\database
```

Example 2




If you have media servers, `bprecover` includes their catalog paths in the prompts and you select the catalogs you want to recover.

The following example recovers only the catalogs for a media server named `eel` (see Figure 4). Here, you execute `bprecover` on the master server `shark` and use the `-dhost` option to specify `eel` as the destination host:

```
bprecover -r -tpath \\.\Tape1 -dhost eel
Recover shark:install_path\NetBackup\db y/n (n)? n
Recover shark:install_path\NetBackup\var y/n (n)? n
Recover shark:install_path\Volmgr\database y/n (n)? n
Recover eel:install_path\NetBackup\db\media y/n (n)? y
Recovering eel:install_path\NetBackup\db\media
Recover eel:install_path\NetBackup\var y/n (n)? y
Recovering eel:install_path\NetBackup\var
Recover eel:install_path\Volmgr\database y/n (n)? y
Recovering eel:install_path\Volmgr\database
```

You can also use the `-dhost` option to restore from a media server to the master (for example, if the master does not have a drive).

Figure 4. Recover Media Server Databases



- After recovering catalogs for the master and all media servers, use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to start the following services:

- ◆ NetBackup Request Manager Service

- ◆ NetBackup Database Manager Service
- ◆ NetBackup Device Manager Service
- ◆ NetBackup Volume Manager Service

Recover Catalogs from Tape - Media Manager Catalogs Intact

When the Media Manager catalogs are intact, you can recover the catalog backups by using a drive configured under Media Manager control as follows:

1. Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to stop the following services if they are running:
 - ◆ NetBackup Request Manager service
 - ◆ NetBackup Database Manager service
2. Insert the tape with the catalog backup into an appropriate drive.
 If the tape is not in the drive, the Device Monitor shows a mount request when you start the recovery. If this occurs, insert the tape and use the Device Monitor to assign the drive to the request.
3. On the NetBackup server where the drive attaches, execute the `bprecover` command.

Example 1

Assume you are restoring the catalogs to disk 1 on Figure 3 and the 8mm tape has media ID JBL29. To recover the NetBackup part of the catalogs from image 1 on the tape, execute the following command on shark:

```
bprecover -r 1 -ev JBL29 -d 8mm
Recovering shark:D:\VERITAS\NetBackup\db
```

Example 2

If the drive attaches to another NetBackup server, execute `bprecover` on the server where the drive attaches and specify `shark` with the `-dhost` option.

```
bprecover -r 1 -ev JBL29 -d 8mm -dhost shark
Recovering shark:D:\VERITAS\NetBackup\db
```

4. Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to:
 - a. Start the following services:
 - ◆ NetBackup Request Manager service



- ◆ NetBackup Database Manager service
- b. Stop and restart the following services so they can read the recovered configuration:
 - ◆ NetBackup Device Manager service
 - ◆ NetBackup Volume Manager service

Recover Catalogs From Disk

If you backed up the NetBackup catalogs to a disk and that disk is intact, you can recover the catalogs as follows:


Note If this disk has failed then you must resort to backups of this disk that have gone to another server. If you have not backed up the NetBackup catalogs to another server, you must use the NetBackup Import Images feature to re-add the image information to the catalogs. See the *NetBackup System Administrator's Guide for Windows* for instructions.

1. Use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to stop the following services:
 - ◆ NetBackup Request Manager service
 - ◆ NetBackup Database Manager service
 - ◆ NetBackup Device Manager service
 - ◆ NetBackup Volume Manager service
2. Execute the `bprecover` command to recover the catalogs.

For example, the following command recovers the `D:\VERITAS\NetBackup\db` catalogs from disk path `D:\apps\dbbackup` on Figure 5.

```
bprecover -r 1 -dpath D:\apps\dbbackup  
Recovering shark:D:\VERITAS\NetBackup\db
```

Figure 5. Recover Catalogs From Disk



3. After recovering the catalogs, use the NetBackup Activity Monitor, or the Services application in the Windows Control Panel, to start the following services:
 - ◆ NetBackup Request Manager Service
 - ◆ NetBackup Database Manager Service
 - ◆ NetBackup Device Manager Service
 - ◆ NetBackup Volume Manager Service





Functional Overview

A

This appendix provides a functional overview of NetBackup for both UNIX and Windows. Such comprehensive treatment is valuable for mixed-platform environments.

The discussions include descriptions of important daemons and programs, and the sequence in which they execute during typical operations. The databases and the directory structure of the installed software are also described.

There are two main sections in this appendix:

- ◆ Backup and Restore Functional Description
- ◆ Media Manager Functional Description

It is assumed that you are already familiar with the overviews in the first chapter of the *NetBackup System Administrator's Guide for UNIX* and the *Media Manager System Administrator's Guide for UNIX*.

Note that this appendix does not pertain to the NetBackup products for backing up relational databases (such as NetBackup for ORACLE). The installation guides for those products have information regarding their operation.

Backup and Restore Functional Description

This section explains the operation of NetBackup during backup and restores and contains the following discussions:

- ◆ Startup Process
- ◆ Backup and Archive Processes
- ◆ Restore Processes
- ◆ NetBackup Directories and Files
- ◆ NetBackup Databases



Startup Process

Before NetBackup can perform scheduled operations or respond to user-directed requests, the NetBackup request daemon `bprd` must be started on the master server, and the Media Manager device daemon `ltid` must be started on the master server and all media servers. These two daemons, in turn, automatically start other daemons and programs as necessary (see Figure 6).

On a media server, it is not necessary to start `bprd` because it is not used. NetBackup automatically starts other required NetBackup programs when it accesses the media server.



Another daemon that executes on all server and clients is the NetBackup client daemon, `bpcd`. On UNIX clients, `inetd` starts `bpcd` automatically so no special actions are required. On Windows NT clients, `bpinetd` performs the same functions as `inetd`. Other PC clients do not use `inetd` or `bpinetd` but are usually configured to start `bpcd` automatically (see their user's guides for instructions).

There are no other daemons or programs that you must explicitly start. The necessary programs are started automatically during the backup or restore operation.

Figure 6 shows the programs that must be running and how they are started. The Media Manager functional description, later in this appendix, has details on the actions started by `ltid`.

Figure 6. Starting NetBackup


Master Server



Media Server

The Media Manager device components of NetBackup must be started as shown to the right.

The master server starts other NetBackup programs as necessary to use storage units that attach to the media server.



Client

On UNIX clients, bpcd must be in a listening state. On Windows and NetWare clients, bpcd must be running. Except for bpcd, required programs are started as necessary during the backup or restore. Macintosh and Windows NT/2000 clients must only be turned on and ready.



Backup and Archive Processes

The backup and archive processes vary depending on the type of client. The following explains the basic variations. There is also a description of how NetBackup operates when backing up its databases.

Backups and Archives - UNIX Clients

For UNIX clients, NetBackup supports scheduled, immediate manual, and user-directed backups of both files and raw partitions. User-directed archives of files is also supported (you cannot archive raw partitions). Once started, these operations are all similar to the extent that the same daemons and programs execute on the server (see Figure 7). Each type, however, is started differently.

- ◆ Scheduled backup operations begin when the NetBackup request daemon, `bprd`, activates the scheduler, `bpsched`. This occurs at intervals determined by the `Wakeup Interval` global attribute. Once activated, the scheduler checks the policy configurations for scheduled client backups that are due.
- ◆ Immediate manual backups begin if the administrator chooses the manual backup option in the NetBackup administrator interface. This causes `bprd` to start `bpsched`, which then processes the policy, client, and schedule selected by the administrator.
- ◆ User-directed backups or archives begin when a user on a client starts a backup or archive through user interface on the client (or the `bpbackup` or `bparchive` commands). This invokes the client's `bpbackup` or `bparchive` program, which sends a request to the request daemon `bprd` on the master server. When `bprd` receives the user request, it starts `bpsched`, which checks the policy configurations for schedules and by default chooses the first user-directed schedule that it finds in a policy that includes the requesting client. It is also possible to specify a policy and schedule by using the NetBackup configuration options, `BPBACKUP_POLICY` and `BPBACKUP_SCHED`, on the client.

The `bpbackup` and `bparchive` programs execute with the same permissions as the user. If you can read and write files (delete in the case of an archive), they can too.

The diagram illustrates the NetBackup architecture, divided into three main sections: Master Server, Server, and UNIX Client.

- Master Server:** Contains the Volume * Database (dashed box), vmd * (dashed oval), Master or Media Server (shaded box), Media Database (cylinder), bptm (parent) (oval), and ltid * (dashed oval).
- Server:** Contains Configuration Database (cylinder), File Database (cylinder), bpdbrm (oval), bpsched (oval), bpcd (oval), and bpbkar (oval).
- UNIX Client:** Contains Backup Policy Management (rounded rectangle), bprdr (oval), NetBackup User Interface (rounded rectangle), Command Line (rounded rectangle), bpbbackup or bparchive (oval), bpcd (oval), and Client Disk (cylinder).

Interactions and Data Flow:

- Master Server to Server:**
 - Volume * Database to vmd *.
 - vmd * to bpdbrm (labeled "New media ID for NB").
 - Configuration Database and File Database to bpdbrm.
 - Media Database to bptm (parent) (labeled "NB Media ID").
 - bpdbrm to bpsched (labeled "File Information").
 - bptm (parent) to ltid * (labeled "Tape request").
 - ltid * to Tape or Optical (labeled "mount").
- Server to UNIX Client:**
 - Backup Policy Management to bprdr.
 - bprdr to bpsched.
 - bpsched to bpcd.
 - bpcd to bpbkar.
 - bpbkar to bpbbackup or bparchive.
 - bpbbackup or bparchive to NetBackup User Interface and Command Line.
 - bpbkar to bpcd (labeled "File Information").
 - bpbkar to bpbkar (labeled "Backup Image").
 - bpbkar to bpbkar (labeled "Shared Memory").
 - bpbkar to bpbkar (labeled "bptm (child)").
 - bpbkar to bpbkar (labeled "bptm (parent)").
 - bpbkar to bpbkar (labeled "bpcd").
 - bpbkar to bpbkar (labeled "bpbkar").
 - bpbkar to bpbkar (labeled "Client Disk").

Notes:

- * For detail on these components, see the Media Manager Functional Description later in this chapter.

For all three types of backup and archive operations, `bpsched` uses `bpcd` (client daemon) to start the backup/restore manager (`bpbrm`). If the required storage unit attaches to the master server, `bpsched` starts the backup/restore manager on the master server. If the storage unit connects to a media server, `bpsched` starts the backup/restore manager on the media server.

The backup/restore manager starts the appropriate media manager process (`bptm` for tape or optical and `bpdm` for disk) and also starts the actual backup (or archive) by using the client daemon (`bpcd`) to start the backup and archive program (`bpbkar`) on the client.


The `bpbkar` program:

- ◆ Sends information about files within the image to the backup/restore manager, which directs the file information to the NetBackup file database.
- ◆ Transmits the backup image to the media manager process, `bptm` or `bpdm`. The `bptm` or `bpdm` process forks a second process, which receives the image and stores it block by block in shared memory. The original process then takes the image from shared memory and directs it to the storage media.
 - ◆ If the storage is tape or optical, `bptm` checks the NetBackup media database for a suitable media ID (for example, the correct density and retention level). If it can't find one, it obtains a new media ID from the Media Manager volume daemon, `vmd`. The `bptm` program includes the media ID in a tape request to the Media Manager device daemon, `ltid`, which finds the physical media and causes it to be mounted on an appropriate device. `bptm` also controls the spanning of backups across multiple tapes, if required.
 - ◆ If the storage media is disk, `bpdm` writes the images to the path configured in the disk storage unit. The system disk manager controls the actual writing of data.

In the case of an archive, NetBackup deletes the files from the client disk after the files have been successfully backed up.

For multiplexed backups, the process is essentially the same except that a separate `bpbrm` and `bptm` process is created for each backup image being multiplexed onto the media. NetBackup also allocates a separate set of shared memory blocks for each image. Figure 8 shows an example of multiplexing images from two clients. The other client and server processes are the same as on Figure 7.

Figure 8. Multiplexed Backups Example (two streams)



Backups and Archives - Windows 95/98 Clients


NetBackup supports the same types of operations on Windows 95 and 98 clients as it does for UNIX clients, with the following exception:

- ◆ Raw partition backups are not supported.

The next figure shows the Windows 95 and 98 client processes. On this figure:

- ◆ The user interface program is called NBWIN. The bpbbackup, bpbarchive, and bplist functions are merged into NBWIN.
- ◆ The NetBackup client daemon is called BPCDW32. The bpbkar functions are merged into BPCDW32.

The server processes are the same as described for UNIX.




Backups and Archives - Windows NT/2000 Clients

NetBackup supports the same types of operations on Windows NT/2000 clients as it does for UNIX clients.

The next figure shows the Windows NT/2000 client processes. On this figure:

- ◆ NBWIN is the user interface program on the client. The bpbbackup, bpbarchive, and bplist functions are merged into NBWIN.
- ◆ BPINETD serves the same purpose as inetd on UNIX clients.
- ◆ The NetBackup client daemon is called BPCD.
- ◆ BPBKAR32 serves the same purpose as bpbkar on UNIX clients.

The server processes are the same as described for UNIX.



Backups and Archives - NetWare Clients


NetBackup supports the same types of operations on NetWare clients as it does on UNIX clients, with the following exceptions:

- ◆ Raw partition backups are not supported.
- ◆ NetBackup for NetWare does not support archiving.

The next figure shows the NetWare client processes. On this figure:


- ◆ For NetWare nontarget, the user interface program is called NBNW95 on Windows 95 and 98 clients and NBNWNT on Windows NT/2000. For NetWare target, the user interface program is called BP on the Netware console. The bpbbackup, bparchive, and bplist functions are merged into the user interface programs on the clients.
- ◆ The NetBackup NetWare client daemon is called BPCD. The bpbkar functions are merged into BPCD.

The server processes are the same as described for UNIX.



Backups - Macintosh Clients

NetBackup supports the same types of operations on Macintosh clients as it does for UNIX clients. The next figure shows the client processes involved in backing up a Macintosh. The server processes are the same as described for UNIX.



- ◆ NetBackupBPBACKUP is a faceless background application that NetBackup launches in order to start a user-directed backup.
- ◆ The application extension, NetBackupListen, starts executing when the Macintosh is booted and listens on the BPCD port number for backup requests from a NetBackup server. When NetBackupListen gets a request, it launches the faceless background application NetBackupBPCD.
- ◆ NetBackupBPCD handles the request in the same way as the UNIX bpcd. NetBackupBPCD also includes bpbkar functionality.

The archive that the Macintosh client generates is essentially the same as the archive from a UNIX client. One difference is that the Macintosh file names may be slightly different in the NetBackup archive (see the *NetBackup User's Guide - Macintosh* for an explanation of the differences).



NetBackup Database Backups

The administrator can use an option in the administrator interface to start a manual backup of the NetBackup databases or configure NetBackup to automatically back up its databases (Figure 9).

It is possible to configure automatic database backups to occur either:

- ◆ After each scheduled backup session that results in the creation of at least one backup image.

Or

- ◆ After scheduled, user-directed, or manual backup or archive sessions that result in the creation of at least one backup or archive image.

For automatic database backups, NetBackup uses the scheduler, `bpsched`, to determine if any backups are required. The scheduler is activated by the request daemon, `bprd`, at intervals determined by the `Wakeup Interval` global attribute. If a backup is needed, `bpsched` uses the client daemon, `bpcd`, to start the database backup program, `bpbackupdb`.


For a manual database backup, NetBackup invokes `bpbackupdb` directly, without going through `bprd` or the scheduler.

Once started, `bpbackupdb`:

1. Queries `bpdbm` for the database paths to back up and the media ID to use for the backup.
2. Starts the tape and optical manager, `bptm`, and sends it the media ID in a special mount request.

The tape and optical manager, `bptm`, recognizes the request as being for a database backup and checks the database to ensure that the media ID is not one used for regular backups. The `bptm` program then includes the media ID in a request to the Media Manager device daemon, `ltid`. The device daemon finds the media and causes it to be mounted on an appropriate device.

Figure 9. NetBackup Database Backup



3. Starts the actual backup by using **bpcd** to start the backup program, **bpbkar**.

If the database is on the master server, **bpbakdbp** starts the backup and archive program on the master server. If the database is on a media server, **bpbakdbp** starts the backup and archive program on the media server.

The **bpbkar** program transmits file information and the backup image to separate **bpbakdbp** processes as shown on Figure 9.

- ◆ The original **bpbakdbp** process receives the backup image and sends it to the backup device.



- ◆ A second `bpbbackupdb` process checks the file information to ensure that the proper files are being backed up.

The entire database backup must fit on a single tape. The `bpbbackupdb` process is unable to span tapes and there is no mechanism for specifying multiple tapes for an NetBackup database backup.

If any part of the database backup fails, then NetBackup discards the entire backup. This is done because you must have a backup of *all* the databases to be certain that you have a consistent database.

Restore Processes

NetBackup restore operations, like backups, can vary according to client type. The following explains the basic variations.


Restores - UNIX Clients

Before starting a restore operation, a user will usually browse the file database and list the files available in the backup images. The desired files can then be selected from the list.

The browsing is done through the `bplist` program on the client. The `bplist` program can be started directly from the command line and is used by the NetBackup user interface programs.

`bplist` obtains the file list by sending a query to the request daemon, `bprd`, on the master server (Figure 10). The request daemon, in turn, queries `bpdbrm` for the information and transmits it to `bplist` on the client.

Figure 10. List Operation - UNIX Client



When the user starts a restore, NetBackup invokes the client's `bprestore` program which sends a request to the request daemon, `bprd` (Figure 11). This request identifies the files and client. The request daemon then uses `bpcd` (client daemon) to start the backup/restore manager (`bpbbrm`).

If the storage unit on which the files reside attaches to the master server, then `bprd` starts the backup/restore manager on the master server. If the storage unit connects to a media server, `bprd` starts the backup/restore manager on the media server.


The backup/restore manager starts the appropriate media manager process (`bptm` for tape or optical or `bpdm` for disk) and uses the client daemon (`bpcd`) to establish a connection between the NetBackup `tar` program on the client and `bptm` or `bpdm` on the server.

The `bptm` (for tape or optical) or `bpdm` (for disk) process obtains the location of the data (media ID or file path) and then starts retrieving data. During retrieval, the original `bptm` or `bpdm` process stores the image block by block in shared memory. A second `bptm` or `bpdm` process transmits the image to the client.

- ◆ If the storage is tape or optical, `bptm` includes the media ID in a `tpreq` command to the Media Manager device daemon, `ltid`. The device daemon finds the physical media and causes it to be mounted on an appropriate device. The `bptm` program reads the image and directs it to the client, where the NetBackup `tar` program writes it on the client disk.
- ◆ If the storage unit is disk, `bpdm` uses the file path in a read request to the system disk manager. The image is then read from disk and transmitted to the client, where the NetBackup `tar` program writes it on the client disk. Only the part of the image that is required to satisfy the restore request is sent to the client, not necessarily the entire backup image.



Figure 11. Restore operation From Tape or Optical




Restores - Windows 95/98 Clients

NetBackup supports the same types of restore operations on Windows 95 and 98 clients as it does for UNIX clients. The next figure shows the client processes involved in these operations. On this figure:

- ◆ The user interface program on Windows 95/98 is called NBWIN. The `bprestore` and `bplist` functions are merged into NBWIN.
- ◆ The NetBackup client daemon is called BPCDW32. The NetBackup `tar` functions are merged into BPCDW32.

The server processes are the same as described for UNIX.




Restores - Windows NT/2000 Clients

NetBackup supports the same types of operations on Windows NT/2000 clients as it does for UNIX clients. The next figure shows the client processes involved in these operations.

- ◆ The user interface program on Windows NT/2000 is called **NBWIN**.
- ◆ **BPINETD** is part of NetBackup for Windows NT/2000 and serves the same purpose as **inetd** on UNIX.
- ◆ The NetBackup client daemon is called **BPCD**.
- ◆ **TAR32** is part of NetBackup for Windows NT/2000 and serves the same purpose as NetBackup **tar** on UNIX.

The server processes are the same as described for UNIX.




Restores - NetWare Clients

NetBackup supports the same types of restore operations on NetWare clients as it does on UNIX clients. The next figure shows the client processes involved in these operations. On this figure:


- ◆ The NetWare nontarget user interface program is called **NBNW95** on Windows 95 and 98 clients and **NBNWNT** on Windows NT/2000 clients. The NetWare target user interface program is **BP** on the Netware console. The **bprestore** and **bplist** functions are merged into the user interface programs on the clients.
- ◆ The NetBackup NetWare client daemon is called **BPCD**. The NetBackup **tar** functions are merged into **BPCD**.

The server processes are the same as described for UNIX.



Restores - Macintosh Clients

NetBackup supports the same types of operations on Macintosh clients as it does for UNIX clients. The next figure shows the client processes involved in restoring files to a Macintosh.



- ◆ NetBackupBPSTORE is a faceless background application that NetBackup launches in order to start a user-directed restore.
- ◆ NetBackupCLIMAGELIST is a faceless background application that NetBackup launches in order to get a list of backup images from the master server.
- ◆ NetBackupBPLIST is a faceless background application that NetBackup launches in order to get a list of backed up files from the master server.
- ◆ The application extension NetBackupListen starts executing when the Macintosh is booted and listens on the BPCD port number for backup requests from a NetBackup server. When NetBackupListen gets a request, it launches the faceless background application NetBackupBPCD.
- ◆ NetBackupBPCD handles the request in the same way as the UNIX bpcd. NetBackupBPCD also includes NetBackup tar functionality.

The server processes are the same as described for UNIX.

NetBackup Directories and Files

Figure 12 shows the NetBackup file and directory structure on UNIX servers and clients. If a host is only a client and not a server, then only the files in the lower part of Figure 12 are present. If a host is both a client and a server, the client component shares files as necessary from those in the upper part of Figure 12.

A Windows NetBackup server has equivalent files and directories that are located in the directory where NetBackup is installed (C:\Program Files\Veritas by default).

Table 5 describes the files and directories that are of special interest.

Figure 12. NetBackup Directories and Files - UNIX Servers and Clients




Table 5. NetBackup Directories and Files - Servers and UNIX Clients

File or Directory	Contents
bin	<p>Commands, scripts, programs, daemons, and files required for NetBackup operation and administration. On a server, there are two subdirectories under bin.</p> <p>admincmd: Contains various commands used internally by NetBackup. Use these commands <i>ONLY</i> if they are documented. Most of these commands are not documented and should not be used directly.</p> <p>goodies (UNIX only): Contains scripts and information that may be useful to the administrator.</p> <p>These subdirectories are not present on clients.</p>
bp.conf	<p>Configuration file where you can specify various options for NetBackup operation. The <i>NetBackup System Administrator's Guide</i> has a detailed explanation of each option and how to set it. On a Windows server, these options are set in the interface.</p>
client	<p>NetBackup client software that is installed on the clients during the installation process. Do not install this directory on a media server.</p>
db	<p>NetBackup databases as described in Table 7.</p>
exclude_list	<p>On UNIX clients, this file contains a list of files and directories to exclude from scheduled backups. The <i>NetBackup System Administrator's Guide</i> explains how to use this file.</p>
help	<p>Help files used by NetBackup programs. These files are in ASCII format.</p>
include_list	<p>On UNIX clients, this file contains a list where you can specify a subset of the exclude list to add back into scheduled backups. The <i>NetBackup System Administrator's Guide</i> explains how to use this file.</p>
logs	<p>Detailed debug logs for NetBackup processes. You must create the necessary subdirectories in order for these log files to be written (see Chapter 3Chapter 3). See Table 6 for an explanation of the processes that produce the logs.</p>
release_notes	<p>NetBackup release notes in ASCII format, so you can conveniently view or print them.</p>
version	<p>Version and release date of the software.</p>

NetBackup Programs and Daemons

Table 6 describes the programs and daemons that provide most of the control for backup, archive, and restore operations. The explanations include what starts and stops the program or daemon, and the debug log subdirectory (if any) where it records its activities. (You must create the subdirectory manually; see “logs” in the previous table, and Chapter 3Chapter 3.)

Table 6. NetBackup Daemons and Programs

Program/ Daemon	Description
bp	<p>On UNIX clients, this menu-driven, character-based interface program has options for starting user-directed backups, restores, and archives.</p> <p>Started By: <code>/usr/opensv/netbackup/bin/bp</code> command on the client.</p> <p>Stopped By: Exiting the interface program.</p> <p>Debug Log: <code>/usr/opensv/netbackup/logs/bp</code> on the client. The debug logs for <code>bpbkup</code>, <code>bparchive</code>, <code>bprestore</code>, and <code>bplist</code> also have information about <code>bp</code> activities.</p>
BP.NLM	<p>On NetWare target clients, this is the NetWare Loadable Module that starts the client-user interface.</p> <p>Started By: <code>LOAD BP</code> command.</p> <p>Stopped By: Choosing Quit Utility from the main menu.</p> <p>Debug Log: <code>SYS:\OPENV\NETBACK\LOGS\BP\mmdyy.log</code> file on the client.</p>
bpadm	<p>On a UNIX master server, this administrator utility has a menu-driven, character-based, interface with options for configuring and managing NetBackup.</p> <p>Started By: <code>/usr/opensv/netbackup/bin/bpadm</code> command on the master server.</p> <p>Stopped By: Quit option from within <code>bpadm</code>.</p> <p>Debug Log: <code>admin.log</code> on the server.</p>
bparchive	<p>On UNIX clients, this program communicates with <code>bprd</code> on the master server when a user starts an archive.</p> <p>Started By: Starting an archive by using the client-user interface or executing the <code>/usr/opensv/netbackup/bin/bparchive</code> command on the client.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bparchive.log</code> on the client.</p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
bpbackup	<p>On UNIX clients, this program communicates with bprd on the master server when a user starts a backup.</p> <p>Started By: Starting a backup by using the client-user interface or executing the <code>/usr/opensv/netbackup/bin/bpbackup</code> command on the client.</p> <p>Stopped By: Completion of operation</p> <p>Debug Log: <code>bpbackup.log</code> on the client.</p>
bpblr	<p>On UNIX clients, the Block-Level Restore program calls the VfMS mapping methods and is used to restore NetBackup for EMC Fastrax images.</p> <p>Started By: For each NetBackup for EMC Fastrax restore, bpcd starts an instance of bpblr on the client.</p> <p>Stopped By: Completion of restore operation.</p> <p>Debug Log: <code>bpblr.log</code> on the client.</p>
bpbrm	<p>On master and media servers, the Backup/Restore Manager manages the client and media manager processes and uses error status from both to determine the final status of backup or restore operations.</p> <p>Started By: For each backup or restore, bpsched starts an instance of bpbrm on the server with the appropriate storage unit.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bpbrm.log</code> on the server.</p>
bpbkar	<p>On UNIX clients (except Apollos), the Backup/Archive Manager generates the backup images.</p> <p>Started By: bpbrm on the server with the storage unit.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bpbkar.log</code> on the client.</p>
BPBKAR32	<p>On Windows clients, the Backup/Archive Manager generates the backup images.</p> <p>Started By: BPCDW32 on the client.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>BPBKAR.LOG</code> file in the NetBackup logs directory on the client.</p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
bpcd	<p>On UNIX clients, <code>bpcd</code> is the NetBackup client daemon and lets NetBackup start programs on remote hosts (can be UNIX clients or other servers). For example, the server can connect to UNIX clients without requiring <code>.rhosts</code> entries on the remote host. The program is used when <code>bpsched</code> starts <code>bpbrm</code> and when <code>bpbrm</code> communicates with the client.</p> <p>(For a description of the NetBackup client daemon on PC clients, see <code>BPCDW32.EXE</code>, <code>BPCD.NLM</code>, and <code>NetBackupBPCD</code> later in this table.)</p> <p>Started By: <code>inetd</code>.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bpcd.log</code> on both client and server.</p>
BPCD.NLM	<p>On NetWare clients, this is the executable file that starts the NetBackup client daemon.</p> <p>Started By: When you start the Novell NetWare system if you add <code>load bpcd</code> to the <code>AUTOEXEC.NCF</code> file. Otherwise, with the <code>LOAD BPCD</code> command.</p> <p>Stopped By: <code>UNLOAD BP</code> command</p> <p>Debug Log: <code>BPCD.LOG</code> file in the NetBackup logs directory on the client.</p>
BPCDW32.EXE	<p>On Windows 95 and NT/2000 clients, this is the executable file that starts the NetBackup client daemon.</p> <p>Started By: When Windows starts if the daemon is in the Startup group. Otherwise, by double clicking on its icon.</p> <p>Stopped By: On Windows NT/2000, you can stop it through the Services application in the Control Panel. On Windows 95, you can stop it by clicking on its icon and choosing Close.</p> <p>Debug Log: <code>BPCD.LOG</code> file in the NetBackup logs directory on the client.</p>
bpdbjobs	<p>On UNIX master servers, this program is used to clean up the NetBackup jobs database.</p> <p>Started By: <code>/usr/opensv/netbackup/bin/admincmd/bpdbjobs</code>. When <code>bprd</code> starts, it runs this command automatically. The administrator can also execute it manually or with a <code>cron</code> job.</p> <p>Stopped By: There is no terminate option for this command outside of using <code>kill</code>.</p> <p>Debug Log: <code>bpdbjobs.log</code> on the server.</p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
bpdbm	<p>On master servers, the NetBackup database manager program that manages the configuration, error, and file databases.</p> <p>Started By: bprd (also by <code>/usr/opensv/netbackup/bin/initbpdbm</code> on UNIX)</p> <p>Stopped By: <code>/usr/opensv/netbackup/bin/bpdbm -terminate</code> command on UNIX and by stopping the NetBackup Database Manager service on Windows.</p> <p>Debug Log: <code>bpdbm.log</code> on the server.</p>
bpdm	<p>On master and media servers, <code>bpdm</code> is the disk-media manager and is used when the storage unit type is a disk. This program manages the transfer of images between the client and the operating-system disk manager on the server to which the disk attaches.</p> <p>Started By: For each backup or restore, <code>bpbrm</code> starts an instance of <code>bpdm</code>, on the server with the storage unit.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bpdm.log</code> on the server.</p>
bphdb	<p>On UNIX database-extension clients, <code>bphdb</code> starts the NetBackup hot-database-backup program (see the applicable NetBackup installation guide for more information).</p> <p>Started By: Client-user interface when the user starts a database backup or restore operation.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: <code>bphdb.log</code> on the client. With NetBackup for Oracle, <code>bphdb</code> also writes to <code>/usr/opensv/netbackup/logs/obackup_tape</code>.</p>
bpjava-msvc	<p>NetBackup-Java master server application program. This program runs on all NetBackup UNIX systems and authenticates users that start the NetBackup-Java interface programs.</p> <p>Started By: <code>inetd</code> during startup of the NetBackup Java interfaces.</p> <p>Stopped By: When authentication is complete.</p> <p>Debug Log: <code>/usr/opensv/netbackup/logs/bpjava-msvc</code></p>

Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
bpjava-usvc	<p>NetBackup-Java user server application program. This program services all requests from the NetBackup-Java user and administration interfaces.</p> <p>Started By: bpjava-msvc upon successful login through the Login dialog box that is presented when a NetBackup-Java interface is started.</p> <p>Stopped By: When the interface program is terminated.</p> <p>Debug Log: /usr/opensv/netbackup/logs/bpjava-usvc</p>
bprd	<p>On master servers, the request daemon responds to client and administrative requests for the following:</p> <ul style="list-style-type: none"> ◆ Restores ◆ Backups (scheduled and user-directed) ◆ Archives ◆ List backed up or archived files ◆ Manual immediate backups (started through the NetBackup administration interface manual backup option) <p>Started By: Initiate Request Daemon option in the NetBackup administrator interface (also the /usr/opensv/netbackup/bin/initbprd command).</p> <p>Stopped By: Terminate Request Daemon option in the NetBackup administrator interface.</p> <p>Debug Log: bprd.log on the server.</p>
bplist	<p>On UNIX clients, this program communicates with bprd on the master server when a user browses the database during a restore operation.</p> <p>Started By: Starting a search of the image database by using the client-user interface or executing the /usr/opensv/netbackup/bin/bplist command on the client.</p> <p>Stopped By: Completion of operation</p> <p>Debug Log: bplist.log on the client.</p>
bprestore	<p>On UNIX clients, this program communicates with bprd on the master server when a user starts a restore.</p> <p>Started By: Starting restore by using the client-user interface (or by executing the /usr/opensv/netbackup/bin/bprestore command on the client).</p> <p>Stopped By: Completion of operation</p> <p>Debug Log: bprestore.log on the client.</p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
bpsched	<p>On master servers, the Scheduler uses policy information from the NetBackup configuration databases to determine:</p> <ul style="list-style-type: none"> ◆ Clients to start and when to start them. ◆ Storage units to use for backups and archives. <p>Started By: bprd for the following operations:</p> <ul style="list-style-type: none"> ◆ User-directed backups and archives ◆ Immediate manual backups (started through the option that is available in the NetBackup administrator interface) ◆ Scheduled automatic incremental or full backups. In this case, bprd starts the scheduler at intervals determined by the wakeup interval global attribute. <p>Stopped By: Completion of all backups that are due.</p> <p>Debug Log: bpsched.log on the server.</p>
bptm	<p>On master and media servers, bptm is the tape-media manager and is used when the storage unit type is Media Manager. This program manages transfer of images between the client and the storage device. It also handles communication between the backup and Media Manager software. In addition, bptm manages the NetBackup media database and provides information for the media list report screen.</p> <p>Started By: For each backup or restore, bpbm starts an instance of bptm on the server that has the storage unit.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: bptm.log on the server.</p>
BPSRV.EXE	<p>On NetWare nontarget clients, this is the program that allows the system that has the client-user interface to communicate with the Netware server that is the NetBackup client.</p> <p>Started By: Starting NetBackup for NetWare.</p> <p>Stopped By: Exiting the client-user interface.</p> <p>Debug Log: BPSRV.LOG file in the NetBackup LOGS directory on the client.</p>
BPSYS.EXE	<p>On Windows NT/2000 clients, this is the NetBackup System Registry Replacement utility.</p> <p>Started By: NetBackup as required.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: BPSYS.LOG file in the NetBackup LOGS directory on the client.</p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
jbpSA	<p>A Java-based program for performing backups, archives and restores of UNIX clients.</p> <p>Started By: On UNIX, the <code>/usr/opensv/netbackup/bin/jbpSA</code> command.</p> <p>Debug Log: None, although the log for the <code>bpbbackup</code>, <code>bparehve</code>, <code>bplist</code>, and <code>bprestore</code> commands on the client can be useful. Also, the logs for <code>bpjava-msvc</code> and <code>bpjava-usvc</code> can be helpful.</p>
jnbSA	<p>A Java-based administration utility for managing NetBackup and Media Manager on UNIX. In addition, administration of supported UNIX systems can be performed by using the NetBackup-Java Windows Display Console on a Windows system.</p> <p>Started By: On UNIX, the <code>/usr/opensv/netbackup/bin/jnbSA</code> command. On a NetBackup-Java Windows Display console, the NetBackup - Java on <i>host</i> menu item on the Programs/NetBackup menu.</p> <p>Stopped By: Exit option in <code>jnbSA</code>.</p> <p>Debug Log: None, although the logs for <code>bpjava-msvc</code> and <code>bpjava-usvc</code> can be helpful.</p>
ndmpmoveragent	<p>On the NetBackup media server (UNIX), this daemon acts as an NDMP server in a type of three-way backup called Remote NDMP.</p> <p>Started By: Executing <code>/usr/opensv/volmgr/bin/ndmpmoveragent.start</code>.</p> <p>Stopped By: Executing <code>/usr/opensv/volmgr/bin/ndmpmoveragent.stop</code>.</p> <p>Debug Log: <code>/usr/opensv/netbackup/logs/ndmpmoveragent</code></p>
NDMP Mover Agent	<p>On the NetBackup media server (Windows), this service acts as an NDMP server in a type of three-way backup called Remote NDMP.</p> <p>Started By: Executing <code>install_path/netbackup/bin/InstallNdmpMoverAgent path_of_NetBackup_binaries</code></p> <p>Stopped By: Executing <code>install_path/netbackup/bin/InstallNdmpMoverAgent -r</code>.</p> <p>Debug Log: <code>install_path/netbackup/logs/ndmpmoveragent</code></p>



Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
NBWIN.EXE	<p>For Windows clients, this is the executable file that starts the client-user interface on Windows systems.</p> <p>Started By: From the Windows Start menu, under Programs/NetBackup.</p> <p>Stopped By: Exiting the client-user interface.</p> <p>Debug Log: <i>mmddy.log</i> file in the NBWIN directory on the client.</p>
NBNWNT.EXE	<p>For NetWare nontarget clients, this is the executable file that starts the client-user interface on Windows systems.</p> <p>Started By: From the Windows Start menu, under Programs/NetBackup.</p> <p>Stopped By: Exiting the client-user interface.</p> <p>Debug Log: none.</p>
NBNW95.EXE	<p>For NetWare nontarget clients, this is the executable file that starts the client-user interface on Windows 98/95 systems.</p> <p>Started By: From the Windows Start menu, under Programs/NetBackup.</p> <p>Stopped By: Exiting the client-user interface.</p> <p>Debug Log: none.</p>
NetBackupBPCD	<p>A faceless background application installed in the <code>System:Extensions</code> folder on the startup volume of a Macintosh client. The Macintosh equivalents of the UNIX <code>bpbkar</code> and <code>tar</code> commands are merged into NetBackupBPCD.</p> <p>Started By: When NetBackupListen receives a request from a server it launches NetBackupBPCD.</p> <p>Stopped By: Completion of operation.</p> <p>Debug Log: Log files in the <code>System:Preferences:NetBackup:bpcd</code> folder, which is in the NetBackup folder, in the Preferences folder, in the System folder on the startup volume.</p>

Table 6. NetBackup Daemons and Programs (continued)

Program/ Daemon	Description
NetBackupListen	<p>An applications extension installed in the <code>System:Extensions</code> folder on the startup volume of a Macintosh client. It starts when the Macintosh is booted and runs in the background until the Macintosh is shut down. NetBackupListen listens on the BPCD port number for requests from NetBackup servers and launches NetBackupBPCD when a request is received.</p> <p>Started By: When the Macintosh boots.</p> <p>Stopped By: When the Macintosh is shut down.</p> <p>Debug Log: Log files in the <code>System:Preferences:NetBackup:inetd</code> folder on the startup volume.</p>
tar	<p>On UNIX clients, the Tape ARchive program is a special version of <code>tar</code> provided with NetBackup and used to restore images.</p> <p>Started By: For each restore, <code>bpbrm</code> starts an instance of <code>tar</code> on the client.</p> <p>Stopped By: Completion of restore operation.</p> <p>Debug Log: <code>tar.log</code> on the client.</p>
TAR32	<p>On Windows clients, the TAR32 program is a special version of <code>tar</code> provided with NetBackup and used to restore images.</p> <p>Started By: For each restore, NetBackup starts an instance of TAR32 on the client.</p> <p>Stopped By: Completion of restore operation.</p> <p>Debug Log: <code>TAR.LOG</code> in the NetBackup logs directory on the client.</p>
xbp	<p>Graphical display based client-user interface, on UNIX clients, with options for starting user-directed backups, restores, and archives. Functionally, it is very similar to the menu version, <code>bp</code>.</p> <p>Started By: <code>/usr/openv/netbackup/bin/xbp</code> command on the client.</p> <p>Stopped By: Quit option in <code>xbp</code>.</p> <p>Debug Log: None, although the log for the <code>bpbackup</code>, <code>bparchive</code>, <code>bplist</code>, and <code>bprestore</code> commands on the client may also be useful for debugging problems with <code>xbp</code>.</p>



NetBackup Databases

Table 7 describes the NetBackup databases. These databases contain information that is used internally by NetBackup and reside in the `/usr/opensv/netbackup/db` directory on UNIX servers and in the `install_path\NetBackup\db` directory on Windows NetBackup servers.

Table 7. NetBackup Databases

Database	Contents
config	Configuration information. This database resides on the master server and has three parts: policy: Contains information about each NetBackup policy. config: Contains information about global attributes, storage units, and database backups. altnames: Contains information about client names for restores.
error	Error and status information about NetBackup operations. This database resides on the master server and has two parts: error: Contains information recorded during backup operations and used in the NetBackup reports. failure_history: Contains daily history of backup errors.
images	Information about the backup images and resides only on the master server. One of the files in the <code>images</code> directory is the <code>file</code> database. The <code>file</code> database is the one that NetBackup accesses when a user browses for files to restore.
jobs	Job information that is used by the NetBackup job monitor (UNIX NetBackup server) and activity monitor (Windows NetBackup server). The Jobs database is on the master server
media	Media related information used by <code>bptm</code> . Each master or media server has a media database with media information for the images stored on that server's storage units. The media database also has an errors file that contains error history information for media and devices.

Media Manager Functional Description

This section explains the operation of Media Manager software and contains the following discussions:

- ◆ Startup Process
- ◆ Media and Device Management Process
- ◆ Barcode Operations



◆ Media Manager Components

Note In this section, the term Media Manager refers to the media and device management software that is part of NetBackup on either a UNIX or Windows NetBackup server.

Startup Process

Media Manager is part of NetBackup but, on UNIX, can also be run independently and used by other applications, such as Storage Migrator. The easiest way to start Media Manager is to initiate all the necessary processes during system startup on all servers that have devices under control of Media Manager.

`ltid` automatically starts other daemons and programs as necessary. Figure 13 shows the Media Manager daemons that should be running after initial startup. In the case of robotic daemons, such as `ts8d` and `rsmd`, the associated robot must also be configured for the daemon to run. See Table 9 for other ways to start and stop these daemons.


As shown on Figure 13, the LMF, TL8, TLH, and TLD, require two types of daemons: robotic and robotic control.

- ◆ Each host with a robotic drive attached must have a robotic daemon. These daemons provide the interface between `ltid` and the robot or, if different drives within a robot can attach to different hosts, the robotic daemon communicates with a robotic-control daemon (see below).
- ◆ Robotic-control daemons centralize the control of robots when drives within a robot can connect to different hosts. A robotic-control daemon receives mount and unmount requests from the robotic daemon on the host to which the drive is attached and then communicates these requests to the robot.

You must know the hosts involved in order to start all the daemons for a robot.



Figure 13. Starting Media Manager



Media and Device Management Process

When the Media Manager daemons are running, NetBackup, Storage Migrator (UNIX only), Storage Migrator for Microsoft Exchange (Windows only), or other users can initiate data storage or retrieval by sending a request for the required media ID to the Media Manager device daemon, `ltid` (Figure 14). `ltid` determines the location of the requested media ID by sending a query to the Media Manager volume daemon, `vmd`. The volume daemon then returns the information it has about the media, including: robot number, robot type, host, slot, and barcode.

If the media is in a robot, `ltid` sends a mount request to the robotic daemon that manages the drives in the robot that are configured on the local host. The robotic daemon then chooses an available drive, mounts the media, and sets a drive busy status in memory shared by itself and `ltid`. If it receives another mount request, `ltid` checks that status to determine which (if any) drives are available. Drive busy status also appears in the Device Monitor.

Assuming that the media is physically in the robot, the media is mounted and the operation proceeds. If not a NetBackup backup job and the media is not in the robot, `ltid` sends a mount request, which appears as a pending request in the Device Monitor. An operator must then insert the media in the robot and use the appropriate Device Monitor command to resubmit the request so the mount request can occur. For a NetBackup job, if the media is not in the robot, `ltid` sends a mount request which is then canceled once the media is determined to be missing and another volume is selected to be mounted.

A mount request is also issued if the media is for a nonrobotic (standalone) drive and the drive does not contain media that meets the criteria in the request. If the request is from NetBackup and the drive does contain appropriate media, then that media is automatically assigned and the operation proceeds. See the *NetBackup System Administrator's Guide* for more information on NetBackup media selection for nonrobotic drives.


Note When a tape is being mounted, the `drive_mount_notify` script is called. This script is in the `/usr/opensv/volmgr/bin` directory. Information on the script can be found within the script itself. A similar script is called for the unmount process (`drive_unmount_notify`, in the same directory).

When a robotic volume is added or removed through the media access port, the media management utility communicates with the appropriate robotic daemon to verify the volume location and/or barcode. The media management utility (through a library or command-line interface) also calls the robotic daemon for robot inventory operations.



Media Manager Functional Description

Figure 14. Media and Device Management Example Process



Barcode Operations

Barcode reading is mainly a function of the robot hardware rather than Media Manager. When a robot has a barcode reader, it scans any barcode that may be on a tape and stores the code in its internal memory. This associates the slot number and the barcode of the tape in that slot. Media Manager determines that association for its own use by interrogating the robot.

If a robot supports barcodes, Media Manager automatically compares a tape's barcode to what is in the volume database as an extra measure of verification before mounting the tape.

Media Requests Involving Barcodes


A request for media that is in a robot that can read barcodes begins in the same manner as other requests (see Figure 15). The Media Manager device daemon, `ltid`, determines the location of the requested media ID by querying the Media Manager volume daemon, `vmd`. The volume daemon then returns the information it has about the media, including: robot number, robot type, host, slot, and barcode.

`ltid` includes the media ID and location information in a mount request to the robotic daemon for the robot that has the media ID. This request causes the robotic daemon to query the robotic-control daemon or the robot for the barcode of the tape in the designated slot. (This is a preliminary check to see if the correct media is in the slot). The robot returns the barcode value it has in memory. The robotic daemon compares this barcode with the value it received from `ltid` and takes one of the following actions.

- ◆ If the barcodes don't match, and the mount request is not for a NetBackup backup job, the robotic daemon informs `ltid` and a pending action request (Misplaced Tape) appears in the Device Monitor. An operator must then insert the correct tape in the slot.
- ◆ If the barcodes don't match and the mount request is for a NetBackup backup job, the robotic daemon informs `ltid` and the mount request is canceled. NetBackup (`bptm`) then selects another volume to mount.
- ◆ If the barcodes match, the robotic daemon requests the robot to move the tape to a drive. The robot then mounts the tape. At the start of the operation, the application (for example, NetBackup) checks the media ID and if it also matches what should be in this slot, the operation proceeds. For NetBackup, a wrong media ID results in a "media manager found wrong tape in drive" error (NetBackup status code 93).



Figure 15. Barcode Request




Media Manager Components

Media Manager Directories and Files

Figure 16 shows the file and directory structure for Media Manager on a UNIX server. A Windows NetBackup server has equivalent files and directories that are located in the directory where NetBackup is installed (C:\Program Files\Veritas by default).

Table 8 describes the directories and files that are of special interest.

Figure 16. Media Manager Directories and Files



1 Created by administrator to enable debug logging.

2 Created by administrator or automatically by media management utilities.



Media Manager Functional Description

Caution *DO NOT* under any circumstances attempt to modify the Media Manager databases. These files are for internal program use only and changing them will result in program failure and possible loss of data. It is also recommended that they not be moved to another host.

Table 8. Media Manager Directories and Files

File or Directory	Contents
bin	<p>Commands, scripts, programs, daemons, and files required for Media Manager operation and administration. There are three subdirectories under bin.</p> <p>driver: Contains SCSI drivers used on various platforms to control robotics.</p> <p>format: Disk format information for optical platters on Solaris platforms.</p> <p>goodies: Contains vmconf script and scan utility.</p>
database	<p>Media Manager databases contain information about the drives, robots, and media that are under Media Manager control.</p> <p>The volume database that usually resides on the master server contains volume information for multiple media servers.</p>
debug	<p>Debug logs for the Media Manager volume daemon, vmd, and all requesters of vmd, ltid, and device configuration. The administrator must create these directories for debug logging to occur.</p>
help	<p>Help files used by Media Manager programs. These files are in ASCII format.</p>
version	<p>Version and release date of the software.</p>
vm.conf	<p>Media manager configuration options.</p>
misc	<p>Lock files and temporary files required by various components of Media Manager.</p>

Programs and Daemons

Table 9 describes the Media Manager programs and daemons. The explanations include what starts and stops the program or daemon, and the log (if any) where it records its activities. On UNIX, all of the components discussed in this table reside under /usr/opensv/volmgr/bin. On Windows, they reside under *install_path*\volmgr\bin.



Table 9. Media Manager Daemons and Programs

Program/ Daemon	Description
acsd	<p>The Automated Cartridge System daemon interfaces with the Automated Cartridge System and communicates with the server that controls the ACS robotics through the <code>acsssi</code> process (UNIX) or the STK Libattach Service (Windows). Also, for UNIX see the <code>acsssi</code> and <code>acsse1</code> programs.</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the <code>/usr/openv/volmgr/bin/ascd</code> command).</p> <p>Stopped By: Stopping <code>ltid</code> (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by starting the daemon with the <code>-v</code> option (either by itself or through <code>ltid</code>) or by putting <code>VERBOSE</code> in the <code>vm.conf</code> file.</p>
acsse1	Available only on UNIX. See the <i>Media Manager System Administrator's Guide</i> (UNIX or Windows) for details.
acsssi	Available only on UNIX. See the <i>Media Manager System Administrator's Guide</i> (UNIX or Windows) for details.
avrd	<p>The automatic-volume-recognition daemon controls automatic volume assignment and label scanning. This lets Media Manager read labeled tape and optical disk volumes and to automatically assign the associated removable media to requesting processes.</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the <code>/usr/openv/volmgr/bin/avrd</code> command).</p> <p>Stopped By: Stopping <code>ltid</code>, (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by aborting <code>avrd</code> and starting the daemon with the <code>-v</code> option.</p>



Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
lmfd	<p>The Library Management Facility daemon works in conjunction with <code>lmfcd</code> to handle requests to robots controlled by a Fujitsu Library Management Facility (LMF). <code>lmfd</code> provides the interface between the local <code>ltid</code> and the robotic control (<code>lmfcd</code>) in the same manner as explained later for <code>tl8d</code>. This robot is only available on Solaris.</p> <p>Started By: Starting <code>ltid</code> (or independently by using the <code>/usr/openv/volmgr/bin/lmfd</code> command).</p> <p>Stopped By: Stopping <code>ltid</code> or independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included if the daemon is started with the <code>-v</code> option (either by itself or through <code>ltid</code>) or by adding <code>VERBOSE</code> to the <code>vm.conf</code> file.</p>
ltid	<p>The device demon (UNIX) or NetBackup Device Manager service (Windows) controls the reservation and assignment of tapes and optical disks.</p> <p>Started By: <code>/usr/openv/volmgr/bin/ltid</code> command on UNIX or Stop/Restart Device Management command in Media and Device Management window on Windows.</p> <p>Stopped By: <code>/usr/openv/volmgr/bin/stoptlid</code> command on UNIX or Stop/Restart Device Manager Service command in the Media and Device Management window on Windows.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included if the daemon is started with the <code>-v</code> option (available only on UNIX) or adding <code>VERBOSE</code> to the <code>vm.conf</code> file.</p>
odld	<p>The Optical Disk Library daemon interfaces with the Optical Disk Library, communicating with the robotics through a SCSI interface. This library is not supported on Windows.</p> <p>Started By: Starting <code>ltid</code> or independently by using the <code>/usr/openv/volmgr/bin/odld</code> command.</p> <p>Stopped By: Stopping <code>ltid</code> or independently by finding the PID (process id) and then using the <code>kill</code> command.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included if the daemon is started with the <code>-v</code> option (either by itself or through <code>ltid</code>) or adding <code>VERBOSE</code> to the <code>vm.conf</code> file.</p>

Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
rsmd	<p>The Removable Storage Manager daemon is the interface between <code>ltid</code> and the Microsoft Windows 2000 Removable Storage Manager (RSM) interface. The <code>rsmd</code> daemon runs only on Windows 2000 systems; note that the system must have drives configured in RSM robots configured in the Media Manager interface.</p> <p>Started By: Starting <code>ltid</code> on Windows 2000 only.</p> <p>Stopped By: Stopping <code>ltid</code> on Windows 2000 only.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included in the system log as notifications.</p>
tl4d	<p>The Tape Library 4MM daemon is the interface between <code>ltid</code> and the Tape Library 4MM and communicates with the robotics through a SCSI interface.</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the <code>/usr/openv/volmgr/bin/tl4d</code> command).</p> <p>Stopped By: Stopping <code>ltid</code> (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by starting the daemon with the <code>-v</code> option (either by itself or through <code>ltid</code>).</p>
tl8d	<p>The Tape Library 8MM daemon drives in the same TL8 robot may be attached to different hosts than the robotic control. <code>tl8d</code> is the interface between the local <code>ltid</code> and the robotic control. If a host has a device path for a drive in a TL8 robot, then mount or unmount requests for that drive go first to the local <code>ltid</code> and then to the local <code>tl8d</code> (all on the same host). <code>tl8d</code> then forwards the request to <code>tl8cd</code> on the host that is controlling the robot (could be on another host).</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the <code>/usr/openv/volmgr/bin/tl8d</code> command).</p> <p>Stopped By: Stopping <code>ltid</code> (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by starting the daemon with the <code>-v</code> option (either by itself or through <code>ltid</code>).</p>



Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
tl8cd	<p>The Tape Library 8MM Control daemon provides the robotic control for a TL8 robot and communicates with the robotics through a SCSI interface. tl8cd receives mount and unmount requests from tl8d on the host to which the drive is attached and then communicates these requests to the robot.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the /usr/opensv/volmgr/bin/tl8cd command).</p> <p>Stopped By: Stopping ltid or by using the tl8cd -t command.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding VERBOSE to the Media Manager configuration file, vm.conf. On UNIX, debug information is also included by starting the daemon with the -v option (either by itself or through ltid).</p>
tldd	<p>The Tape Library DLT daemon works in conjunction with tldcd to handle requests to TLD robots. tldd provides the interface between the local ltid and the robotic control (tldcd) in the same manner as explained previously for tl8d.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the /usr/opensv/volmgr/bin/tldd command).</p> <p>Stopped By: Stopping ltid (or on UNIX, independently by finding the PID (process id) and then using the kill command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding VERBOSE to the Media Manager configuration file, vm.conf. On UNIX, debug information is also included by starting the daemon with the -v option (either by itself or through ltid).</p>
tldcd	<p>The Tape Library DLT Control daemon provides robotic control for a TLD robot in the same manner as explained previously for tl8cd.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the /usr/opensv/volmgr/bin/tldcd command).</p> <p>Stopped By: Using the tldcd -t command. Stopping ltid or by using the tldcd -t command.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding VERBOSE to the Media Manager configuration file, vm.conf. On UNIX, debug information is also included by starting the daemon with the -v option (either by itself or through ltid).</p>



Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
tlhd	<p>The Tape Library Half-inch daemon works in conjunction with tlhcd to handle requests to TLH robots that are in an IBM Automated Tape Library (ATL). tlhd provides the interface between the local ltid and the robotic control (tlhcd) in the same manner as explained previously for t18cd.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the <code>/usr/opensv/volmgr/bin/tlhd</code> command).</p> <p>Stopped By: Stopping ltid (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by starting the daemon with the <code>-v</code> option (either by itself or through ltid).</p>
tlhcd	<p>The Tape Library Half-inch Control daemon provides robotic control for a TLH robot that is in an IBM Automated Tape Library (ATL) in a similar manner to that which was explained previously for t18cd.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the <code>/usr/opensv/volmgr/bin/tlhcd</code> command).</p> <p>Stopped By: Stopping ltid or by using the <code>tlhcd -t</code> command.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included if the daemon is started with the <code>-v</code> option (either by itself or through ltid). The <code>-v</code> option is available only on UNIX. Also, add the <code>VERBOSE</code> option to the <code>vm.conf</code> file.</p>
tlmd	<p>The Tape Library Multimedia daemon is the interface between ltid and a TLM robot that is in an ADIC Distributed AML Server (DAS). This daemon communicates with the TLM robotics through a network API interface.</p> <p>Started By: Starting ltid or independently by using the <code>/usr/opensv/volmgr/bin/tlmd</code> command.</p> <p>Stopped By: Stopping ltid or independently by finding the PID (process id) and then using the <code>kill</code> command.</p> <p>Debug Log: All errors are logged in the system log. Debug information is included if the daemon is started with the <code>-v</code> option (either by itself or through ltid). The <code>-v</code> option is available only on UNIX. Also, add the <code>VERBOSE</code> option to the <code>vm.conf</code> file.</p>



Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
tpconfig	<p>tpconfig is a command line interface or interactive administrator utility for configuring devices under Media Manager. The graphical user interfaces provide equivalent functionality.</p> <p>Started By: tpconfig command.</p> <p>Stopped By: Quit option from within the utility on UNIX. On Windows, tpconfig is only a command-line interface that runs to completion (no quit option).</p> <p>Debug Log: None</p>
tsdd	<p>The Tape Stacker DLT daemon is the interface between ltid and the DLT tape stacker and communicates with the robotics through a SCSI interface.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the /usr/opensv/volmgr/bin/tsdd command).</p> <p>Stopped By: Stopping ltid (or on UNIX, independently by finding the PID (process id) and then using the kill command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding VERBOSE to the Media Manager configuration file, vm.conf. On UNIX, debug information is also included by starting the daemon with the -v option (either by itself or through ltid).</p>
tshd	<p>The Tape Stacker Half-inch daemon is the interface between ltid and the half-inch-cartridge stacker and communicates with the robotics through a SCSI interface. This robot is not supported on Windows.</p> <p>Started By: Starting ltid (or on UNIX, independently by using the /usr/opensv/volmgr/bin/tshd command).</p> <p>Stopped By: Stopping ltid (or on UNIX, independently by finding the PID (process id) and then using the kill command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding VERBOSE to the Media Manager configuration file, vm.conf. On UNIX, debug information is also included by starting the daemon with the -v option (either by itself or through ltid).</p>

Table 9. Media Manager Daemons and Programs (continued)

Program/ Daemon	Description
ts8d	<p>The Tape Stacker 8MM daemon is the interface between <code>ltid</code> and the 8-mm Tape Stacker and communicates with the robotics through a SCSI interface.</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the <code>/usr/openv/volmgr/bin/ts8d</code> command).</p> <p>Stopped By: Stopping <code>ltid</code> (or on UNIX, independently by finding the PID (process id) and then using the <code>kill</code> command).</p> <p>Debug Log: All errors are logged in the system log. Debug information is included by adding <code>VERBOSE</code> to the Media Manager configuration file, <code>vm.conf</code>. On UNIX, debug information is also included by starting the daemon with the <code>-v</code> option (either by itself or through <code>ltid</code>).</p>
vmd	<p>The Media Manager volume daemon (NetBackup Volume Manager service on Windows) manages the volume database, provides <code>ltid</code> with the location of requested volumes, keeps track of the number of mounts and last mount time for each volume, and allows remote administration and control of Media Manager.</p> <p>Started By: Starting <code>ltid</code> (or on UNIX, independently by using the Initiate Media Manager Volume daemon option in <code>vmadm</code>)</p> <p>Stopped By: Terminate Media Manager Volume Daemon option in <code>vmadm</code>.</p> <p>Debug Log: System log and also a debug log if the daemon or <code>reqlib</code> debug directories exist (see “Debug Logs” on page 47).</p>
vmadm	<p>Available only on UNIX. An administrator utility with options for configuring and managing volumes under control of Media Manager. It has a menu-driven, character-based interface that can be used from workstations that do not have graphical display capabilities.</p> <p>Started By: <code>/usr/openv/volmgr/bin/vmadm</code> command</p> <p>Stopped By: Quit option from within the utility.</p> <p>Debug Log: <code>/usr/openv/volmgr/debug/reqlib</code></p>



Media Manager Functional Description



Networks and Hostnames

B

In a configuration with multiple networks and clients with more than one hostname, the NetBackup administrator must configure the policy entries carefully, at all times considering the network configuration (physical, hostnames and aliases, DNS, routing tables, and so on). This is especially true if the desire is to direct backup and restore data across specific network paths.

For a backup, NetBackup connects to the host name as configured in the policy. The operating system's network code resolves this name and sends the connection across the network path defined by the system's routing tables.

For restores from the client, the client connects to the master server. On a Windows system, the master server is specified on the Servers tab of the Specify NetBackup Machines dialog box (to open this dialog, start the NetBackup client user interface and click Specify NetBackup Machines on the Actions menu). The network path to the server is determined by the client's network code that maps the server name to an IP address.

Upon receipt of the connection, the server determines the client's configured name from the *peername* of its connection to the server.

The *peername* is derived from the IP address of the connection. This means that the address must translate into a host name (using the `gethostbyaddr()` network routine). This name is visible in the `bprd` debug log when a connection is made as in the line:

```
Connection from host peername ipaddress ...
```

The client's configured name is then derived from the *peername* by querying the `bpdbm` process (NetBackup Database Manager service).

The `bpdbm` process compares the *peername* to a list of client names generated from:

1. All clients for which a backup has been attempted
- and
2. All clients in all policies

The comparison is first a simple string comparison which, if successful, is verified by comparing hostnames and aliases retrieved by using the network function `gethostbyname()`.



If none of the comparisons succeed, a more brute force method is used, which compares all names and aliases using `gethostbyname()`.

The configured name is the first comparison that succeeds. Note that other comparisons might also have succeeded if aliases or other “network names” are configured.

If the comparison fails, the client’s hostname as returned by the `gethostname()` function on the client is used as the configured name. One example of why the comparison could fail is the case where the client had changed its hostname but its new hostname is not reflected in any policies yet.

These comparisons are logged in the `bpdbm` debug log if `VERBOSE` is set. You can determine a client’s configured name by using the `bpclntcmd` command on the client. For example:

```
# install_path\NetBackup\bin\bpclntcmd -pn
expecting response from server wind.abc.me.com
danr.abc.me.com danr 194.133.172.3 4823
```

Where the first output line identifies the server to which the request is directed and the second output line is the server’s response in the following order:

- ◆ Peername of the connection to the server
- ◆ Configured name of the client
- ◆ IP address of the connection to the server
- ◆ Port number used in the connection

When the client connects to the server, it sends three names to the server:

- ◆ *browse client*
- ◆ *requesting client*
- ◆ *destination client*

The *browse client* name is used to identify the client files to list or restore from. The user on the client can modify this name to restore files from another client. For example, on a Windows client, the user can change the client name by using the client user interface (see the user’s guide for instructions). For this to work, however, the administrator must also have made a corresponding change on the server. For more information, refer to the *NetBackup System Administrator’s Guide for Windows*.

The *requesting client* is the value from the `gethostname()` function on the client.

The *destination client* name is a factor only if an administrator is pushing a restore to a client from a server. For a user restore, *destination client* and *requesting client* are the same. For an administrator restore, the administrator can specify a different name for the destination client.

By the time these names appear in the `bprd` debug log, the requesting client name has been translated into the client's configured name.

Depending on the particulars of the restore request (for example, from root on a server, from a client, to a different client, and so on), the name used to connect back to the client to complete the restore is either the client's peername or its configured name.

When modifying client names in NetBackup policies to accommodate specific network paths, the administrator needs to consider:

- ◆ The client name as configured on the client. On a Windows client, it is on the General tab of the NetBackup Configuration dialog box. To open this dialog box, click Configure on the Actions menu in the Backup, Archive, and Restore interface.
- ◆ The client as currently named in the policy configuration.
- ◆ Existing client backup and archive images as recorded in the `images` directory on the master server. On a Windows NetBackup server this is the `install_path\NetBackup\db\images` directory.

All of the above can require manual modification by the administrator if a client has multiple network connections to the server and restores from the client fail due to a connection-related problem.

If Domain Name Services are used and the (possibly unqualified) name that the NetBackup client obtains through its `gethostbyname()` network function is unknown to the Domain Name Service (DNS) on the master server, the master server can be unable to reply to client requests. Whether this situation exists, depends on how the client and the server are configured. If `gethostbyname()` on the client returns host names that are not qualified to the extent that DNS on the master server can resolve them, then you will encounter problems.

Although a possible solution is to reconfigure the client or the master server DNS hosts file, this is not always desirable. For this reason, NetBackup provides a special file on the master server. This file is:

`install_path\NetBackup\db\altnames\host.xlate`

You can create and edit this file to force the desired translation of NetBackup client host names.

Each line in the `host.xlate` file has three elements: a numeric key and two hostnames. Each line is left-justified, and each element of the line is separated by a space character.

key hostname_from_client client_as_known_by_server

Where

- ◆ *key* is a numeric value used by NetBackup to specify the cases where the translation is to be done. Currently this value must always be 0, indicating a configured name translation.



- ◆ *hostname_from_client* is the value to translate. This must correspond to the name that is obtained by the client's `gethostname()` function and sent to the server in the request.
- ◆ *client_as_known_by_server* is the name to substitute for *hostname_from_client* when responding to requests. This name must be the name configured in the NetBackup configuration on the master server and must also be known to the master server's network services.

For example, the line

```
0 danr danr.eng.aaa.com
```

specifies that when the master server receives a request for a configured client name (numeric key 0), the name `danr` is always replaced by the name `danr.eng.aaa.com`. This resolves the problem mentioned above, assuming that:

- ◆ The client's `gethostname()` function returned `danr`.
- ◆ The master server's network services `gethostbyname()` function did not recognize the name `danr`.
- ◆ The client was configured and named in the NetBackup configuration as `danr.eng.aaa.com` and this name is also known to network services on the master server.



Robotic Test Utilities

C

Each of the robotic software packages includes a robotic test utility for communicating directly with robotic peripherals. The tests are for diagnostic purposes and the only documentation is the online help that you can view by entering a question mark (?) after starting the utility. Specify `-h` to display the usage message.

Note Do not use the robotic test utilities when backups or restores are active. The tests lock the robotic control path and prevent the corresponding robotic software from performing actions, such as loading and unloading media. If a mount is requested, the corresponding robotic process times out and goes to the DOWN state. This usually results in a media mount timeout. Also, be certain to quit the utility when your testing is complete.

If the robot has been configured (that is, added to the Media Manager device database), start the robotic test utility by using the `robtest` command. This saves time, since robotic and drive device paths are passed to the test utility automatically. The procedure is as follows:

1. Execute the following command:

```
install_path\Volmgr\bin\robtest.exe
```

The test utility menu appears.

2. Select a robot and press Enter.

The test starts.

Note If the robot is not configured, you cannot use `robtest` and must execute the command that applies to the robot you are testing (see below). However, in the case of an RSM robot, the robot *must* be configured under NetBackup before a test can be run. When the RSM robot has been configured, use the `robtest` command as described above.

ACS

```
install_path\Volmgr\bin\acstest -r ACSL_HOST
```

RSM



```
install_path\Volmgr\bin\rsmtest -r robotnumber roboticpath
```

TL4

```
install_path\Volmgr\bin\tl4test -r roboticpath
```

TL8

```
install_path\Volmgr\bin\tl8test -r roboticpath
```

TLD

```
install_path\Volmgr\bin\tldtest -r roboticpath
```

TLH

```
install_path\Volmgr\bin\tlhtest -r robotic_library_name
```

TLM

```
install_path\Volmgr\bin\tlmtest -r DAS_Hostname
```

TS8

```
install_path\Volmgr\bin\ts8test -r roboticpath
```

TSD

```
install_path\Volmgr\bin\tsdtest -r roboticpath
```

Note For more information on ACS, TLH, LMF, and TLM robotic control, see the appendixes in the *NetBackup DataCenter Media Manager System Administrator's Guide for Windows*.

For more information on RSM robotic control, refer to the *Microsoft Removable Storage Manager (RSM)* appendix in the *NetBackup BusinessServer Media Manager System Administrator's Guide for Windows*.

In the above commands, *roboticpath* is the full path to the device file for the robotic control (SCSI). Refer to the *Media Manager Device Configuration Guide for Windows* and review the chapter for your platform to find the appropriate value for *roboticpath*.

There is also an optional parameter that specifies the device file path for the drive(s) so that SCSI unloading of the drive(s) can be done with this utility.

Usage is:

```
install_path <-p port -b bus -t target -l lan | -r roboticpath>
```

where: *roboticpath* is the changer name (eg., Changer0)

Backup Exec Tape Reader for NetBackup

D

Overview

This chapter explains problems that can occur when browsing or restoring from Backup Exec media. For the procedures for restoring files backed up by Backup Exec, see the *Using the Backup Exec Tape Reader Option* appendix in the *NetBackup DataCenter System Administrator's Guide*, or the *NetBackup BusinessServer System Administrator's Guide*.

beconv Error Messages

The Backup Exec catalog converter utility (`beconv`) writes debugging information to the NetBackup debug logs in the `admin` folder. The cause of a problem can be determined by examining the debug logs.

This section describes the error messages specific to `beconv`. These messages are not related to Media Manager or NetBackup status codes.

Message: Unable to connect to the Backup Exec engine on the local host

Explanation: Backup Exec services are not running on the host on which `beconv` is being run.

Recommended Action:

Check whether the Backup Exec services are running. Start them if needed. The Backup Exec services are the following:

- ◆ Backup Exec 8.x Agent Browser
- ◆ Backup Exec 8.x Alert Server
- ◆ Backup Exec 8.x Device & Media Service
- ◆ Backup Exec 8.x Job Engine
- ◆ Backup Exec 8.x Naming Service
- ◆ Backup Exec 8.x Notification Server
- ◆ Backup Exec 8.x Server



Message: No device of the appropriate type found for this media

Explanation: NetBackup does not have any drives configured that match the base media type of the Backup Exec media.

For example: If the Backup Exec media has media type dlt, there should be at least one NetBackup drive whose drive type is dlt, dlt2 or dlt3.

Recommended Action: Configure drives of the appropriate drive type. Use the Device Configuration Wizard or another device configuration interface in NetBackup.

Message: Media is not assigned to the local NetBackup media server

Explanation: This happens when `beconv` associates a Backup Exec media with a volume record in the Media Manager volume database either by a barcode, GUID, or slot match, but the volume is not assigned to the local NetBackup media server. This situation is detected when the volume record in the Media Manager volume database is assigned, but the volume is not present in the NetBackup media database of the local host. This is an error condition, because Backup Exec media will only be mounted on the local host. Such Backup Exec media should only be assigned to the local NetBackup media server.

Recommended Action: Examine the Media Manager volume record and determine to which media server it is assigned. There is no direct method to obtain the assigned media server, other than by checking all media servers. The status field in the volume record indicates the application owner. If it does not need to be assigned to that media server, manually expire the media and run `beconv` again.

Caution Do not unassign media in Media Manager. Unassigning volumes in Media Manager may lead to inconsistencies between the application media database and the Media Manager volume database, leading to possible data loss.

Message: A mismatch between media type and robot type detected

Explanation: This happens when `beconv` associates Backup Exec media with a volume record in the Media Manager volume database either by a barcode or GUID match, but the robot type of the record does not have a drive available to match the media type of the Backup Exec media.

For example: The Backup Exec ADAMM database says that Backup Exec media BE-Media, having barcode EFG00, media type dlt, is in Backup Exec robot Exabyte-210. Backup Exec robot Exabyte-210 corresponds to Media Manager robot tld (0). The Media Manager volume database for robot tld(0) contains a media record EFG000, having barcode EFG00, media type 4mm, belonging to robot tld(1).

This is an error because a Backup Exec media of type dlt, having barcode EFG00 cannot be associated with a Media Manager volume record having media type 4mm. Backup Exec media cannot be associated with a Media Manager volume record of an incompatible robot type.

Recommended Action: Examine the Media Manager volume record having the same barcode as the Backup Exec media. Is the Media Manager media type of the volume record really the media type of the media to which the record corresponds? Update the Media Manager volume record accordingly (either manually with add/change/delete volume operations or by using the NetBackup robot inventory update) and run `beconv` again.

Message: Null guid in volume record

Explanation: This happens when a user runs `beconv` with the `beconv -m media_id` option, but `media_id` has a NULL ADAMM GUID in the Media Manager volume database. When `beconv` is run with the `beconv -m media_id` option, `media_id` should always have a non-NULL ADAMM GUID.

Recommended Action: Run `bpimport` (and also `bephyinv` if required) for that media ID.

Message: Media having guid 'XXX' not present in Backup Exec database

Explanation: This happens when a user runs `beconv` with the `beconv -m media_id` option, but the ADAMM GUID field of `media_id` in the Media Manager volume database is not NULL and not present in the Backup Exec ADAMM database. Such a situation can arise when the Media Manager volume database was updated by utilities other than `bephyinv` or `beconv` (like `vmadd`).

Recommended Action: Examine the Media Manager volume record corresponding to `media_id` and determine whether the ADAMM GUID field is correct. If required run `bephyinv` on `media_id`. After updating the volume record corresponding to `media_id`, run `beconv` again.

Message: Backup Exec media type and Media Manager volume record media type incompatible

Explanation: This happens when the user runs `beconv` with the `beconv -m media_id` option, but the Backup Exec media record corresponding to `media_id` has a different base media type than the base media type of the Media Manager volume record.

Recommended Action: Examine the Media Manager volume record corresponding to `media_id` and determine whether the media type is correct. If required run `bephyinv` on `media_id`. After updating the volume record corresponding to `media_id`, run `beconv` again.

Message: No corresponding Media Manager record found for this media

Explanation: This happens when the user runs `beconv` with the `-tbs` option specified, and `beconv` could not associate a Backup Exec media with any Media Manager volume database records. This situation can arise when the `-tbs` option is specified and a NetBackup robot inventory update has not been done on the required robots.



Recommended Action: Do not specify the `-tbs` option or run a NetBackup robot inventory update on the robots that contain Backup Exec media.

bephyinv Error Messages

The Backup Exec Physical Inventory utility (`bephyinv`) logs debugging information to the NetBackup debug logs in the `admin` folder. The exact cause of a problem can be determined by examining the debug logs.

For more information on `bephyinv`, refer to the *Using the Backup Exec Tape Reader Option* appendix in the *NetBackup DataCenter System Administrator's Guide*, or the *NetBackup BusinessServer System Administrator's Guide*.

Message: Unable to connect to the Backup Exec engine on the local host

Explanation: Backup Exec services are not running on the host on which `bephyinv` is running.

Recommended Action: Check whether the Backup Exec services are running. The Backup Exec services are the following:

- ◆ Backup Exec 8.x Agent Browser
- ◆ Backup Exec 8.x Alert Server
- ◆ Backup Exec 8.x Device & Media Service
- ◆ Backup Exec 8.x Job Engine
- ◆ Backup Exec 8.x Naming Service
- ◆ Backup Exec 8.x Notification Server
- ◆ Backup Exec 8.x Server

Message: Volume database mismatch detected. `media_id XXX` was obtained from volume database ABC, but the drive in which it was mounted has a volume database XYZ

Explanation: This happens when the same media IDs are present in different Media Manager volume databases. The volume record that was used to issue the mount was different from the volume record used by Media Manager to mount the media.

Recommended Action: Run `beconv -check_consistency` to determine which Media Manager databases contain the same media ID. Remove the duplicate media ID from the appropriate volume databases and run `bephyinv`. Use a single volume database instead of configuring volumes on multiple hosts.

bpimport Error Messages

The cause of problems relating to `bpimport` can be determined by examining the NetBackup `bptm` logs on the media server on which the media is being imported.

Message: Unable to connect to the Backup Exec engine

Explanation: Backup Exec services are not running on the host on which the media is being mounted.

Recommended Action: Check whether the Backup Exec services are running. The Backup Exec services are the following:

- ◆ Backup Exec 8.x Agent Browser
- ◆ Backup Exec 8.x Alert Server
- ◆ Backup Exec 8.x Device & Media Service
- ◆ Backup Exec 8.x Job Engine
- ◆ Backup Exec 8.x Naming Service
- ◆ Backup Exec 8.x Notification Server
- ◆ Backup Exec 8.x Server

Message: media manager - system error occurred (174)

Explanation: It may be that `bephyinv` was not run on the media ID being imported.

Recommended Action: Check whether the media ID being imported has a non-default ADAMM GUID in the Media Manager volume database. Run `bephyinv` on the media ID and rerun `bpimport`.

Backup Exec File Browse

To determine the cause of Backup Exec file browse problems, examine the `bpdbm`, `bpcd`, and `bptm` logs.

To browse Backup Exec files using the Backup, Archive, and Restore interface:

1. Open the Restore menu and choose Select Restore Type.
2. Set the restore type to Backup Exec Backups or Normal and Backup Exec Backups.

For more assistance, refer to the NetBackup user guide appropriate for your platform.

To list Backup Exec files using the `bplist` command, ensure that the `-flops` parameter has been specified correctly to list only Backup Exec files, or both Backup Exec and NetBackup files.



To list only Backup Exec files, `-flops 524288` should be specified. To list both Backup Exec and NetBackup files, `-flops 1048576` should be specified. Refer to the *NetBackup DataCenter System Administrator's Guide* for usage of the `bplist` command.

Ensure that the Backup Exec services are running on the Media Servers that contain the Backup Exec catalogs whose images are being browsed.

The Backup Exec services are the following:

- ◆ Backup Exec 8.x Agent Browser
- ◆ Backup Exec 8.x Alert Server
- ◆ Backup Exec 8.x Device & Media Service
- ◆ Backup Exec 8.x Job Engine
- ◆ Backup Exec 8.x Naming Service
- ◆ Backup Exec 8.x Notification Server
- ◆ Backup Exec 8.x Server

Backup Exec File Restore

To determine the cause of Backup Exec file restore problems, examine the `bprd`, `bpcd`, and `bptm` logs.

To restore Backup Exec files using the Backup, Archive, and Restore interface:

1. Open the Restore menu and choose Select Restore Type.
2. Set the restore type to Backup Exec Backups or Normal and Backup Exec Backups.

For more assistance, refer to the NetBackup user guide appropriate for your platform.

To restore Backup Exec files using the `bprestore` command, ensure that the `-F` parameter has been specified correctly to restore only Backup Exec files, or both Backup Exec and NetBackup files.

To restore only Backup Exec files, `-F 524288` should be specified. To restore both Backup Exec and NetBackup files, `-F 1048576` should be specified. Refer to the *NetBackup DataCenter System Administrator's Guide* for the usage of the `bprestore` command.

Ensure that the Backup Exec services are running on the Media Servers that contain the Backup Exec catalogs whose images are being restored.

The Backup Exec services are the following:

- ◆ Backup Exec 8.x Agent Browser
- ◆ Backup Exec 8.x Alert Server

- ◆ Backup Exec 8.x Device & Media Service
- ◆ Backup Exec 8.x Job Engine
- ◆ Backup Exec 8.x Naming Service
- ◆ Backup Exec 8.x Notification Server
- ◆ Backup Exec 8.x Server

Note If the NetBackup device configuration is changed and the NetBackup Device Manager service is restarted, the “Backup Exec 8.x Device & Media Service” on the same host should also be restarted. If the Backup Exec service is not restarted, Backup Exec restore jobs may not run, or some of the available drives may not be used for Backup Exec restore jobs.

Redirected Restores

Please note the following:

- ◆ Redirected restores are not allowed when restoring files from a combination of Backup Exec and NetBackup images.
- ◆ When restoring from only Backup Exec images, individual files cannot be restored to different paths. To restore to a different path, all the files must be directed to the same path.
- ◆ The restore option Restore the file using a temporary filename is not available when restoring from Backup Exec images or from a combination of both Backup Exec and NetBackup images.

For Backup Exec images, the following kinds of redirected restores are supported:

- ◆ Backups of a Windows client to the same or a different Windows client.
- ◆ Backups of a Windows client to a different UNIX client.
- ◆ Backups of a UNIX client to the same or a different UNIX client.
- ◆ Backups of a UNIX client to a different Windows client.
- ◆ Backups of an Netware client to the same or a different Netware client.
- ◆ Backups of an Netware client to a different Windows client.
- ◆ Backups of an Netware client to a different UNIX client.

Note The path specified depends upon the client type of the destination machine.

Restoring to Windows Clients

When redirecting a restore to Windows clients, the path should be specified as follows:



Backup Exec File Restore

`\share_name\dir1`

For example, to restore to `C:\temp`, if the sharename for drive `C:` is `C$`, specify the path as `\C$\temp`.

Note When restoring Netware client backups to a Windows client, the NetBackup Windows client interface (`nbwin.exe`), NetBackup Java interface, or the `bprestore` command should be used. The NetBackup Netware client (`nbnwnt.exe`) should not be used to restore Netware client backups to Windows clients.

Restoring to UNIX Clients

When redirecting a restore to UNIX clients, the path should be specified as follows:

`export_path\dir1`

`export_path` is defined in the `agent.cfg` file on the UNIX client (this file is a Backup Exec configuration file for the Backup Exec UNIX client). Files can only be redirected to this path.

For example: If the `agent.cfg` file on machine A contains the following lines:

`export /space/home as space_home`

`export /home1 as home1`

To redirect to `/space/home/dir1`, the path should be specified as `space_home\dir1`.

To redirect to `/home1/dir1`, the path should be specified as `home1\dir1`.

You can only restore to paths which have been exported in the `agent.cfg` file. In the above example, you could only restore to paths under `space/home` or `/home1` on machine A.

Note When restoring Netware client backups to a UNIX client, use the NetBackup Windows client interface (`nbwin.exe`), NetBackup Java interface, or the `bprestore` command. The NetBackup Netware client (`nbnwnt.exe`) should not be used to restore Netware client backups to UNIX clients.

Restoring to Netware Clients

When restoring Netware client backups to Netware clients, use the NetBackup Netware client (`nbnwnt.exe`). To perform Backup Exec restores to a Netware machine, the machine being restored to must be a NetBackup Netware client. Refer to *NetBackup User's Guide Novell Netware NonTarget for Microsoft Windows* for restoring Netware backups to Netware clients.



Troubleshooting with the Debug Logs

To troubleshoot problems that occur when using Backup Exec file browse and restore, create the following debug log directories. For further information on creating these logs, refer to “Debug Logs” in the chapter titled “Using the Logs and Reports.”

On the master server:

```
install_path\NetBackup\logs\bprd
install_path\NetBackup\logs\bpdbm
```

On the media server:

```
install_path\NetBackup\logs\bptm
install_path\NetBackup\logs\bpcd
```

Set the debug logging level to 5.

Backup Exec File Browse Problems

The NetBackup user interfaces and the command lines obtain Backup Exec file lists using a NetBackup internal protocol called the C_BPLIST_4_5 file list protocol.

To determine whether the file browse request has reached bprd, check whether or not the following line appears in the bprd debug log:

```
13:58:46.458 [4132.2140] <2> process_request: command C_BPLIST_4_5
(82) received
```

The NetBackup user interfaces and the command lines must explicitly indicate that a list of Backup Exec files or both Backup Exec and NetBackup files are requested. To determine whether the correct file list options have been specified, check the bprd debug log for the following text:

If only Backup Exec files are requested:

```
13:58:46.488 [4132.2140] <2> fileslist: client_flops = 524288
```

If both Backup Exec and NetBackup files are requested:

```
13:58:46.488 [4132.2140] <2> fileslist: client_flops = 1048576
```

If the NetBackup user interfaces are being used to browse the Backup Exec images, then `client_flops` should be set correctly as above. If `bplist` was being used, then ensure that the `-flops` parameter has been set correctly.

If the correct file browse request has reached bprd, bprd will ask bpdbm to obtain a list of files. For Backup Exec images, bpdbm will launch bpcd on the media server that contains the Backup Exec catalogs whose images are being browsed. This can be seen by searching the bpdbm debug log for the following text:

```
13:58:46.819 [1780.3476] <2> open_file_rec_remote: host = dell_2
```



```
13:58:46.819 [1780.3476] <2> open_file_rec_remote: mediaid = BE0001
13:58:46.819 [1780.3476] <2> open_file_rec_remote: keyword = 22
13:58:46.819 [1780.3476] <2> open_file_rec_remote: path = /
13:58:46.819 [1780.3476] <2> open_file_rec_remote: client = adaj
13:58:46.819 [1780.3476] <2> open_file_rec_remote: depth = 2
13:58:46.819 [1780.3476] <2> open_file_rec_remote: dirs_only = 0
```

In the above text:

Host dell_2 is the name of the media server that contains the Backup Exec catalogs corresponding to the image of client (adaj). The NetBackup image has a keyword (22) which is the Backup Exec backupset number on the Backup Exec media having a Media Manager media ID BE0001.

bpcd will be launched on host dell_2 and will launch bptm to obtain the ADAMM GUID corresponding to Media Manager media ID of BE0001. This can be seen by searching the bpcd debug log on the media server host for the following text:

```
13:58:47.029 [3792.2544] <2> bpcd main: BPCD_GET_FILE_REC_RQST
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received mediaid: BE0001
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received keyword: 22
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received path: /
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received client: adaj
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received dirs_only: 0
13:58:47.029 [3792.2544] <2> bpcd_get_file_rec: received depth: 2
13:58:47.029 [3792.2544] <2> createProcessWithOutput: CreateProcess of
>D:\nb\NetBackup\bin\bptm.exe -guid -ev BE0001 -cmd<
13:58:47.710 [3792.2544] <2> MediaID2MediaGuid: Backup Exec media id BE0001 has
guid {6EE3FFEF-B111-4EDD-97C1-78931D988268} (voldb: dell_2)
```

The above text indicates that bptm obtained the ADAMM GUID {6EE3FFEF-B111-4EDD-97C1-78931D988268} corresponding to Media Manager media ID BE0001 from the Media Manager volume database on host voldb (dell_2).

The text below from the bpcd debug log file indicates that two files were returned to bpdgm:

```
13:58:50.023 [3792.2544] <2> BEopen_file_rec: GetNBFileList returns 2
files
```

bpdgm will send the file list to bprd and bprd will send the file list to the requesting user interface or command line.

By looking at the debug logs, the exact stage where a file browse problem occurred can be determined.



Examples

Example 1: The `bplist` command did not specify the `-flops` parameter, or the Backup Exec Backups or the Normal and Backup Exec Backups option was not selected in the user interface. The `bprd` debug log indicates that `client_flops` has not been set.

```
14:38:09.215 [3316.2376] <2> fileslist:      client_flops = 0
```

Example 2: If the NetBackup Volume Manager service is not running on the media server that contains the Backup Exec catalogs corresponding to the image, the `bpcd` and `bptm` debug logs indicate the problem.

The following is from the `bpcd` log on the media server that contains the Backup Exec catalogs corresponding to the image:

```
15:08:26.614 [3792.3596] <2> bpcd main: BPCD_GET_FILE_REC_RQST
15:08:26.614 [3792.3596] <2> bpcd_get_file_rec: received mediaid: BE0001
15:08:26.614 [3792.3596] <2> bpcd_get_file_rec: received keyword: 22
15:08:26.624 [3792.3596] <2> bpcd_get_file_rec: received path: /
15:08:26.624 [3792.3596] <2> bpcd_get_file_rec: received client: adaj
15:08:26.624 [3792.3596] <2> bpcd_get_file_rec: received dirs_only: 0
15:08:26.624 [3792.3596] <2> bpcd_get_file_rec: received depth: 3
15:08:26.644 [3792.3596] <2> createProcessWithOutput: CreateProcess of
>D:\nb\NetBackup\bin\bptm.exe -guid -ev BE0001 -cmd<
15:09:04.267 [3792.3596] <16> MediaID2MediaGuid: Error - can't get GUID from
string
15:09:04.267 [3792.3596] <16> MediaID2MediaGuid: couldn't obtain media guid for
Backup Exec media id BE0001
```

The following is from the `bptm` log on the media server that contains the Backup Exec catalogs corresponding to the image:

```
15:09:04.207 [4160.3616] <16> vmd_connect: unable to connect to vmd:
Error number: (10061)
15:09:04.217 [4160.3616] <16> query_one_volume: query_onevol request
status: cannot connect to vmd (70)
15:09:04.237 [4160.3616] <16> GetMediaGuid: Media Manager error 70,
cannot connect to vmd, host = dell_2
```

The `bptm` log above indicates that it could not connect to `vmd`, perhaps because `vmd` was not running.

Example 3: If the Backup Exec services are not running on the media server that contains the Backup Exec catalogs corresponding to the image, the `bpcd` debug logs indicate the problem:



Troubleshooting with the Debug Logs

```
15:29:59.695 [3292.3280] <2> bpcd main: BPCD_GET_FILE_REC_RQST
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received mediaid: BE0001
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received keyword: 22
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received path: /
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received client: adaj
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received dirs_only: 0
15:29:59.695 [3292.3280] <2> bpcd_get_file_rec: received depth: 3
15:29:59.695 [3292.3280] <2> createProcessWithOutput: CreateProcess of
>D:\nb\NetBackup\bin\bptm.exe -guid -ev BE0001 -cmd<
15:29:59.975 [3292.3280] <2> MediaID2MediaGuid: Backup Exec media id BE0001 has
guid {6EE3FFEF-B111-4EDD-97C1-78931D988268} (voldb: dell_2)
15:29:59.985 [3292.3280] <2> bpcd_get_file_rec: Successfully loaded beutil.dll
15:29:59.985 [3292.3280] <2> bpcd_get_file_rec: Obtained pointer to
BEopen_file_rec
15:29:59.985 [3292.3280] <2> bpcd_get_file_rec: Obtained pointer to
BRead_file_rec
15:29:59.985 [3292.3280] <2> bpcd_get_file_rec: Obtained pointer to
Bclose_file_rec
15:29:59.995 [3292.3280] <16> BEopen_file_rec: Unable to connect to the Backup
Exec engine on the local host
15:29:59.995 [3292.3280] <2> bpcd_get_file_rec: closing connection
15:30:00.005 [3292.3280] <2> FreeBELibrary: Successfully unloaded beutil.dll
```

Backup Exec File Restore Problems

The NetBackup user interfaces restore Backup Exec files using the NetBackup-internal C_BPSTORE_4_5 restore protocol.

To determine if the restore request has reached bprd, check whether or not the following line appears in the bprd debug log:

```
16:10:56.824 [2540.3248] <2> process_request: command C_BPSTORE_4_5
(80) received
```

The NetBackup user interfaces and commands must explicitly indicate that a list of Backup Exec files or both Backup Exec and NetBackup files need to be restored. To determine if the correct restore options have been specified, check that the following text appears in the bprd debug log:

If only Backup Exec files need to be restored:

```
16:10:59.618 [2540.3248] <2> restorefiles:      clnt_flops = 524288
```



If both Backup Exec and NetBackup files need to be restored:

```
16:10:59.618 [2540.3248] <2> restorefiles:      clnt_flops = 1048576
```

If the user interfaces are being used to restore Backup Exec images, then `client_flops` should be set correctly as above. If `bprestore` was used, ensure that the `-F` command line parameter has been set correctly.

If the correct file list request has reached `bprd`, `bprd` will launch `bpcd` on the media server that contains the Backup Exec catalogs whose images are being restored. This can be seen in the `bprd` debug log:

```
16:11:00.570 [2540.3248] <2> restorefiles: Restoring from image =
adaj_1007712098 (browse_client = adaj, requesting_client = adaj, user = root)
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: mediahost = dell_2
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: browse_client = adaj
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: requesting_client =
adaj
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: destination_client =
adaj
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: client_type = 13
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: mediaid = BE0001
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: keyword = 22
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: obj_desc = NULL
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: keep = 1
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: progress_file =
/G/nb/NetBackup/logs/user_ops/adonijah/logs/NBWIN007
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: rename_file = NONE
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: commit = 0
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: dirByteCount = 0
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: tempDirectory =
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: mountDatabase = 0
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: bePathByteCount = 19
16:11:00.580 [2540.3248] <2> open_BE_restore_connection: beRedirectionPath =
\\f$\temp\be_restore
```

In the above text:

`mediahost dell_2` is the name of the media server that contains the Backup Exec catalogs corresponding to the image of `destination_client` (`adaj`). The NetBackup image has a keyword (22), which is the Backup Exec backupset number on the Backup Exec media having a Media Manager media ID of (BE0001).



bpcd will be launched on host dell_2 and will launch bptm to obtain the ADAMM GUID corresponding to Media Manager media ID BE0001. This can be seen in the bpcd debug log on the media server host for text such as the following:

```
16:11:00.950 [1660.3324] <2> bpcd main: BPCD_RESTORE_IMAGE_FILES_RQST
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: browse_client= adaj
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: requesting_client= adaj
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: destination_client= adaj
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: client_type= 13
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: mediaid= BE0001
16:11:00.960 [1660.3324] <2> bpcd_restore_image_files: keyword= 22
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: obj_desc= NULL
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: keep= 1
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: progress_file=
/G/nb/NetBackup/logs/user_ops/adonijah/logs/NBWIN007
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: rename_file= NONE
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: commit= 0
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: dirByteCount= 0
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: tempDirectory= NONE
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: mountDatabase= 0
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: beFilePathLen= 19
16:11:00.980 [1660.3324] <2> bpcd_restore_image_files: beRedirectionPath=
\\f$\temp\be_restore
16:11:01.010 [1660.3324] <2> createProcessWithOutput: CreateProcess of
>D:\nb\NetBackup\bin\bptm.exe -guid -ev BE0001 -cmd<
16:11:01.992 [1660.3324] <2> MediaID2MediaGuid: Backup Exec media id BE0001 has
guid {6EE3FFEF-B111-4EDD-97C1-78931D988268} (voldb: dell_2)
```

The previous text indicates that bptm obtained the ADAMM GUID {6EE3FFEF-B111-4EDD-97C1-78931D988268} corresponding to Media Manager media ID BE0001 from the Media Manager volume database on host voldb (dell_2).

A portion of the bpcd debug log below shows the Backup Exec files being added to the restore selection list and the restore job being launched on host dell_2:

```
16:11:04.185 [1660.3324] <2> StartRestoreJob: adding Backup Exec path:
util\mykill to selection list
16:11:04.185 [1660.3324] <2> StartRestoreJob: adding Backup Exec file:
pkill.cpp to selection list
16:11:04.185 [1660.3324] <2> GetRedirectionDeviceAndPath: NT Share Name f$
```




```
16:11:04.185 [1660.3324] <2> SetRestoreJobProperties: Device Name: \\ADAJ\fs$
16:11:04.185 [1660.3324] <2> SetRestoreJobProperties: Path: temp\be_restore
16:11:06.318 [1660.3324] <2> SetBEDrivesToUnknown: Obtained 2 drives
16:11:09.162 [1660.3324] <2> write_BE_restore_progress: sending job status
message to bprd: JOB_START:DELL_2
```

A portion of the bpcd debug log below shows that the Backup Exec job was successfully completed:

```
16:12:17.889 [1660.3324] <2> StartBERestoreJob: Backup Exec Job Status: 5
16:12:17.889 [1660.3324] <2> write_BE_restore_progress: sending job status
message to bprd: JOB_SUCCESS
16:12:19.311 [1660.3324] <2> FreeBELibrary: Successfully unloaded beutil.dll
```

A portion of the bprd debug log below shows bprd receiving the JOB_START and JOB_SUCCESS status from bpcd:

```
16:11:09.162 [2540.3248] <2> close_BE_restore_connection: recieved JOB_START
from bpcd
16:12:17.889 [2540.3248] <2> close_BE_restore_connection: recieved JOB_SUCCESS
from bpcd
16:12:17.889 [2540.3248] <2> close_BE_restore_connection: sending disconnect
request to bpcdor command line.
```

By looking at the debug logs, the exact stage where a file restore problem occurred can be determined.

Examples

Example 1: If the bprestore command did not specify the -F parameter, the bprd debug log indicates that client_flops has not been set:

```
16:22:54.735 [3476.2644] <2> restorefiles:      clnt_flops = 0
```

Example 2: If the NetBackup Volume Manager service is not running on the media server that contains the Backup Exec catalogs corresponding to the image, the bpcd and bptm debug logs indicate the problem. The following is an example bpcd log on the media server that contains the Backup Exec catalogs corresponding to the image:

```
16:25:25.918 [1600.4028] <2> bpcd main: BPCD_RESTORE_IMAGE_FILES_RQST
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: browse_client= adaj
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: requesting_client= adaj
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: destination_client= adaj
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: client_type= 13
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: mediaid= BE0001
```



Troubleshooting with the Debug Logs

```
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: keyword= 22
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: obj_desc= NULL
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: keep= 1
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: progress_file=
/G/nb/NetBackup/logs/user_ops/adonijah/logs/NBWIN008
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: rename_file= NONE
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: commit= 0
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: dirByteCount= 0
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: tempDirectory= NONE
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: mountDatabase= 0
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: beFilePathLen= 19
16:25:25.918 [1600.4028] <2> bpcd_restore_image_files: beRedirectionPath=
\\f$\temp\be_restore
16:25:25.918 [1600.4028] <2> createProcessWithOutput: CreateProcess of
>D:\nb\NetBackup\bin\bptm.exe -guid -ev BE0001 -cmd<
16:26:03.431 [1600.4028] <16> MediaID2MediaGuid: Error - can't get GUID from
string Cannot
16:26:03.431 [1600.4028] <16> MediaID2MediaGuid: couldn't obtain media guid for
Backup Exec media id BE0001
```

The following is an example bptm log on the media server that contains the Backup Exec catalogs corresponding to the image:

```
16:26:03.411 [3672.3924] <16> vmd_connect: unable to connect to vmd:
Error number: (10061)
16:26:03.411 [3672.3924] <16> query_one_volume: query_onevol request
status: cannot connect to vmd (70)
16:26:03.421 [3672.3924] <16> GetMediaGuid: Media Manager error 70,
cannot connect to vmd, host = dell_2
```

The bptm log above indicates that it could not connect to vmd, perhaps because vmd was not running.

Example 3: If the Backup Exec services are not running on the media server that contains the Backup Exec catalogs corresponding to the image, the progress log contains the following text:

```
16:21:14 12/7/2001: Restore Started
16:21:16 (97.xxx) Media id BE0001 is needed for the restore.
16:21:17 (97.001) Restoring from image created 12/07/2001 01:31:38 PM
```



```
16:21:19 (97.001) Unable to start Backup Exec restore job on host
DELL_2. Unable to connect to the Backup Exec engine on host DELL_2

16:21:19 (97.001) Status of restore from image created 12/07/2001
01:31:38 PM = the restore failed to recover the requested files

16:21:21 (97.xxx) INF - Status = the restore failed to recover the
requested files.
```

The above text indicates that the Backup Exec services are not running on media server dell_2.

Example 4: If a Backup Exec restore job has been launched with an invalid restore path, the bpcd log file indicates the error. In the example below, the user intends to redirect to D:\public\restored on a Windows machine. The path should be specified as \D\$\public\shared (if D: is shared as D\$). However, the path was incorrectly specified as D:\public\restored. The bpcd log below shows the error:

```
16:26:59.684 [1516.1420] <2> bpcd main: BPCD_RESTORE_IMAGE_FILES_RQST
16:26:59.684 [1516.1420] <2> bpcd_restore_image_files: browse_client= redeemer
16:26:59.684 [1516.1420] <2> bpcd_restore_image_files: requesting_client=
redeemer
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: destination_client=
redeemer
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: client_type= 13
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: mediaid= ISV181
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: keyword= 7
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: obj_desc= NULL
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: keep= 1
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files:
progress_file= /D/VERITAS/NetBackup/logs/user_ops/birk/logs/NBWIN001
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: rename_file= NONE
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: commit= 0
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: dirByteCount= 0
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: tempDirectory= NONE
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: mountDatabase= 0
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: beFilePathLen= 18
16:26:59.694 [1516.1420] <2> bpcd_restore_image_files: beRedirectionPath=
D:\Public\Restored
```



As shown above, the redirection path (beRedirectionPath) has been specified as D:\Public\Restored. Since the browse_client (redeemer) is the same as the destination_client (redeemer), and since the browse_client is of type Windows (client_type = 13), the destination client is of type Windows. Since we are restoring to Windows, the path should be of the format \\D\$\Public\Restored. But the path was incorrectly formatted and the Backup Exec job was not started. This can be seen in the bpcd log below.

```
16:27:00.555 [1516.1420] <16> GetRedirectionDeviceAndPath: Format of
Redirection path is not correct. Correct format for NT target is
"\Share-Name\Directory1"
16:27:00.555 [1516.1420] <16> SetRestoreJobProperties: Error in
redirection
16:27:00.555 [1516.1420] <16> StartRestoreJob: Restore Job properties
could not be set.
16:27:00.555 [1516.1420] <2> write_BE_restore_progress: sending job
status message to bprd: JOB_NO_START_R:REDEEMER
16:27:00.555 [1976.988] <2> bpcd main: BPCD_LOG_RQST_NO_STATUS
16:27:00.555 [1516.1420] <2> FreeBELibrary: Successfully unloaded
beutil.dll
```

Example 5: If a Backup Exec restore job requires media that has been misplaced, the restore job fails. The progress log of the restore job indicates the location of the Backup Exec job log file that contains the reason for the failure. Following is an example of such a NetBackup progress log:

```
13:49:42 2/5/2002: Restore Started

13:50:01 (11.xxx) Media id A00000 is needed for the restore.

13:50:01 (11.001) Restoring from image created 12/17/2001 01:27:18 PM
13:50:10 (11.001) Backup Exec restore job started on host ANTRIKSH
13:52:10 (11.001) Backup Exec restore job failed. See file
'\ANTRIKSH\C$\nbn\BackupExec\Data\BEX09.txt' for details
13:52:12 (11.001) Status of restore from image created 12/17/2001
01:27:18 PM = the restore failed to recover the requested files

13:52:13 (11.xxx) INF - Status = the restore failed to recover the
requested files.
```



In the following log file, the message “User canceled a Physical Volume Library operation” implies that Backup Exec could not get the required media from NetBackup Media Manager. This can happen when the media is misplaced.

For example: Backup Exec job progress log (BEX09.txt):

```
Error - Mount failed.
```

```
^ ^ ^ ^ ^
```

```
User canceled a Physical Volume Library operation.
```

```
Unable to acquire device for the specified pool and media
```

```
^ ^ ^ ^ ^
```

```
User canceled a Physical Volume Library operation.
```

The adamm.log file in the Backup Exec install path indicates the ADAMM GUID of the media that was required for the restore. The adamm.log file indicates whether or not the media was misplaced. In the following example log, the text “MountMedia failure - requested media not found” indicates that the Backup Exec media having ADAMM GUID C4B3BBAE-8B29-4823-ACE5-EBD546E1574B was misplaced.

The Backup Exec install path can be obtained from the following registry value:

```
HKEY_LOCAL_MACHINE\SOFTWARE\VERITAS\Backup Exec\Install\Path
```

This is the adamm.log file in the Backup Exec install path:

```
[1012] 02/05/02 13:52:07 MountMedia failure - requested media not found.
```

```
[1012] 02/05/02 13:50:10 PvlSession::Mount(
{C4B3BBAE-8B29-4823-ACE5-EBD546E1574B}, 1, 1, 4294967295 )
```

```
Job ID = 689276194, Job Name = "Restore 2915851e"
```

```
Drive Pool = {FFFFFFFF-0000-0000-0000-000000000000} "NetBackup Drives"
```

```
Media Set = {00000009-0004-0000-0000-000000000000} "Backup Exec and Windows NT Backup Media"
```

```
ERROR = 0xA000810F (E_PVL_USER_ABORTED)
```

How to locate misplaced Backup Exec media

If the media are robotic and have barcodes, plus the robotic library has a barcode reader, a NetBackup robot inventory update must be run on the robot in which the media reside.



This problem is more likely to occur with non-barcoded robotic media. The NetBackup media id of the Backup Exec media required for the restore can be obtained from the NetBackup job progress log. For example:

```
13:50:01 (11.xxx) Media id A00000 is needed for the restore.
```

The NetBackup Media Manager volume database can be queried to determine the ADAMM GUID (ADAMM GUID field of a Media Manager volume database record), the description and residence (robot and slot number) of the media id. (The media id is A00000 in the above example.) The Backup Exec cartridge label of the media can be determined from the “description” field of the NetBackup Media Manager volume database record.

If the ADAMM GUID (corresponding to the media id in the NetBackup Media Manager volume database) is the same as the GUID obtained from the `adamm.log` (C4B3BBAE-8B29-4823-ACE5-EBD546E1574B, in the above example), then the wrong media may be present in the robot and slot indicated by the NetBackup Media Manager volume database. Verify whether the correct Backup Exec media, identified by ADAMM GUID and cartridge label, is actually present in the robot and slot as indicated by the NetBackup Media Manager volume database record (corresponding to media id A00000, in the above example).

A physical inventory of the robot can be performed to update the NetBackup Media Manager volume database. Refer to the section “Updating the Media Manager Volume Database with Respect to Backup Exec Media” in the *NetBackup DataCenter System Administrator's Guide*.

If the ADAMM GUID corresponding to the media id in the NetBackup Media Manager volume database is not the same as the GUID obtained from the `adamm.log`, then different ADAMM GUIDs are associated with the same media id in the NetBackup Media Manager volume databases of the locally configured drives.

Run `beconv` with the `-check_consistency` option, to detect inconsistencies in the NetBackup Media Manager volume database. Refer to the section “Using `beconv` with the `-check_consistency` Option” in the *NetBackup DataCenter System Administrator's Guide*.

Glossary

access control list (ACL)

Security information associated with files on some file systems.

ACS

Automated Cartridge System. ACS can refer to any of the following:

- ◆ A type of Media Manager robotic control. This robot type is supported only by NetBackup DataCenter servers.
- ◆ The StorageTek (STK) system for robotic control.
- ◆ The highest-level component under STK's ACS library software, which refers to a specific standalone robotic library or to multiple libraries connected with a media passthru mechanism.

active job

A job for which NetBackup is currently processing backup or restore data.

activity logs

See “debug logs.”

activity monitor

A NetBackup administration utility that displays information about NetBackup jobs and provides limited control over them.

administration client

See “remote administration console.”

administrator

A user that is granted special privileges to install, configure, and manage the operation of a system, network, or application.



AIT

Sony Advanced Intelligent Tape, a type of tape drive or media type.

alternate-client restore

See “redirected restore (different client).”

alternate-target restore

See “redirected restore (different target).”

alternate path restore

See “redirected restore (different path).”

alternate read server

A server used to read a backup image which was originally written by a different media server. The media server specified as Alternate Read Server must have access to the media containing the backup image or images it is configured to read.

archive

A special kind of backup where NetBackup backs up the selected files, and if the backup is successful, deletes the files from the local disk. In this manual, references to backups also apply to the backup portion of archive operations except where otherwise noted.

archive bit

A file-status bit that the Microsoft based operating system sets when it writes a file, thereby indicating that the file has changed.

attributes for a policy

Configuration parameters that control the behavior of NetBackup during operations involving this policy.

autochanger

See “robotic library.”

autoloader

See “robotic library.”

automatic backup

A scheduled backup by the master server.



back up

The act of copying and saving files and folders to storage media.

backup

Refers to the process of copying and saving files and directories to storage media. For example, *the backup is complete*. This term can also refer to the collection of data that NetBackup saves for a client during a backup or archive. For example, *duplicate the backup*.

Backup is two words when used as a verb. For example, *back up the file*.

backup, archive, and restore interface

The name of the NetBackup Microsoft Windows and Java based user interfaces for clients. On servers these interfaces can be started through the NetBackup Administration Console.

backup window

The period of time during which backups can begin.

block size

The number of bytes in each block of data written on the media during a backup.

bp

A backup, archive, and restore utility for users on NetBackup UNIX clients. It has a character-based, menu interface that can be run from terminals that do not have X Windows capabilities.

bpadm

An administrator utility that runs on NetBackup UNIX servers. It has a character-based, menu interface that can be run from terminals that do not have X Windows capabilities.

bp.conf file

A NetBackup configuration file on UNIX servers and also on UNIX, Macintosh, and OS/2 clients.

bp.ini file

NetBackup initialization file for Novell NetWare target clients.

bpcd

NetBackup Client service on Windows and the NetBackup Client daemon on UNIX.



bprd

NetBackup Request Manager service on Windows and NetBackup Request daemon on UNIX.

cancel a job

Terminating a job and removing it from the job queue.

carousel

See “robotic library.”

catalogs

Internal NetBackup and Media Manager databases. These catalogs contain information about configuration, media, devices, status, errors, and the files and directories in the stored backup images.

CDF

Context-dependent file, which is a type of directory structure on a Hewlett-Packard system.

changer

See “robotic library.”

class

See “policy.”

client

The system with the files to back up, archive, or restore.

client-user interface

See “user interface.”

cluster

See master and media server cluster.

command lines

Commands that users can execute either from the system prompt or in scripts.

compression

The process of compacting data to enable more efficient transmission and storage.



configuration

The parameters that govern the behavior of an application. This term can also refer to the manner in which a network or system is laid out or connected (for example, a network configuration).

consolidated eject

A process of ejecting media for more than one Vault session at a time. A Consolidated Eject can be performed for one or more logical vaults at one time.

consolidated report

A process of generating reports for more than one Vault session at a time. A Consolidated Report can be performed for one or more logical vaults at one time. Consolidated reports are organized by report title, not by vault.

cpio

A UNIX command that can be used for copying files to or from a cpio archive on disk or tape.

ctime

The time that a UNIX inode was changed.

cumulative-incremental backup

A backup that is scheduled by the administrator on the master server and backs up files that have changed since the last successful full backup. All files are backed up if no prior backup has been done. Also see “differential-incremental backup.”

daemon

A program on a UNIX system that runs in the background and performs some task (for example, starting other programs when they are needed). Daemons are generally referred to as services or processes on Windows server systems.

database-agent clients

Clients with additional NetBackup software that is designed to back up relational databases.

database-extension clients

See “database-agent clients.”



debug logs

Logs that can be optionally enabled for specific NetBackup and Media Manager programs and processes and then used to investigate problems.

destination storage unit

A storage unit to which Vault sends the data from a duplication operation. If the duplicated backup images are to be vaulted, then the destination storage unit must correspond to the robotic volume group.

device delays

Delays caused by the device that are beyond the control of the storage application. An example is the time required to position tape under the read and write heads.

device host

A host (that has Media Manager installed) where a drive or robotic control is attached or is defined.

device monitor

A Media Manager administration utility that provides monitoring and manual control of Media Manager storage devices. For example, an administrator or computer room operator can use this utility to manually reset devices or set them to the UP or DOWN state.

DHCP

Dynamic host configuration protocol. This TCP/IP protocol automatically assigns temporary IP addresses to hosts when they connect to the network.

differential-incremental backup

Scheduled by the administrator on the master server and backs up files that have changed since the last successful incremental or full backup. All files are backed up if no prior backup has been done. Also see “cumulative-incremental backup.”

directory depth

The number of levels below the current directory level that the NetBackup interfaces show in their directory and file list displays.

directory tree

The hierarchical structure in which files are organized on a disk. Each directory lists the files and directories that are directly below it in the tree. On UNIX, the topmost directory is called the root directory.



disaster recovery

Recovering data from backups after a disk crash or other catastrophe.

disk

Magnetic or optical disk storage media.

disk-image backup

A bit-by-bit rather than a file system backup of a disk drive on a Windows platform.

DLT

Digital-linear tape or tape drive type.

Domain Name Service (DNS)

A program that handles name translation for network communications.

drive cleaning

The use of a special cleaning tape to clean the heads on a drive.

duplicate image

A copy of a backup image.

eject

Move media out of a robotic library.

encryption

Provides additional security by encrypting backup data on the client. This capability is available only with the NetBackup Encryption option.

entry and exit ports

See “media access port.”

exclude list

A list that designates files or directories to exclude from automatic backups.

expiration (image)

The date and time when NetBackup stops tracking a backup image.



expiration (volume)

The date and time when the physical media (tape) is considered to be no longer usable.

external media ID

This is an identifier written on a media cartridge or canister to help the operator identify the volume before inserting it into a drive or robot. For labeled media, the external media ID should be the same as the media ID recorded on the media.

EVSN

See “external media ID.”

FlashBackup

A special type of raw-partition backup that requires the NetBackup FlashBackup separately-priced option (this option is available only for NetBackup DataCenter).

flush level

Controls how often Netbackup clears its log files on a Novell NetWare or Microsoft Windows client platform.

fragment

A part of a backup or archive image. NetBackup can be configured to divide images into fragments when they exceed a certain size or span tapes.

frequency (backup)

How often NetBackup performs scheduled backups. For example, if the frequency is seven days then backups occur once a week.

FROZEN media state

If a volume is FROZEN, NetBackup keeps it indefinitely and can restore from it but not use it for further backups or archives.

full backup

A backup that copies, to a storage unit, all files and directories that are beneath a specified directory.

FULL media state

If this appears in a report or listing, it indicates the volume is FULL and cannot hold more data or be used for further backups.



global attributes

NetBackup configuration attributes that affect all policies.

GDM Dashboard

The name for the Global Data Manager interface. The Dashboard enables monitoring job and drive activity on multiple master servers, as well as providing alerts to problem conditions.

GDM Managed Server

A NetBackup master server that appears as a managed master server in the left pane of the GDM Dashboard.

GDM Server

A NetBackup master server that has the Global Data Manager license activated. When logging into this host, the user can monitor the activity on multiple master servers using the GDM Dashboard interface. If the host has installed the Advanced Reporter option, the reports show information on multiple master servers.

Global Data Manager (GDM)

A separately-priced option (for UNIX servers) that provides an interface with a tree view where the administrator can view and administer multiple master servers. The server where the option is installed is called a GDM Server.

Global Device Database

A single host that serves as the repository for global device configuration information. When you install NetBackup, by default the master server is configured as the global device database host.

GNU tar

A public domain version of the UNIX tar program.

goodies directory

A directory containing programs, scripts, and other files that are not formally supported.

GUI

Graphical user interface.



hard link

On UNIX, a hard link is a pointer to the inode for the data. On a Windows server, a hard link is a directory entry for a file. Every file can be considered to have at least one hard link. On NTFS volumes each file can have multiple hard links, and a single file can appear in many directories (or even in the same directory with different names).

heap level

A parameter for memory-heap debugging on a Novell NetWare or Windows NetBackup client.

hierarchical storage management

The process of automatically migrating selected files from a managed file system to specified migration levels on secondary storage, while maintaining transparent access to those files.

host

A computer that executes application programs.

host name

Name by which a host computer is identified by programs and other computers in the network.

HSM

See storage migrator.

image

The collection of data that NetBackup saves for an individual client during each backup or archive. The image contains all the files, directories, and catalog information associated with the backup or archive.

import

The process of recreating NetBackup records of images so the images can be restored.

include list

A list that designates files or directories to add back in from the exclude list.

incremental backup

See “cumulative-incremental backup” and “differential-incremental backup.”



inject

Move media into a robotic library.

inport

See “media access port.”

inode

A UNIX data structure that defines the existence of a single file.

install_path

Directory where NetBackup and Media Manager software is installed. The default on Windows servers is `C:\Program Files\VERITAS` and on UNIX it is `/usr/opensv`.

jbpSA

The Java-based NetBackup interface for performing user backups, archives, and restores.

jnbSA

The Java-based NetBackup interface for administrators.

job

A parcel of work submitted to a computer. NetBackup jobs are backups, archives, or restores.

kernel

The nucleus of an operating system.

keyword phrase

A textual description of a backup.

kill a job

See “cancel a job.”

label

Identifier of a tape or optical disk volume. A recorded label includes a media ID.

A barcode label allows a barcode scanner to be used for media tracking.

library

See “robotic library.”



link

See “hard link” or “symbolic link.”

LMF - Library Management Facility

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

This robot type is supported only by NetBackup DataCenter servers.

load

(noun) Amount of work that is being performed by a system or the level of traffic on a network. For example, network load affects performance.

(verb) Copy data to internal memory. For example, load the installation program.

(verb) Used to indicate tape drive initialization done when new media is being added.

logs

Files where a computer or application records information about its activities.

mailslot

See “media access port.”

man pages

Online documentation provided with UNIX computer systems and applications.

Master and media server cluster

A NetBackup master server and the remote media servers that it is using for additional storage. It is possible to configure clusters only with NetBackup DataCenter servers. NetBackup BusinessServer supports only a single server, the master.

Master of Masters

A NetBackup host where Global Data Manager software is installed. When logging into this host, the interface has a tree view where the administrator can view and administer multiple master servers.

master server

The NetBackup server that provides administration and control for backups and restores for all clients and servers in a master and media server cluster. NetBackup BusinessServer supports only a single server and it is the master.



media

Physical magnetic tapes, optical disks, or magnetic disks where data are stored.

media access port

A slot or other opening in a robot where you can insert or remove a tape without having to access the interior of the robot. After inserting a tape, you move it to a slot by using an inject command. Prior to removing a tape, you move it to the port by using an eject command. The inject and eject commands are supported through the add and move screens in the Media Manager administration interface.

media host

NetBackup server to which the job (client) is sending the data.

media ID

An identifier that is written on a volume as part of the recorded label.

Media Manager

Software that is part of NetBackup and manages the storage devices and removable media.

Media Manager Host

Host where Media Manager is installed (may have devices attached).

media server

A NetBackup server that provides storage within a master and media server cluster. The master can also be a media server. A media server that is not the master is called a remote media server. NetBackup BusinessServer does not support remote media servers.

menu interface

A character-based interface for use on terminals that do not have graphical capabilities.

mount

Make a volume available for reading or writing.

mount point

The point where a file system on a disk logically connects to a system's directory structure so the file system is available to users and applications.



MPX

See “multiplexing.”

mtime

The point in time when a UNIX or NTFS file is modified.

multiplexing

The process of sending concurrent-multiple backups from one or more clients to a single storage device and interleaving those images onto the media.

multiplexed group

A set of backups that were multiplexed together in a single multiplexing session.

NDMP

Network data management protocol. NetBackup requires the NetBackup for NDMP separately-priced option to support NDMP.

NetBackup Client service

NetBackup Windows service that runs on clients and servers and listens for connections from NetBackup servers and clients in the network. When a connection is made, this service starts the necessary programs.

NetBackup configuration options

On UNIX servers and on UNIX and Macintosh, clients, these settings are made in the `bp.conf` file. On NetWare target and OS/2 clients, they are in the `bp.ini` file. On Windows servers and Windows clients, these settings are called properties and are made through the Backup, Archive, and Restore interface or the Host Properties dialog in the NetBackup Administration Console.

NetBackup databases

See catalogs.

NetBackup Database Manager service

NetBackup Windows service that runs on the master server and manages the NetBackup internal databases (called catalogs). This service must be running on the master server during all NetBackup administrative operations.



NetBackup Device Manager service

The NetBackup Windows service that runs on a NetBackup server and starts the robotic control processes and controls the reservation and assignment of volumes. This service runs only if the server has devices under Media Manager control. The process is `ltid`.

NetBackup properties

Same as NetBackup configuration options but are called NetBackup properties on Microsoft Windows platforms.

NetBackup Request Manager service

The NetBackup Windows service that runs on the master server and starts the scheduler and receives requests from clients.

NetBackup Volume Manager service

A NetBackup Windows service that runs on a NetBackup server, allows remote administration of Media Manager, and manages volume information. The process is `vmd`.

NIS

Network information service.

NLM

NetWare loadable module.

NFS

Network file system.

nonrobotic

See “standalone.”

ODL

Optical disk library. This robot type is supported only by NetBackup DataCenter servers.

offsite volume group

A volume group in which media will appear after having been ejected from the robot for vaulting. When Vault ejects media it is moved from the robotic volume group to the off-site volume group.



offsite volume pool

A volume pool that contains media that is to be ejected and vaulted. Backup images written to an off-site volume pool by an original NetBackup backup policy or by Vault's duplication feature will be ejected and vaulted. More than one off-site volume pool can be specified for the Eject step of a Vault profile.

original backup

A backup image created by a backup job. A single backup image or all backup images created by an Inline Tape Copy (multiple copy) configuration are considered original backups. A backup image created by a duplication job is not an original backup.

outport

See “media access port.”

partitions

The logical partitions into which a magnetic disk is divided.

patch

A program that corrects a problem or adds a feature to an existing release of software.

path length

Number of characters in a pathname.

pathname

The list of directories in the path to a destination directory or file.

PC clients

NetBackup clients that have Microsoft Windows, Macintosh, or IBM OS/2 operating systems.

peername

The name by which a computer identifies itself when establishing connections to other systems.

policy

Defines the backup characteristics for a group of one or more clients that have similar backup requirements.



port

A location used for transferring data in or out of a computer.

Also see “media access port.”

primary copy

The copy of an image that NetBackup uses to satisfy restores. When NetBackup duplicates an image, the original is designated as the primary copy.

privileges

The tasks or functions that a user, system, or application is authorized to perform.

profile

A vault profile is a way to save configuration settings. Specific parameters for duplication, catalog backup, eject, and report or any combination of these steps, are configured within a profile.

progress report

Log where NetBackup records events that occur during user operations.

proxy restore

A proxy restore allows the user to restore files that he has write access to, on a machine other than his desktop. The files must be in a backup of the machine to which they are being restored.

QIC

Quarter-inch-cartridge tape.

queued job

A job that has been added to the list of jobs to be performed.

raw-partition backup

Bit-by-bit backup of a partition of a disk drive on UNIX. On Windows, this is called a disk-image backup.

rbak

The program that Apollo clients use to read data from tape during a restore.



recorded media ID

This is an identifier written as part of the label on a volume and used by Media Manager to ensure that the correct volume is mounted. The recorded media ID should match the external media ID.

redirected restore (different client)

Restoring files to your client when they were originally backed up from a different client. The administrator using the interface on the master server can direct a restore to any client (this variation is called a server directed restore).

redirected restore (different target)

On a Novell NetWare server platform running the NetBackup target version of client software, this operation restores files to a different target than the one from which they were backed up.

redirected restore (different path)

Restores files to a different directory than the one from which they were backed up.

registry

A Microsoft Windows database that has configuration information about hardware and user accounts.

remote administration console

A Windows NetBackup client that has the administration interface software installed and can be used to administer NetBackup servers.

remote media server

A media server that is not the master. Note that only NetBackup DataCenter supports remote media servers. NetBackup BusinessServer supports only a single server, the master.

residence

In Media Manager, information about the location of each volume is stored in a volume database. This residence entry contains information, such as robot number, robot host, robot type, and media type.

resource

A Novell NetWare term that refers to a data set on the target. For example, in DOS, resources are drives, directories, and files. Also see “target service.”



restore

(verb) The act of restoring selected files and directories from a previous backup or archive and returning them to their original directory locations (or to a different directory).

(noun) The process of restoring selected files and directories from a previous backup and returning them to their original directory locations (or to a different directory).

retention level

An index number that corresponds to a user-defined retention period. There are 10 levels from which to choose (0 through 9) and the retention period associated with each is configurable. Also see “retention period.”

retention period

The length of time that NetBackup keeps backup and archive images. The retention period is specified on the schedule.

robotic arm

The component of a robotic library that physically selects the media (tape or optical disk).

robotic library

Refers to a robot and its accompanying software. A robotic library includes a collection of tapes or optical platters used for data storage and retrieval. For example, a Tape Library DLT (TLD) refers to a robot that has TLD robotic control.

robotic volume group

A volume group from which media will be ejected and vaulted. When Vault duplicates backups, they are duplicated to media in the robotic volume group.

root

The highest level directory in a hierarchical directory structure. In MS-DOS, the root directory on a drive is designated by a backslash (for example, the root on drive C is C:\). On UNIX, the root directory is designated by a slash (/).

Also, a UNIX user name having administration capability.

RS-232

An industry-standard interface for serial communications and sometimes used for communicating with storage peripherals.



RSM Interface

Application in Windows 2000 used to manage Removable Storage Manager (RSM) devices.

RSM - Removable Storage Manager

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

Also, a component of the Windows 2000 operating system that manages storage devices.

RVSN

See “recorded media ID.”

schedules

Controls when backups can occur in addition to other aspects of the backup, such as: the type of backup (full, incremental) and how long NetBackup retains the image.

SCSI

Small computer system interface. This is a type of parallel interface that is frequently used for communicating with storage peripherals.

server-directed restore

Using the user interface on the master server to restore files to any client. Only the administrator can perform this operation.

server independent restore

Restoring files by using a NetBackup server other than the one that was used to write the backup. This feature is available only with NetBackup DataCenter.

server list

The list of servers that a NetBackup client or server refers to when establishing or verifying connections to NetBackup servers. On a Windows server and Microsoft Windows clients, you update the list through a dialog box in the interface. On a UNIX server and UNIX and Macintosh clients, the list is in the `bp.conf` file. On NetWare target and OS/2 clients, the list is in the `bp.ini` file.

service

A program on a Windows server system that runs in the background and performs some task (for example, starting other programs when they are needed). Services are generally referred to as daemons on UNIX systems.



session

An instance of NetBackup checking its schedules for backups that are due, adding them to its worklist, and attempting to complete all jobs in the worklist. For user backups and archives, a session usually consists of a single backup or archive.

Session (Vault)

A vault session consists of executing a particular profile or profiles.

shared drives

See “Shared Storage Option (SSO).”

Shared Storage Option (SSO)

A separately priced VERITAS software option that allows tape drives (standalone or in a robotic library) to be dynamically shared among multiple NetBackup and Storage Migrator servers.

This option is supported only on NetBackup DataCenter servers.

SMDR

Storage management data requestor, a Novell NetWare program that provides its services transparently to all SMS modules and lets remote and local modules communicate with one another.

SMS

Novell NetWare storage management services.

source volume group

A volume group from which Vault can select backups to duplicate. This parameter is used to restrict the list of backups from all backups that reside on media in any volume group to backups that reside on media in a single volume group. Where a volume group corresponds to a particular robot, the profile will duplicate only backups on media in that robot. The Source Volume Group is normally only specified if you have multiple robots attached to the same server, for example you want to duplicate backups that reside in robot 0 to media that reside in robot 1.

SSO

See “Shared Storage Option (SSO).”

stacker

Usually a small robotic library that contains one drive only. See “robotic library.”



standalone

A qualifier used with drives and media to indicate they are not associated with a robot. For example, a standalone tape drive is one where you must manually find and insert tapes before using them. A standalone volume is one that is located in a standalone drive or is stored outside of a drive and designated as standalone in the volume configuration.

status code

A numerical code, usually accompanied by a troubleshooting message, that indicates the outcome of an operation.

storage migrator

Refers to the VERITAS Storage Migrator line of hierarchical storage management products for UNIX and Windows. These products make extra room on a disk by transparently moving data to other storage and then transparently retrieving the data when it is needed by a user or application.

Storage Migrator is available only for NetBackup DataCenter servers.

storage unit

Refers to a storage device where NetBackup or Storage Migrator stores files. It can be a set of drives in a robot or consist of one or more single tape drives that connect to the same host.

SUSPENDED media state

If a volume is SUSPENDED, NetBackup can restore from it but cannot use it for backups. NetBackup retains a record of the media ID until the last backup image on the volume expires.

symbolic link

On a UNIX system, this is a pointer to the name of the file that has the source data.

TapeAlert

Allows reactive cleaning for most drive types and is a function of the tape drive.

tape format

The format that an application uses to write data on a tape.

tape marks

A mark that is recorded between backup images on a tape.



tape overhead

The space required for data that is not part of the backup images. For example, tape marks and catalogs of what are on the tape are considered overhead.

tape spanning

Using more than one tape to store a single backup image.

tar

Tape Archive program that NetBackup uses to extract backup images during a restore.

target

See “target service.”

target service

A Novell NetWare service that needs storage management. The SMS views all services (for example, print services, communication services, workstations) as targets.

Target Service Agent

A Target-service agent is a Novell NetWare agent that prepares the target's data for SMS during a backup and for the target during a restore.

TLD - Tape Library DLT

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

TLH - Tape Library Half-inch

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

This robot type is supported only by NetBackup DataCenter servers.

TLM - Tape Library Multimedia

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

This robot type is supported only by NetBackup DataCenter servers.

TL4 - Tape Library 4MM

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.



TL8 - Tape Library 8MM

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

timeout period

The period of time that an application has allotted for an event to occur.

TIR

See “true image restore.”

tpconfig

A Media Manager administration utility for configuring devices which is started from the command line. On UNIX, it has a character-based menu interface that can be run from terminals that do not have X Windows capabilities. tpconfig also has a command line interface.

transfer rate

The rate at which computer information is transferred between a source and a destination.

transport

See “robotic arm.”

true image restore

Restores the contents of a directory to what it was at the time of any scheduled full or incremental backup. Previously deleted files are ignored.

TS8 - Tape Stacker 8MM

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

TSA

See “Target Service Agent.”

TSD - Tape Stacker DLT

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

TSH - Tape Stacker Half-inch

A Media Manager designation for a category of robot. For the specific vendor types and models in this category, see the VERITAS support web site.

This robot type is supported only by NetBackup DataCenter servers.

unassigned media

Media that contain no valid images. A piece of unassigned media has an entry in the volumes database but no entries in the images database. Unassigned Media do not have a “time assigned” in the Media section of the GUI.

user interface

The program used to perform user backups, archives, and restores.

user operation

A backup, archive, or restore that is started by a person on a client system.

Vault

Vault is a separately-priced NetBackup option that provides offsite backup management. Vault automatically duplicates specified backup images, and automates the process of offsite media rotation (a critical component of any backup or disaster recovery strategy). Vault manages offsite storage and retrieval of media for original backups, duplicate backups, and catalog backups. Additionally, NetBackup Vault generates reports to track the location and content of each piece of media.

vault

In the context of the NetBackup Vault, a vault is logical entity associated with a particular robot that acts as a designated holding place for backups that will eventually be sent to a physical offsite vault. The term ‘vault’ is used to refer both to the process, and to the physical storage location of a set of tapes offsite.

vault process

Vaulting is the process of choosing backup images to duplicate or eject, optionally duplicating backups, ejecting duplicate or original media, storing it at an offsite location, and later returning expired media to your robot. Vaulting is an integral part of the disaster recovery process.

verbose flag

Configuration file entry that causes a higher level of detail to be written in the logs.



verify

An operation that compares the list of files that are actually on a volume with what NetBackup has recorded as being on it. The data that is on the media is not verified.

vmadm

A Media Manager administrator utility for managing volumes. It runs on UNIX and has a character-based, menu interface that can be run from terminals.

vm.conf

A Media Manager configuration file with entries that include the servers that can manage local devices and default media ID prefixes for media that do not contain barcodes.

volume

Media Manager volumes are logical units of data storage or cleaning capability on media that have been assigned media IDs and other attributes, which are recorded in the Media Manager volume database.

volume configuration

Refers to configuration information that is stored in the Media Manager volume database.

volume database

An internal database where Media Manager keeps information about volumes. All hosts (where Media Manager is installed) have a volume database. However, the database is empty unless the host is designated as a volume database host.

volume database host

The host (where Media Manager is installed) that contains information about the volumes that Media Manager uses in a device. Because NetBackup BusinessServer supports only a single server, the volume database host is always on the same server.

volume group

A set of volumes that are configured within Media Manager to reside at the same physical location (for example, in a specific robot).

volume pool

A set of volumes that are configured within Media Manager to be used by a single application and are protected from access by other applications and users.

wakeup interval

The time interval at which NetBackup checks for backups that are due.



wildcard characters

A character that can be used to represent other characters in searches.

Microsoft Windows

(noun) Describes a line of operating systems developed by Microsoft, Inc.

For more information on the Windows operating systems that NetBackup supports, refer to the VERITAS support web site at <http://www.support.veritas.com>.

Windows

(adjective) Used to describe a specific product or clarify a term. Some examples are: Windows 95, Windows 98, Windows NT, Windows 2000, Windows servers, Windows clients, Windows platforms, Windows hosts, and Windows GUI.

Windows servers

A term that defines the Windows server platforms that NetBackup supports; those platforms are: Windows NT and 2000.

Windows clients

A term that defines the Windows client platforms that NetBackup supports; those platforms are: Windows 95, 98, ME, NT, 2000, XP (for 32- and 64-bit versions), and LE.

Windows Display Console

A NetBackup-Java interface program that runs on Windows 2000, NT, 98, and 95 computers. Users can start this interface on their local system, connect to a UNIX system that has the NetBackup-Java software installed, and then perform any user operations that their permissions allow.

WORM media

Write-once, read-many media for optical disks. NetBackup BusinessServer does not support WORM media.

xbp

The X Windows-based backup, archive, and restore program for users on NetBackup UNIX clients.





Index

Numerics

3pc.conf file 123

A

acssel, description 459
acsssi, description 459
acstest 471
activity logs. See debug logs
ADAMM 475
ADAMM_GUID 477
admin log 45
admincmd, directory 440
Administration interface
 activity logging 53
 errors 51
All Log Entries report 43
Alternate client restores
 host.xlate file 469
altnames file 450
application server status codes (Java interface) 52
asc value 124
ascd, description 459
ascq value 124
associate.bat file 54
Audience for manual ix
auto-configuration problems 12
avrdr, description 459

B

Backup Exec
 beconv problems 473
 bephyinv problems 476
 file browse problems 477
 file restore problems 478
 import problems 477
 restoring files 477, 478
 services 478
 tape reader 473

Backup process

files 422
Macintosh clients 429
multiplexing 424
NetBackup databases 430
NetWare clients 428
UNIX clients 422
Windows 98/95 clients 426
Windows NT/2000 clients 427

Backup Status report 43

base NetBackup license key 76

beconv 473

bephyinv 475, 476

bin

 Media Manager 458

 UNIX client 440

BP 437

bp

 description 441

bp log 46

bp.conf file

 UNIX client/server 440

BP.NLM 441

bpadm

 description 441

bparchive

 description 441

bparchive log 46

bpbackup

 description 442

bpbackup log 47

bpbkar

 description 442

bpbkar and fsclone 63

bpbkar log 47

BPBKAR32 427, 442

bpblr

 description 442



- bpbrm
 - description 442
- bpbrm log 45
- BPCD 428, 436, 437
- bpcd
 - description 443
 - Mac client log 48
 - server log 45
 - UNIX client log 47
- BPCD.NLM 443
- BPCDW32 426, 435
- BPCDW32.EXE 443
- bpcIntcmd utility 28
- bpdjobs
 - description 443
- bpdjobs log 45
- bpdbm
 - description 444
- bpdbm log 45
- bpdm
 - description 444
- bpdm log 45
- bperror command 55
- bphdb
 - description 444
- bpimport 477
- BPINETD 427, 436
- bpinetd log 46
- bpjava-msvc 444, 445
- bpjava-msvc log 53
- bpjava-usvc log 53
- bplist 477
 - description 445
- bplist log 47
- bpmount log 47
- bprd
 - description 445
- bprd log 45
- bprecover 112, 401, 404, 405, 409, 410, 411, 412, 413, 415, 416
- bprestore
 - description 445
- bprestore log 47
- bpsched
 - description 446
- bpsched log 45
- bpsrv log 47
- BPSRV.EXE 446
- BPSYS.EXE 446

- bptm
 - description 446
- bptm log 45

C

- Catalog recovery
 - identify media 410
 - procedure 411
- class database file 450
- Client Backups report 43
- Client, NetBackup
 - activity logs
 - Mac clients 48
 - configured name 467
 - debug logs
 - Windows and NetWare clients 46
 - installation problems 11
 - multiple hostnames 467
 - NT disk recovery 406
 - peername 467
 - software location
 - UNIX clients 440
 - testing configuration 16, 19
- CLIENT_CONNECT_TIMEOUT 58, 73
- CLIENT_READ_TIMEOUT 58, 73
- clone (fsclone, removing) 63
- clone (mirror, removing) 64
- Communications problems
 - PC clients 21
- compression device 15
- config file 450
- Configuration database 450
- configuration device file does not exist 15
- Configuration problems 11

D

- Daemons
 - Media Manager 458
 - NetBackup 441
 - robotic 451
 - robotic control 451
- Database directory, Media Manager 458
- Database extension 419
- Databases
 - Media Manager
 - device 458
 - volume 458
 - NetBackup
 - backup process 430
 - description 450



- db directory, NetBackup 440
 - debug level 48, 53
 - debug logs 44, 53
 - NetBackup 458
 - vmd 458
 - Define the problem 1
 - Device configuration problems 12
 - Device database 458
 - Directory structure
 - Media Manager 457
 - NetBackup
 - UNIX client/server 439
 - Disaster recovery 399
 - Disk recovery
 - master when NT intact 399
 - media server 405
 - NT client 406
 - NT master server 399
 - total on master 402
 - DNS (see Domain Name Service)
 - Domain Name Service
 - hostnames 469
 - drive
 - drive limit exceeded 14
 - type not determined 15
 - drive_mount_notify script 453
 - drive_unmount_notify script 453
 - driver directory 458
 - drives, too many 13
 - Duration to Retain Logs 45
- E**
- Error codes (see Status codes)
 - Error database 450
 - evaluation license key 76
 - Event viewer logging option 49
 - exception errors in Java Admin interface 51
 - exclude_list
 - UNIX client 440
 - expired license key 76
 - Extended Frozen Image Services 64
 - external mapping files 401, 404
- F**
- failure_history file 450
 - Fastrax 58, 73
 - fi.conf file 147
 - file
 - restore problems (Backup Exec) 478
 - File database 450
 - file list
 - symbolic link 60
 - file pathname (max length) 56
 - Files
 - archive process 422
 - backup process 422
 - host.xlate 469
 - restore process 432
 - flops on bplist 478
 - format directory 458
 - frozen image
 - source
 - for symbolic link 60
 - frozen image (removing) 64
 - fscckptadm command 63
 - fscclone frozen image 63
 - Functional overview
 - introduction 419
 - Media Manager
 - device management 453
 - directories and files 457
 - programs and daemons 458
 - startup 451
 - volume management 453
 - NetBackup
 - backup and archive 422
 - directories and files 439
 - programs and daemons 441
 - restores 432
 - startup 420
- G**
- gethostbyname 154
 - getpid 155
 - goodies directory 458
 - goodies, directory 440
 - GUID 474
- H**
- Help files
 - Media Manager 458
 - UNIX client 440
 - Host name entries, checking 25
 - host.xlate file 26, 469
- I**
- IDR 406
 - Images database 450
 - Images on Media report 43
 - import 477



- include_list
 - UNIX client 440
- inetd 10
- inetd, Mac client log 48
- installation
 - Linux 10
- Installation problems 10
- Intelligent Disaster Recovery (IDR) 406
- Introduction to troubleshooting 1

J

- Java interface
 - debug logging 53
 - troubleshooting background 51
- jbpSA, overview 447
- JBPSimple.properties file 53
- Jobs database 450

K

- key value 124

L

- Launch.properties file 53
- license key 76
- license problems 13, 15
- links (in file list) 60
- Linux 10
- listing Backup Exec and NetBackup files 478
- lmfs description 460
- Log level
 - Macintosh clients 48
 - Windows and NetWare clients 48
- Logs
 - overview 41
 - debug, enabling detailed 53
 - event viewer logging option 49
 - Mac client activity
 - bpcd 48
 - inetd 48
 - NT Event Viewer Application 44
 - PC client activity
 - bp 46
 - bparchive 46
 - bpbbackup 47
 - bpbkcar 47
 - bpcd 47
 - bpinetd 46
 - bplist 47
 - bpmount 47
 - bprestore 47

- bpsrv 47
- nbwin 47
- tar 47
 - user_ops 47
- reports, NetBackup 43
- server activity
 - admin 45
 - bpbrm 45
 - bpcd 45
 - bpdjobs 45
 - bpbm 45
 - bpdm 45
 - bprd 45
 - bpsched 45
 - bptm 45
- user progress 44
- logs
 - activity. See debug
 - debug, introduction 44
- Logs directory
 - UNIX client/server 440
- ltid, description 460

M

- mapping files (external) 401, 404
- Master server, test procedure 16, 19
- maximum pathname length 56
- Media Contents report 43
- Media database 450
- Media List report 43
- Media Log Entries report 43
- Media Manager
 - functional description 450
- Media server, test procedure 19
- Media Summary report 43
- Media Written report 43
- message
 - finding message text from status code 55
- Messages, NetBackup 173, 364
- mirror (VxVM snapshot) 61
- mirror frozen image (removing) 64
- misc file 458
- mover.conf file 123
- Multiplexed backups 424
- multiplexing 71

N

- NBNW95 428, 437
- NBNW95.EXE 448
- NBNWNT 428, 437



- NBNWNT.EXE 448
- NBWIN 426, 427, 435, 436
- nbwin log 47
- NBWIN.EXE 448
- ndmpmoveragent, overview 447
- NetBackup Administration Console
 - debug logging 53
 - errors 51
- NetBackup Client service
 - start and stop 9
- NetBackup Database Manager service
 - start and stop 9
- NetBackup Device Manager service
 - start and stop 9
- NetBackup Request Manager service
 - start and stop 9
- NetBackup Volume Manager service
 - start and stop 9
- NetBackupBPCD 429, 438, 448
- NetBackupListen 429, 438, 449
- Network connections, multiple 467
- Network problems
 - PC clients 21
- Novell
 - values affecting restore 73, 74

O

- odld, description 460
- Operating system errors 52
- output, redirect to a file 54

P

- pass-thru not supported 15
- patches (installing during recovery) 401, 404, 407
- pathname length 56
- Preliminary troubleshooting procedure 7
- Problems report 43
- Procedures
 - recovery
 - master when NT intact 399
 - media server disk 405
 - NetBackup catalogs 409
 - NT client disk 406
 - NT master server disk 399
 - total on master 402
 - troubleshooting
 - communications problems 21
 - host names and services 25
 - installation and configuration 10

- introduction 7
 - master server and clients 16
 - media server and clients 19
 - preliminary 7
- Processes (see Functional overview)
- Programs
 - Media Manager 458
 - NetBackup 441
- Progress logs, user 44

R

- Raw partitions
 - backup process 422
 - restore process 432
- Recording information 2
- Recovery procedures
 - importing media 410
 - master when NT intact 399
 - NetBackup catalogs 409
 - NT client disk 406
 - NT master server disk 399
 - server disk 405
 - total on master 402
- RedHat 10
- redirect output to a file 54
- Related manuals x
- Release notes, online copy 440
- removing a frozen image clone 63, 64
- Reports, NetBackup 43
- Restore process 432
 - NetWare client 437
 - Windows 98/95 client 435
 - Windows NT/2000 client 436
- restore type
 - for Backup Exec files 477, 478
- restoring Backup Exec files 478
- robot
 - drive number unknown 14
 - robot limit exceeded 14
 - type not determined 14
 - unknown 14
- Robot drive selection 453
- Robotic control daemons 451
- Robotic daemons 451
- Robotic test utility 471
 - acstest 471
 - RSM robot 471
 - tl4test 472
 - tl8test 472



- tldtest 472
- tlhstest 472
- ts8test 472
- tsdtest 472
- robtest 471
- RSM robot 471
- rsmd, description 461

S

- Scheduler, bpsched 45
- serialization problems 12
- Server
 - disk recovery 405
 - installation problems 10
 - NetBackup debug logs 44
 - NT disk recovery 399
 - recover master, NT intact 399
 - test procedure for master 16, 19
 - test procedure for media server 19
 - total recovery of master 402
- ServerFree Agent
 - pathname length 56
- Services entries, checking 25
- slots, too many 13
- snaplist command 62
- snappoff command 62
- snapshot
 - mirror (VxVM) 61
 - stale 62
- Software version, determining
 - Macintosh clients 72
 - Media Manager 458
 - NetWare nontarget clients 72
 - NetWare target clients 72
 - UNIX client/server 440
 - Windows clients 72
 - Windows NT servers 71
- stale snapshots 62
- Startup
 - Media Manager process 451
 - NetBackup 420
- status code
 - finding message from 55
- Status codes, NetBackup
 - sorted by code 55
 - sorted by message 173, 364
- stderr 51
- stdout 51
- SuSE 10

- symbolic links 60
- SYMINIT failed 64

T

- tape reader (Backup Exec) 473
- tar log 47
- tar, NetBackup 449
- TAR32 436
- Test utility, robotic 471
- third-party copy 123
 - and multiplexing 71
- tl4d, description 461
- tl4test 472
- tl8cd, description 462
- tl8d, description 461
- tl8test 472
- tldd, description 462
- tldtest 472
- tlhcd, description 463
- tlhd, description 463
- tlhstest 472
- tlldcd, description 462
- tlmd, description 463
- tpautoconf 304
- tpcommand 287
- tpconfig, overview 464
- Troubleshooting procedure
 - communication problems
 - PC clients 21
 - general
 - introduction 16
 - master server and clients 16, 19
 - media server and clients 19
 - host name and services entries 25
 - installation 10
 - preliminary 7
- ts8d, description 465
- ts8test 472
- tsdd, description 464
- tsdtest 472
- tshd, description 464

U

- user_ops log 45
- Utility, robotic test 471

V

- vault 56
- Verbose option 46
- VERITAS NetBackup ix



VERITAS Volume Manager 61	Volume database 458
Version, software (see Software version, determining)	vxassist command 61
vlteject 154	vxvm frozen image method 61
vltoffsitemedia 154	vxvol command 61
vltopmenu 154, 155	
vltrun 153, 154	W
vm.conf file 458	Windows Display Console 54
vmadm, overview 465	
vmd	X
overview 465	xbp, overview 449
	xinetd 10



